

PROGRESS[®] ORBIX[®]

CORBA Trader Service Guide, Java

Version 6.3.5, July 2011

© 2011 Progress Software Corporation and/or its subsidiaries or affiliates. All rights reserved.

These materials and all Progress® software products are copyrighted and all rights are reserved by Progress Software Corporation. The information in these materials is subject to change without notice, and Progress Software Corporation assumes no responsibility for any errors that may appear therein. The references in these materials to specific platforms supported are subject to change.

Actional, Apama, Artix, Business Empowerment, Business Making Progress, DataDirect (and design), DataDirect Connect, DataDirect Connect64, DataDirect Technologies, DataDirect XML Converters, DataDirect XQuery, DataXtend, Dynamic Routing Architecture, EdgeXtend, Empowerment Center, Fathom, Fuse Media tion Router, Fuse Message Broker, Fuse Services Framework, IntelliStream, IONA, Making Software Work Together, Mindreef, ObjectStore, OpenEdge, Orbix, PeerDirect, POSSENET, Powered by Progress, PowerTier, Progress, Progress DataXtend, Progress Dynamics, Progress Business Empowerment, Progress Empowerment Center, Progress Empowerment Program, Progress OpenEdge, Progress Profiles, Progress Results, Progress Software Business Making Progress, Progress Software Developers Network, Progress Sonic, ProVision, PS Select, Savvion, SequeLink, Shadow, SOAPscope, SOAPStation, Sonic, Sonic ESB, SonicMQ, Sonic Orchestration Server, SpeedScript, Stylus Studio, Technical Empowerment, WebSpeed, Xcalia (and design), and Your Software, Our Technology-Experience the Connection are registered trademarks of Progress Software Corporation or one of its affiliates or subsidiaries in the U.S. and/or other countries. AccelEvent, Apama Dashboard Studio, Apama Event Manager, Apama Event Modeler, Apama Event Store, Apama Risk Firewall, AppsAlive, AppServer, ASPen, ASP-in-a-Box, BusinessEdge, Cache-Forward, CloudEdge, DataDirect Spy, DataDirect SupportLink, Fuse, FuseSource, Future Proof, GVAC, High Performance Integration, Object Store Inspector, ObjectStore Performance Expert, OpenAccess, Orbacus, Pantero, POSSE, ProDataSet, Progress Arcade, Progress CloudEdge, Progress Control Tower, Progress ESP Event Manager, Progress ESP Event Modeler, Progress Event Engine, Progress RFID, Progress RPM, PSE Pro, SectorAlliance, SeeThinkAct, Shadow z/Services, Shadow z/Direct, Shadow z/Events, Shadow z/Presentation, Shadow Studio, SmartBrowser, SmartComponent, SmartDataBrowser, SmartDataObjects, SmartDataView, SmartDialog, SmartFolder, SmartFrame, SmartObjects, SmartPanel, SmartQuery, SmartViewer, SmartWindow, Sonic Business Integration Suite, Sonic Process Manager, Sonic Collaboration Server, Sonic Continuous Availability Architecture, Sonic Database Service, Sonic Workbench, Sonic XML Server, The Brains Behind BAM, WebClient, and Who Makes Progress are trademarks or service marks of Progress Software Corporation and/or its subsidiaries or affiliates in the U.S. and other countries. Java is a registered trademark of Oracle and/or its affiliates. Any other marks contained herein may be trademarks of their respective owners.

Third Party Acknowledgements:

Progress Orbix v6.3.5 incorporates Jakarata-struts 1.0.2 from the Apache Software Foundation (<http://www.apache.org>). Such Apache Technology is subject to the following terms and conditions: The Apache Software License, Version 1.1 Copyright (c) 1999-2001 The Apache Software Foundation. All rights reserved. Redistribution and use in source and

binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copy right notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. 3. The end-user documentation included with the redistribution, if any, must include the following acknowledgment: "This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>)." Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear. 4. The names "The Jakarta Project", "Struts", and "Apache Software Foundation" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact apache@apache.org. 5. Products derived from this software may not be called "Apache", nor may "Apache" appear in their name, without prior written permission of the Apache Software Foundation. THIS SOFTWARE IS PROVIDED ``AS IS'' AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MER CHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DIS CLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBU TORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEM-PLARY, OR CONSEQUEN TIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCURE-MENT OF SUB STITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIA BILITY, OR TORT (INCLUDING NEGLIGENCE OR OTH-ERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. This software consists of voluntary contributions made by many individuals on behalf of the Apache Soft ware Foun dation. For more information on the Apache Software Foundation, please see <<http://www.apache.org/>>.

Progress Orbix v6.3.5 incorporates Jakarta-bcel 5.0 from the Apache Software Foundation (http://www.apache.org). Such Apache Technology is subject to the following terms and conditions: The Apache Software License, Version 1.1 Copy right (c) 2001 The Apache Software Foundation. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the docu mentation and/or other materials provided with the distribution. 3. The end-user documentation included with the redistribu-tion, if any, must include the following acknowledgment: "This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>)." Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear. 4. The names "Apache" and "Apache Software Foundation" and "Apache BCEL" must not be used to endorse or promote products derived from this software with out prior written permission. For written permission, please contact apache@apache.org. 5. Products derived from this software may not be called "Apache", "Apache BCEL", nor may "Apache" appear in their name, without prior written permission of the Apache Software Foundation. THIS SOFTWARE IS PROVIDED ``AS IS'' AND ANY EXPRESSED OR IMPLIED WAR-RANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTA-BILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES;

LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. This software consists of voluntary contributions made by many individuals on behalf of the Apache Software Foundation. For more information on the Apache Software Foundation, please see <<http://www.apache.org/>>.

Progress Orbix v6.3.5 incorporates Jakarta-regexp 1.2 from the Apache Software Foundation (<http://www.apache.org>). Such Apache Technology is subject to the following terms and conditions: The Apache Software License, Version 1.1 Copyright (c) 1999 The Apache Software Foundation. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. 3. The end-user documentation included with the redistribution, if any, must include the following acknowledgment: "This product includes software developed by the Apache Software Foundation (<http://www.apache.org>)." Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear. 4. The names "The Jakarta Project", "Jakarta -Regexp", and "Apache Software Foundation" and "Apache BCEL" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact apache@apache.org. 5. Products derived from this software may not be called "Apache", nor may "Apache" appear in their name, without prior written permission of the Apache Software Foundation. THIS SOFTWARE IS PROVIDED `AS IS' AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. This software consists of voluntary contributions made by many individuals on behalf of the Apache Software Foundation. For more information on the Apache Software Foundation, please see <<http://www.apache.org/>>.

Progress Orbix v6.3.5 incorporates the Jakarta-log4j 1.2.6 from the Apache Software Foundation (<http://www.apache.org>). Such Apache Technology is subject to the following terms and conditions: The Apache Software License, Version 1.1 Copyright (c) 1999 The Apache Software Foundation. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. 3. The end-user documentation included with the redistribution, if any, must include the following acknowledgment: "This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>)." Alternately, this acknowledgment may appear in

the software itself, if and wherever such third-party acknowledgments normally appear. 4. The names "log4j" and "Apache Software Foundation" and "Apache BCEL" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact apache@apache.org. 5. Products derived from this software may not be called "Apache", nor may "Apache" appear in their name, without prior written permission of the Apache Software Foundation. THIS SOFTWARE IS PROVIDED ``AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. This software consists of voluntary contributions made by many individuals on behalf of the Apache Software Foundation. For more information on the Apache Software Foundation, please see <http://www.apache.org/>.

Progress Orbix v6.3.5 incorporates Ant 1.5 from the Apache Software Foundation (<http://www.apache.org>). Such technology is subject to the following terms and conditions: The Apache Software License, Version 1.1 Copyright (c) 2000-2002 The Apache Software Foundation. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. 3. The end-user documentation included with the redistribution, if any, must include the following acknowledgment: "This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>)." Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear. 4. The names "Ant" and "Apache Software Foundation" and "Apache BCEL" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact apache@apache.org. 5. Products derived from this software may not be called "Apache", nor may "Apache" appear in their name, without prior written permission of the Apache Software Foundation. THIS SOFTWARE IS PROVIDED ``AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. This software consists of voluntary contributions made by many individuals on behalf of the Apache Software Foundation. For more information on the Apache Software Foundation, please see <http://www.apache.org/>.

Progress Orbix v6.3.5 incorporates Xalan-j 2.3.1 from the Apache Software Foundation (<http://www.apache.org>). Such Apache Technology is subject to the following terms and conditions: The Apache Software License, Version 1.1. Copyright (c) 1999 The Apache Software Foundation. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. 3. The end-user documentation included with the redistribution, if any, must include the following acknowledgment: "This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>)." Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear. 4. The names "Xalan" and "Apache Software Foundation" and "Apache BCEL" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact apache@apache.org. 5. Products derived from this software may not be called "Apache", nor may "Apache" appear in their name, without prior written permission of the Apache Software Foundation. THIS SOFTWARE IS PROVIDED ``AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. This software consists of voluntary contributions made by many individuals on behalf of the Apache Software Foundation. For more information on the Apache Software Foundation, please see <http://www.apache.org/>.

Progress Orbix v6.3.5 incorporates the Xerces-c++ 2.4 from the Apache Software Foundation (<http://www.apache.org>). Such Apache Technology is subject to the following terms and conditions: The Apache Software License, Version 1.1. Copyright (c) 1999-2001 The Apache Software Foundation. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. 3. The end-user documentation included with the redistribution, if any, must include the following acknowledgment: "This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>)." Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear. 4. The names "Xerces" and "Apache Software Foundation" and "Apache BCEL" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact apache@apache.org. 5. Products derived from this software may not be called "Apache", nor may "Apache" appear in their name, without prior written permission of the Apache Software Foundation. THIS SOFTWARE IS PROVIDED ``AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE

APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. This software consists of voluntary contributions made by many individuals on behalf of the Apache Software Foundation. For more information on the Apache Software Foundation, please see <<http://www.apache.org/>>.

Progress Orbix v6.3.5 incorporates xerces-j 2.5 from the Apache Software Foundation (<http://www.apache.org>). Such Apache Technology is subject to the following terms and conditions: The Apache Software License, Version 1.1. Copyright (c) 1999-2002 The Apache Software Foundation. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. 3. The end-user documentation included with the redistribution, if any, must include the following acknowledgment: "This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>)." Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear. 4. The names "Xerces" and "Apache Software Foundation" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact apache@apache.org. 5. Products derived from this software may not be called "Apache", nor may "Apache" appear in their name, without prior written permission of the Apache Software Foundation. THIS SOFTWARE IS PROVIDED ``AS IS'' AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. This software consists of voluntary contributions made by many individuals on behalf of the Apache Software Foundation. For more information on the Apache Software Foundation, please see <<http://www.apache.org/>>.

Progress Orbix v6.3.5 incorporates the Tomcat 4.0.4 from the Apache Software Foundation (<http://www.apache.org>). Such Apache Technology is subject to the following terms and conditions: The Apache Software License, Version 1.1. Copyright (c) 1999, 2000 The Apache Software Foundation. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. 3. The end-user documentation included with the

redistribution, if any, must include the following acknowledgment: "This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>)." Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear. 4. The names "The Jakarta Project", "Tomcat" and "Apache Software Foundation" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact apache@apache.org. 5. Products derived from this software may not be called "Apache", nor may "Apache" appear in their name, without prior written permission of the Apache Software Foundation. THIS SOFTWARE IS PROVIDED ``AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. This software consists of voluntary contributions made by many individuals on behalf of the Apache Software Foundation. For more information on the Apache Software Foundation, please see <http://www.apache.org/>.

Progress Orbix v6.3.5 incorporates MCPP 2.6.4 from the MCPP Project. Such technology is subject to the following terms and conditions: Copyright (c) 1998, 2002-2007 Kiyoshi Matsui kmatsui@t3.rim.or.jp All rights reserved. This software including the files in this directory is provided under the following license. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. THIS SOFTWARE IS PROVIDED BY THE AUTHOR ``AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Progress Orbix v6.3.5 incorporates Xalan c++ v1.7 from The Apache Software Foundation. Such technology is subject to the following terms and conditions: The Apache Software License, Version 1.1 Copyright (c) 1999-2004 The Apache Software Foundation. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. 3. The end-user documentation included with the redistribution, if any, must include the follow-

ing acknowledgment: "This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>)." Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear. 4. The names "Xalan" and "Apache Software Foundation" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact apache@apache.org. 5. Products derived from this software may not be called "Apache", nor may "Apache" appear in their name, without prior written permission of the Apache Software Foundation. THIS SOFTWARE IS PROVIDED ``AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

This software consists of voluntary contributions made by many individuals on behalf of the Apache Software Foundation and was originally based on software copyright (c) 1999, Lotus Development Corporation., <http://www.lotus.com>. For more information on the Apache Software Foundation, please see <http://www.apache.org/>.

Progress Orbix v6.3.5 incorporates Tcl 8.4.15 from Regents of the University of California, Sun Microsystems, Inc., Scriptics Corporation, and other parties. Such technology is subject to the following terms and conditions: This software is copyrighted by the Regents of the University of California, Sun Microsystems, Inc., Scriptics Corporation, and other parties. The following terms apply to all files associated with the software unless explicitly disclaimed in individual files. The authors hereby grant permission to use, copy, modify, distribute, and license this software and its documentation for any purpose, provided that existing copyright notices are retained in all copies and that this notice is included verbatim in any distributions. No written agreement, license, or royalty fee is required for any of the authorized uses. Modifications to this software may be copyrighted by their authors and need not follow the licensing terms described here, provided that the new terms are clearly indicated on the first page of each file where they apply. IN NO EVENT SHALL THE AUTHORS OR DISTRIBUTORS BE LIABLE TO ANY PARTY FOR DIRECT, INDIRECT, SPECIAL, INCIDENTAL, OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OF THIS SOFTWARE, ITS DOCUMENTATION, OR ANY DERIVATIVES THEREOF, EVEN IF THE AUTHORS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. THE AUTHORS AND DISTRIBUTORS SPECIFICALLY DISCLAIM ANY WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, AND NON-INFRINGEMENT. THIS SOFTWARE IS PROVIDED ON AN "AS IS" BASIS, AND THE AUTHORS AND DISTRIBUTORS HAVE NO OBLIGATION TO PROVIDE MAINTENANCE, SUPPORT, UPDATES, ENHANCEMENTS, OR MODIFICATIONS. GOVERNMENT USE: If you are acquiring this software on behalf of the U.S. government, the Government shall have only "Restricted Rights" in the software and related documentation as defined in the Federal Acquisition Regulations (FARs) in Clause 52.227.19 (c) (2). If you are acquiring the software on behalf of the Department of Defense, the software shall be classified as "Commercial Computer Software" and the Government shall have only "Restricted Rights" as defined in Clause 252.227-7013 (c) (1) of DFARs. Notwithstanding the

CORBA Trader Service Guide,

foregoing, the authors grant the U.S. Government and others acting in its behalf permission to use and distribute the software in accordance with the terms specified in this license.

Progress Orbix v6.3.5 incorporates bzip2 1.0.2 from Julian Seward. Such Technology is subject to the following terms and conditions: This program, "bzip2" and associated library "libbzip2", are copyright (C) 1996-2002 Julian R Seward. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2.

The origin of this software must not be misrepresented; you must not claim that you wrote the original software. If you use this software in a product, an acknowledgment in the product documentation would be appreciated but is not required. 3. Altered source versions must be plainly marked as such, and must not be misrepresented as being the original software. 4. The name of the author may not be used to endorse or promote products derived from this software without specific prior written permission. THIS SOFTWARE IS PROVIDED BY THE AUTHOR "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. Julian Seward, Cambridge, UK.jseward@acm.org bzip2/libbzip2 version 1.0.2 of 30 December 2001.

Progress Orbix v6.3.5 incorporates zlib 1.2.3 from Jean-loup Gailly and Mark Adler. Such Technology is subject to the following terms and conditions: License /* zlib.h -- interface of the 'zlib' general purpose compression library version 1.2.3, July 18th, 2005 Copyright (C) 1995-2000 Jean-loup Gailly and Mark Adler. This software is provided 'as-is', without any express or implied warranty. In no event will the authors be held liable for any damages arising from the use of this software. Permission is granted to anyone to use this software for any purpose, including commercial applications, and to alter it and redistribute it freely, subject to the following restrictions: 1. The origin of this software must not be misrepresented; you must not claim that you wrote the original software. If you use this software in a product, an acknowledgment in the product documentation would be appreciated but is not required. 2. Altered source versions must be plainly marked as such, and must not be misrepresented as being the original software. 3. This notice may not be removed or altered from any source distribution. Jean-loup Gailly jloup@gzip.org Mark Adler madler@alumni.caltech.edu */

Progress Orbix v6.3.5 incorporates the MinML 1.7 from John Wilson. Such Technology is subject to the following terms and conditions: Copyright (c) 1999, John Wilson (tug@wilson.co.uk). All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: Redistributions of source code must retain the above copyright notice,, this list of conditions and the following disclaimer. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. All advertising materials mentioning features or use of this software must display the following acknowledgement: This product includes software developed by John

Wilson. The name of John Wilson may not be used to endorse or promote products derived from this software without specific prior written permission. THIS SOFTWARE IS PROVIDED BY JOHN WILSON "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL JOHN WILSON BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Progress Orbix v6.3.5 incorporates JDOM vbeta9 from JDOM. Such Technology is subject to the following terms and conditions: LICENSE.txt, v 1.10 2003/04/10 08:36:05 jhunter Exp \$ Copyright (C) 2000-2003 Jason Hunter & Brett McLaughlin. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions, and the following disclaimer. 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions, and the disclaimer that follows these conditions in the documentation and/or other materials provided with the distribution. 3. The name "JDOM" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact <license AT jdom DOT org>. 4. Products derived from this software may not be called "JDOM", nor may "JDOM" appear in their name, without prior written permission from the JDOM Project Management <pm AT jdom DOT org>. In addition, we request (but do not require) that you include in the end-user documentation provided with the redistribution and/or in the software itself an acknowledgement equivalent to the following: "This product includes software developed by the JDOM Project (<http://www.jdom.org/>)." Alternatively, the acknowledgment may be graphical using the logos available at <http://www.jdom.org/images/logos>. THIS SOFTWARE IS PROVIDED "AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE JDOM AUTHORS OR THE PROJECT CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. This software consists of voluntary contributions made by many individuals on behalf of the JDOM Project and was originally created by Jason Hunter <jhunter AT jdom DOT org> and Brett McLaughlin <brett AT jdom DOT org>. For more information on the JDOM Project, please see <<http://www.jdom.org/>>.

Progress Orbix v6.3.5 incorporates OpenSSL 0.9.8i Copyright (c) 1998-2008 The OpenSSL Project Copyright (c) 1995-1998 Eric A. Young, Tim J. Hudson All rights reserved. Such Technology is subject to the following terms and conditions: The OpenSSL toolkit stays under a dual license, i.e. both the conditions of the OpenSSL License and the original SSLeay license apply to the toolkit. See below for the actual license texts. Actually both licenses are BSD-style Open Source licenses. In case of any license issues related to

OpenSSL please contact openssl-core@openssl.org. OpenSSL License - Copyright (c) 1998-2008 The OpenSSL Project. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. 3. All advertising materials mentioning features or use of this software must display the following acknowledgment: "This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit. (<http://www.openssl.org/>)" 4. The names "OpenSSL Toolkit" and "OpenSSL Project" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact openssl-core@openssl.org. 5. Products derived from this software may not be called "OpenSSL" nor may "OpenSSL" appear in their names without prior written permission of the OpenSSL Project. 6. Redistributions of any form whatsoever must retain the following acknowledgment: "This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit (<http://www.openssl.org/>)" THIS SOFTWARE IS PROVIDED BY THE OpenSSL PROJECT ``AS IS'' AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE OpenSSL PROJECT OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. This product includes cryptographic software written by Eric Young (ey@cryptsoft.com). This product includes software written by Tim Hudson (tjh@cryptsoft.com). - Original SSLeay License - Copyright (C) 1995-1998 Eric Young (ey@cryptsoft.com) All rights reserved. This package is an SSL implementation written by Eric Young (ey@cryptsoft.com). The implementation was written so as to conform with Netscapes SSL. This library is free for commercial and non-commercial use as long as the following conditions are adhered to. The following conditions apply to all code found in this distribution, be it the RC4, RSA, lhash, DES, etc., code; not just the SSL code. The SSL documentation included with this distribution is covered by the same copyright terms except that the holder is Tim Hudson (tjh@cryptsoft.com). Copyright remains Eric Young's, and as such any Copyright notices in the code are not to be removed. If this package is used in a product, Eric Young should be given attribution as the author of the parts of the library used. This can be in the form of a textual message at program startup or in documentation (online or textual) provided with the package. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the copyright notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. 3. All advertising materials mentioning features or use of this software must display the following acknowledgment: "This product includes cryptographic software written by Eric Young (ey@cryptsoft.com)" The word 'cryptographic' can be left out if the routines from the library being used are not cryptographic related :-). 4. If you include any Windows specific code (or a derivative thereof) from the apps directory (application code) you must include an acknowledgement: "This product includes software written by Tim Hudson (tjh@cryptsoft.com)" THIS SOFTWARE IS PROVIDED BY ERIC YOUNG ``AS IS'' AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF

MERCHANT ABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. The licence and distribution terms for any publically available version or derivative of this code cannot be changed. i.e. this code cannot simply be copied and put under another distribution licence [including the GNU Public Licence.]

Progress Orbix v6.3.5 incorporates PCRE v7.8 from the PCRE Project. Such Technology is subject to the following terms and conditions:

PCRE LICENCE

PCRE is a library of functions to support regular expressions whose syntax and semantics are as close as possible to those of the Perl 5 language. Release 7 of PCRE is distributed under the terms of the "BSD" licence, as specified below. The documentation for PCRE, supplied in the "doc" directory, is distributed under the same terms as the software itself. The basic library functions are written in C and are free-standing. Also included in the distribution is a set of C++ wrapper functions.

THE BASIC LIBRARY FUNCTIONS

Written by: Philip Hazel
Email local part: ph10
Email domain: cam.ac.uk
University of Cambridge Computing Service,
Cambridge, England.
Copyright (c) 1997-2008 University of Cambridge
All rights reserved.

THE C++ WRAPPER FUNCTIONS

Contributed by: Google Inc.
Copyright (c) 2007-2008, Google Inc.
All rights reserved.

THE "BSD" LICENCE

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. Neither the name of the University of Cambridge nor the name of

Google Inc. nor the names of their contributors may be used to endorse or promote products derived from this software without specific prior written permission. THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Progress Orbix v6.3.5 incorporates IDL Compiler Front End 1 from Sun Microsystems, Inc. Copyright 1992, 1993, 1994 Sun Microsystems, Inc. Printed in the United States of America. All Rights Reserved. Such technology is subject to the following terms and conditions: This product is protected by copyright and distributed under the following license restricting its use. The Interface Definition Language Compiler Front End (CFE) is made available for your use provided that you include this license and copyright notice on all media and documentation and the software program in which this product is incorporated in whole or part. You may copy and extend functionality (but may not remove functionality) of the Interface Definition Language CFE without charge, but you are not authorized to license or distribute it to anyone else except as part of a product or program developed by you or with the express written consent of Sun Microsystems, Inc. ("Sun"). The names of Sun Microsystems, Inc. and any of its subsidiaries or affiliates may not be used in advertising or publicity pertaining to distribution of Interface Definition Language CFE as permitted herein. This license is effective until terminated by Sun for failure to comply with this license. Upon termination, you shall destroy or return all code and documentation for the Interface Definition Language CFE. INTERFACE DEFINITION LANGUAGE CFE IS PROVIDED AS IS WITH NO WARRANTIES OF ANY KIND INCLUDING THE WARRANTIES OF DESIGN, MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, NONINFRINGEMENT, OR ARISING FROM A COURSE OF DEALING, USAGE OR TRADE PRACTICE. INTERFACE DEFINITION LANGUAGE CFE IS PROVIDED WITH NO SUPPORT AND WITHOUT ANY OBLIGATION ON THE PART OF Sun OR ANY OF ITS SUBSIDIARIES OR AFFILIATES TO ASSIST IN ITS USE, CORRECTION, MODIFICATION OR ENHANCEMENT. SUN OR ANY OF ITS SUBSIDIARIES OR AFFILIATES SHALL HAVE NO LIABILITY WITH RESPECT TO THE INFRINGEMENT OF COPYRIGHTS, TRADE SECRETS OR ANY PATENTS BY INTERFACE DEFINITION LANGUAGE CFE OR ANY PART THEREOF. IN NO EVENT WILL SUN OR ANY OF ITS SUBSIDIARIES OR AFFILIATES BE LIABLE FOR ANY LOST REVENUE OR PROFITS OR OTHER SPECIAL, INDIRECT AND CONSEQUENTIAL DAMAGES, EVEN IF SUN HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.227-7013 and FAR 52.227-19. Sun, Sun Microsystems and the Sun logo are trademarks or registered trademarks of Sun Microsystems, Inc. Sun-Soft, Inc. 2550 Garcia Avenue, Mountain View, California 94043 NOTE: SunOS, Sun Soft, Sun, Solaris, Sun Microsystems or the Sun logo are trademarks or registered trademarks of Sun Microsystems, Inc.

Progress Orbix v6.3.5 incorporates LibXML2 2.4.24 from Daniel Veillard. Such Technology is subject to the following terms and conditions: Except where otherwise noted in the source code (trio files, hash.c and

list.c) covered by a similar license but with different Copyright notices: Copyright (C) 1998-2002 Daniel Veillard. All Rights Reserved. Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including with out limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions: The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software. THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE DANIEL VEILLARD BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE. Except as contained in this notice, the name of Daniel Veillard shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Software without prior written authorization from him.

==== trio.c, trio.h: Copyright (C) 1998 Bjorn Reese and Daniel Stenberg. Permission to use, copy, modify, and distribute this software for any purpose with or without fee is hereby granted, provided that the above copyright notice and this permission notice appear in all copies. THIS SOFTWARE IS PROVIDED "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE AUTHORS AND CONTRIBUTORS ACCEPT NO RESPONSIBILITY IN ANY CONCEIVABLE MANNER. ===== triop.h: Copyright (C) 2000 Bjorn Reese and Daniel Stenberg. Permission to use, copy, modify, and distribute this software for any purpose with or without

fee is hereby granted, provided that the above copyright notice and this permission notice appear in all copies. THIS SOFTWARE IS PROVIDED "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE AUTHORS AND CONTRIBUTORS ACCEPT NO RESPONSIBILITY IN ANY CONCEIVABLE MANNER.

===== hash.c: Copyright (C) 2000 Bjorn Reese and Daniel Veillard. Permission to use, copy, modify, and distribute this software for any purpose with or without fee is hereby granted, provided that the above copyright notice and this permission notice appear in all copies. THIS SOFTWARE IS PROVIDED "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE AUTHORS AND CONTRIBUTORS ACCEPT NO RESPONSIBILITY IN ANY CONCEIVABLE MANNER.

===== list.c: Copyright (C) 2000 Gary Pennington and Daniel Veillard. Permission to use, copy, modify, and distribute this software for any purpose with or without fee is hereby granted, provided that the above copyright notice and this permission notice appear in all copies. THIS SOFTWARE IS PROVIDED "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE AUTHORS AND CONTRIBUTORS ACCEPT NO RESPONSIBILITY IN ANY CONCEIVABLE MANNER. =====

triodef.h, trionan.c, trionan.h: Copyright (C) 2001 Bjorn Reese Permission to use, copy, modify, and distribute this software for any purpose with or without fee is hereby granted, provided that the above copyright notice and this permission notice appear in all copies. THIS SOFTWARE IS PROVIDED "AS IS" AND

CORBA Trader Service Guide,

WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE AUTHORS AND CONTRIBUTORS ACCEPT NO RESPONSIBILITY IN ANY CONCEIVABLE MANNER.

==== triostr.c, triostr.h: Copyright (C) 2001 Bjorn Reese and Daniel Stenberg.

Permission to use, copy, modify, and distribute this software for any purpose with or without fee is hereby granted, provided that the above copyright notice and this permission notice appear in all copies. THIS SOFTWARE IS PROVIDED "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE AUTHORS AND CONTRIBUTORS ACCEPT NO RESPONSIBILITY IN ANY CONCEIVABLE MANNER.

Progress Orbix v6.3.5 incorporates ICU library 2.6 from IBM. Such Technology is subject to the following terms and conditions: Copyright (c) 1995-2009 International Business Machines Corporation and others. All rights reserved. Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, provided that the above copyright notice(s) and this permission notice appear in all copies of the Software and that both the above copyright notice(s) and this permission notice appear in supporting documentation. THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OF THIRD PARTY RIGHTS. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR HOLDERS INCLUDED IN THIS NOTICE BE LIABLE FOR ANY CLAIM, OR ANY SPECIAL INDIRECT OR CONSEQUENTIAL DAMAGES, OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE. Except as contained in this notice, the name of a copyright holder shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Software without prior written authorization of the copyright holder. All trademarks and registered trademarks mentioned herein are the property of their respective owners.

Updated: 13-Jul-2011

Contents

List of Figures	xxi
List of Tables	xxiii
Preface	xxv
Chapter 1 An Introduction to the CORBA Trading Service	1
Introduction	2
Service Types	4
Service Offers	8
The Trader Service's Components	9
Chapter 2 Configuring the Trader Service	11
Configuring and Running the Trader Service	12
Steps 1-2: Determine the hosts and ports to be used in the deployment	13
Step 3: Enter the host and port information in the configuration	14
Step 4: Configure the trader service to run in replicated or non-replicated mode	16
Step 5: Run the service in prepare mode to obtain initial references	17
Step 6: Adding the initial references to the configuration	18
Step 7: Running the trader service	19
Additional Configuration Information	20
Chapter 3 Getting Started with the Trader Service	21
Starting the Trader Service	22
The Printer Application	23
Trader Service Programming	25
Connecting to the Trader	26
Adding a New Service Offer Type	27
Exporting a Service Offer	29
Querying for a Service Offer	31
Chapter 4 Querying for Service Offers	33

How the Trader Service Processes a Query	34
A Basic Query for Service Offers	36
Selecting a Service from Query Results	39
Forming Constraints for Queries	41
Setting Preferences to Sort Service Offers	44
Refining the Properties a Query Returns	46
Chapter 5 Understanding Trader Service Policies	49
Overview	50
Policies that Affect Queries	51
Policies that Affect Trader Functionality	54
Using Policies in a Query	55
Setting a Trader's Global Policies	57
Chapter 6 Exporting and Managing Service Offers	59
Overview	60
Initializing Service Offer Properties	61
Exporting a Service Offer to Trader	63
Getting Service Offer Data from Trader	65
Modifying a Service Offer	66
Withdrawing a Service Offer from Trader	68
Chapter 7 Programming Topics	69
Managing the Service Type Repository	70
Using Dynamic Property Values	74
Managing Links Between Traders	78
Chapter 8 Trader Service Console	81
Starting the Trader Console	83
Main Window	84
The Trader Console Menus	86
Managing Service Types	89
Managing Offers	93
Managing Proxy Offers	98
Managing Links	100
Configuring the Trader Attributes	102
Support Attributes	103
Import Attributes	104

Link Attributes	106
Admin Attributes	107
Executing Queries	108
Connecting to a New Trader	111
Appendix A The OMG Constraint Language	113
Introduction	114
Language Basics	115
The Constraint Language BNF	118
Glossary	121
Index	127

CONTENTS

List of Figures

Figure 1: Typical trading service process	2
Figure 2: Property Mode Strengths	6
Figure 3: Typical Interactions with the trader	23
Figure 4: How Query Parameters Affect Offers Gathered	34
Figure 5: The Trader Console main window	84

LIST OF FIGURES

List of Tables

Table 1: Kinds of traders and their components	9
Table 2: Query policies and Trader Service policies	52
Table 3: Policies You Can Set for a Query	56
Table 4: Trader policies	57

LIST OF TABLES

Preface

CORBA Trader Service is a Java implementation of the Object Management Group (OMG) Trading Service. The CORBA Trader Service provides facilities for object location and discovery. Unlike the CORBA Naming Service where an object is located by name, an object in the Trading Service does not have a name. Rather, a server advertises an object in the Trading Service based on the kind of service provided by the object. A client locates objects of interest by asking the Trading Service to find all objects that provide a particular service. The client can further restrict the search to select only those objects with particular characteristics.

The Trader Service is compliant with the OMG CORBA services: Common Object Services Specification (<ftp://www.omg.org/pub/docs/formal/98-12-09.pdf>) and conforms to the specification's definition of a *full-service trader*, meaning that the service supports all of the functionality described in the specification.

Audience

This manual is aimed at users wanting to create a trader service for use by their applications.

Related documentation

The document set for Orbix includes the following:

- *CORBA Programmer's Guide*
- *Administrator's Guide*
- *CORBA Programmer's Reference*

The latest updates to the Orbix documentation can be found at <http://www.iona.com/support/docs>.

Additional resources

The [IONA knowledge base](http://www.iona.com/support/knowledge_base/index.xml) (http://www.iona.com/support/knowledge_base/index.xml) contains helpful articles, written by IONA experts, about the Orbix and other products. You can access the knowledge base at the following location:

The [IONA update center](http://www.iona.com/support/updates/index.xml) (<http://www.iona.com/support/updates/index.xml>) contains the latest releases and patches for IONA products:

If you need help with this or any other IONA products, contact IONA at support@iona.com. Comments on IONA documentation can be sent to docs-support@iona.com.

Typographical conventions

This guide uses the following typographical conventions:

Constant width Constant width (courier font) in normal text represents portions of code and literal names of items such as classes, functions, variables, and data structures. For example, text might refer to the `CORBA: :Object` class.

Constant width paragraphs represent code examples or information a system displays on the screen. For example:

```
#include <stdio.h>
```

Italic Italic words in normal text represent *emphasis* and *new terms*.

Italic words or characters in code and commands represent variable values you must supply, such as arguments to commands or path names for your particular system. For example:

```
% cd /users/your_name
```

Note: Some command examples may use angle brackets to represent variable values you must supply. This is an older convention that is replaced with *italic* words or characters.

Keying conventions

This guide may use the following keying conventions:

No prompt When a command's format is the same for multiple platforms, a prompt is not used.

%	A percent sign represents the UNIX command shell prompt for a command that does not require root privileges.
#	A number sign represents the UNIX command shell prompt for a command that requires root privileges.
>	The notation > represents the DOS or Windows command prompt.
...	Horizontal or vertical ellipses in format and syntax descriptions indicate that material has been eliminated to simplify a discussion.
·	
·	
·	
[]	Brackets enclose optional items in format and syntax descriptions.
{ }	Braces enclose a list from which you must choose an item in format and syntax descriptions.
	A vertical bar separates items in a list of choices enclosed in { } (braces) in format and syntax descriptions.

PREFACE

An Introduction to the CORBA Trading Service

The Trader Service is a full implementation of the CORBA Trading Object Service. With this service, servers can offer functionality by making a number of objects publicly available. Clients can then get references to objects that match a specified functionality.

In this chapter

The following topics are discussed in this chapter:

Introduction	page 2
Service Types	page 4
Service Offers	page 8
The Trader Service's Components	page 9

Introduction

Overview

The CORBA Trader Service is a Trading Object Service that allows an object to be registered with a description of its functionality. This service greatly increases the scalability of distributed systems by making services easier to locate. An example of a service that a client might search for is a printer.

How clients and servers use a trader

A trader contains a number of *service types* that describe a service. For example, a printer service type might have properties such as `pages_per_minute` (a long) and `location` (a string). Service types are stored in a *Service Type Repository*. *Service offers*, or *offers*, are instances of these service types.




Figure 1: Typical trading service process

A server can export an offer to the trader, which includes an object reference for one of its objects and values for properties defined by the service type, for example, “50 pages per minute, located on the first floor”.

A client can then query the trading service based on these properties using a filter called a *constraint*. For example, a client could search for a printer where “`pages_per_minute > 200`”. The trader then returns to the client an offer of a service. The client can then use the object reference in the offer to invoke on the server.

Scalability

The trader can be a tool for constructing efficient distributed applications. The advantage of annotating a service offer with properties, and allowing offers to be filtered on the basis of those properties using a constraint, is that clients can select offers without having to incur the overhead of invoking operations on each object.

For example, suppose that `Printer2Interface`, which is a subclass of `PrinterInterface`, has an additional operation, `cost()`, which returned a value of type `float`:

```
//IDL
interface Printer2Interface : PrinterInterface {
    void page_counter();
    float cost();
};
```

In this situation, if the importer needed to select only those printers whose `cost` is within a certain range, the importer would need to iterate over each printer returned by the trading service to invoke the `cost()` operation. In a distributed environment, the overhead of this activity could be prohibitively expensive. It is the developer's responsibility to anticipate the types of queries that importers will need to perform and design their service types accordingly.

Service Types

Service type definition

Service types are general descriptions of a kind of service. They consist of the following:

- A *type name* (for example, *printer*) uniquely identifies the service type.
- An *interface type* defines the IDL interface to which an advertised object of this type must conform (for example, "IDL:MyAppModule/MyAppInterface:1.0").
- A collection of *property types* defines additional attributes of the service offer (for example, "*long page_per_min*", "*string location*").

Service type names

Each service type in the repository has a unique name. Orbix Trader supports two name formats:

- **Scoped names** - These names have formats such as `::One::Two`. Other supported variations include `Three::Four` and simply `Five`.
- **Interface repository identifiers** - These names adhere to the format of interface repository identifiers. The most common format is

```
IDL: [prefix/] [Module/] Interface:X.Y
```

Note: Although both naming formats follow interface repository conventions, service type names are never used to look up information in the interface repository.

Interface types

An *interface type* describes the IDL signature of the advertised service. The interface type is a string whose format should be a scoped name or an interface repository identifier as described above for service type names. When a new service is exported, the trader may use the interface repository to confirm that the object being advertised *conforms* to the interface defined by the interface type. An object conforms to an interface if it implements that interface, or if it implements a subclass of that interface.

Property types

A service type can have zero or more *property types*, representing additional information that can be associated with an advertised service.

A property type definition consists of a name, a value type and a mode. The value type is a `CORBA::TypeCode`, and the mode indicates whether a property is mandatory and whether it is read-only.

The property modes have the following semantics:

- **Mandatory**—The exporter must provide a value for the property at the time the service is exported. Mandatory properties cannot be removed.
- **Read-only**—Once an exporter has supplied a value for the property, it cannot be modified. Read-only properties can be removed.
- **Mandatory and Read-only**—The property must have a value when the service is exported, and cannot subsequently be changed or removed.

A property that is neither mandatory nor read-only is considered optional, and can be changed and removed.

Orbix Trader accepts Java-style identifiers as property names, meaning a property name must start with a letter, and may consist of letters, numbers and underscores.

Super types

Service types can *inherit* from other service types, which enables the definition of *super types* that encapsulate behavior and characteristics common to many service types. When a new service type is created that has super types, the trader checks that several prerequisites are met:

1. All super types must already exist in the service type repository.
2. Any property type definitions in the new service type that have the same name as a definition in a super type must be compatible with the super type definition. For two property definitions to be compatible, their value types

must match, and the mode of the new definition must be the same as, or stronger than, the mode of the property in the super type according to the graph in Figure 2.




Figure 2: *Property Mode Strengths*

3. The interface type of the new service type must conform to the interface type of all super types. Orbix Trader may use the interface repository to verify that this is true.

For example, consider two IDL interfaces, `InterfaceA` and `InterfaceB`, defined below:

```
// IDL
interface InterfaceA {
    void do_something();
};

interface InterfaceB : InterfaceA {
    void do_something_else();
};
```

Here, `InterfaceB` inherits from `InterfaceA`. Now, let's define two service types:

```
service ServiceTypeA
{
  interface InterfaceA;
  property string name;
};

service ServiceTypeB : ServiceTypeA
{
  interface InterfaceB;
  mandatory property string name;
  readonly property float cost;
};
```

In the example above, `ServiceTypeB` inherits from `ServiceTypeA`. As such, it inherits all of the property types from `ServiceTypeA`, and declares an interface type of `InterfaceB`, which conforms to the interface type of its super type because `InterfaceB` is a subclass of `InterfaceA`.

Notice that `ServiceTypeB` redefines the mode of the “name” property. Whereas the definition in `ServiceTypeA` does not specify a mode (making the property optional), the definition in `ServiceTypeB` makes this property mandatory, therefore a value for the property must be supplied when the offer is exported. The reverse is not allowed; a subtype cannot redefine a mandatory property to be optional.

`ServiceTypeB` also adds a new property, “cost”, which is defined to be read-only. Because the property is not mandatory, an exporter does not need to supply a value for it at the time a service offer is exported. However, once a value has been defined for this property, it cannot subsequently be changed.

Service Offers

Service offers

A *service offer* is an instance of a service type and represents the advertisement of a service by a service provider.

A service offer has the following characteristics:

- A *service type name* associates the offer with a particular service type.
- An *object reference* provides the “pointer” (the object reference) to the advertised object that is necessary for clients to invoke the service being offered.
- A set of *properties* describe this service offer and must conform to the property types defined by the service type.

The trader uses the definition of the specified service type to perform several validation steps on a new offer:

1. The exporter must provide values for all mandatory properties (including all mandatory properties that the service type inherits from its super types, if any).
2. The object must conform to the interface type defined by the service type. Orbix Trader may use the interface repository to verify that this is true.
3. The value types of all properties must match the value types as defined by the service type. For example, a value of type `double` is not allowed for a property whose type is defined as `string` in the service type.

Note: Orbix Trader allows an exporter to supply values for named properties that are not defined in the service type.

The value of a property in a service offer can be modified if the mode of the property is not read-only. A property can be removed from a service offer if the property is not mandatory. New properties can also be added to an existing service offer.

The Trader Service's Components

Trader components

The Trader Service functionality is divided into components where each component has an associated interface as follows:

- Lookup
- Register
- Admin
- Link
- Proxy

The CORBA Trader Service is a full-service implementation of the OMG's Trading Object Service specification. The following table summarizes the different kinds of traders and the component functionality offered:

Table 1: *Kinds of traders and their components*

Kind of Trader	Component Interfaces				
	Lookup	Register	Admin	Link	Proxy
Full-Service	CORBA Trader Service				
Linked	X	X	X	X	
Proxy	X	X	X		X
Stand-alone	X	X	X		
Simple	X	X			
Query	X				

The functionality of each kind of trader depends on the interfaces that it supports. The following is a list of the kinds of traders specified by the OMG:

- The simplest trader is the *Query trader*, which just supports the `Lookup` interface. This could be useful, for example, where a trader is pre-loaded and optimized for searching.
- The *simple trader* supports not only the `Lookup` interface but it also supports exporting of offers with the `Register` interface.

- The *stand-alone trader* supports the interfaces of a simple trader and additionally supports administration of the trader's configuration settings using the `Admin` interface.
- The *proxy trader* supports the interfaces of a stand-alone trader and additionally supports the `Proxy` interface. The proxy trader essentially exports a *lookup* interface for delayed evaluation of offers, and can be used for encapsulating legacy applications, or as a kind of service offer factory.
- The *linked trader* supports the interfaces of a stand-alone trader and additionally supports federation of traders using the `Link` interface.
- The *full-service trader* combines the functionality of all component interfaces. The Orbix CORBA Trader Service is a full-service trader.

Configuring the Trader Service

This chapter provides a description of the steps necessary to configure the Trader Service.

In this chapter

This chapter contains the following sections:

Configuring and Running the Trader Service	page 12
Additional Configuration Information	page 20

Configuring and Running the Trader Service

Introduction

These instructions describe how to configure the Trader Service.

Preparatory steps

Several preparatory steps are necessary to configure and run the trader service. The specific actions taken at each step are somewhat different depending on whether you want to run the service replicated or non-replicated.

The general sequence of actions are as follows:

1. Determine on which hosts you want to run the master trader service and on which hosts any slaves will run.
 2. Determine the port number on which the master, slaves, and Replicators will listen.
 3. Enter the host and port number information into the configuration.
 4. Configure the trader service to run in replicated or non-replicated mode.
 5. Run the trader service in “prepare” mode to obtain initial references needed to enable clients to interact with the service.
 6. Add each of the references obtained during step 4 to the configuration database.
 7. Start the master trader service and any slaves.
-

Explanation

In the following explanation of the steps listed above, example settings are given assuming a deployment of one master trader service instance running on host “master”, and one slave trader service instance running on host “slave”. In addition, it will be pointed out where steps should be modified or bypassed in order to run a single non-replicated instance of the service.

Steps 1-2: Determine the hosts and ports to be used in the deployment

These steps are completely deployment-specific. Depending on the number of trader service instances you want to deploy, you will need to select 1 or more distinct host/port pairs for each instance of the service to use as a communication end-point. In our example, we use a replicated service with one master and one slave. The master runs on host `master` and listens on port 15001; the slave runs on host `slave` and listens on port 15001. The master and slave need not listen on the same port number. Also, two or more replicas may run on the same host as long as they listen on different ports.

Furthermore, each trader service instance running in a replicated deployment scenario will also create a *Replicator* object. You must also select the ports on which each Replicator will listen. In the sample configuration, the Replicator always listens on port 15002.

Step 3: Enter the host and port information in the configuration

The Trader Service configuration will contain variables set in a global scope (the outer scope not contained within a named block), and variables set in one or more named scopes. The global scope specifies configuration variable settings for all replicas in a replicated deployment, while the named scopes each specify configuration variable settings that apply to a specific trader service instance. The name of each scope corresponds to the ORB name that will be used when launching each instance of the service.

In the default `trader.cfg` included with the trader service package, there are two named scopes: one for ORB name `trading0`, and the other for ORB name `trading1`. All host/port information is set within a named configuration scope. The host/port information within a given configuration scope is contained in the following variables:

```
trader:iiop:addr_list
replication:Replicator:iiop:addr_list
```

In the sample configuration, these variables are set as follows in the `trading0` scope:

```
trader:iiop:addr_list = ["master:15001", "+slave:15001"];
replication:Replicator:iiop:addr_list = ["master:15002"];
```

These settings indicate that the trader service instance using ORB name `trading0` will run on host `master` and listen on port 15001. The service will be replicated, with the one replica participating in the service running on host `slave` and listening on port 15001. The Replicator will listen on port 15002.

Note that if more replicas are being used in the deployment, an additional `"<hostname>:<port>"` pair would be appended to the list for each replica. If running the service non-replicated, only a single `"<hostname>:<port>"` pair should be included in the `trader:iiop:addr_list`. Including additional pairs in the list will only increase the size of IORs used by the service, but this will result in unnecessary resource consumption when running non-replicated. In addition, in the non-replicated case, the second `addr_list` variable listed above need not be set.

In the sample configuration, these same variables are set as follows in the `trading1` configuration scope:

```
trader:iiop:addr_list = ["slave:15001", "+master:15001"];  
replication:Replicator:iiop:addr_list = ["slave:15002"];
```

These settings indicate that the trader service instance run with ORB name `trading1` will run on host `slave` and listen on port 15001. The service will be replicated, and the one other replica will run on host `master` and also listen on port 15001. The Replicator used by this service instance will listen on port 15002.

Step 4: Configure the trader service to run in replicated or non-replicated mode

Before running the trader service in “prepare” mode, you should decide if you want to run with replication enabled or disabled, and if replication is enabled how many replicas will be used.

Whether replication is enabled or disabled is controlled by the setting of the configuration variable `replication:enable`. This variable should be set to `"True"` to enable replication, and to `"False"` to disable replication.

If running with replication enabled, you must also indicate the number of replicas that will be used by setting the `replication:replica_count` to the appropriate value. This variable should be set to the total number of replicas including the master and any slaves. In the example scenario with one master trader service instance and one slave, this variable should be set to 2.

Step 5: Run the service in prepare mode to obtain initial references

Now you are ready to run the service in prepare mode, and obtain the initial references necessary for clients to connect to the service. Note that when running a replicated service, each individual replica must be prepared. The command to run the trader service in prepare mode is:

```
asp/Version/bin/ittrader prepare [-publish_to_file <filename>]
```

If running with replication enabled, preparing each instance of the trader service will result in three IORs being sent to standard output:

- The IOR of the replicated trader service (which will be the same for all replicas)
- The non-replicated, per-instance trader service IOR
- The IOR of the per-trader service Replicator.

If running with replication disabled only the IOR of the prepared trader service instance will be output.

Save the values for use in step 5.

Step 6: Adding the initial references to the configuration

The initial references of each trader service instance and each Replicator need to be added to the configuration.

If running one non-replicated instance of the service, the initial reference to the service returned by preparing the one instance should be set as the value of the following variable in the global configuration scope:

```
initial_references:TradingService:reference
```

If running with replication enabled, the IOR of the *replicated* trader service should be set as the value of the trader service initial reference in the global scope (the same variable as described above for the non-replicated case).

If replication is enabled, or if running multiple non-replicated instances of the service within the same domain, the trader service initial reference variable within each named scope must also be set. If replication is enabled, the value set for the following variable within each named scope should be the non-replicated, per-instance trader service IOR:

```
initial_references:TradingService:reference
```

In addition, the non-replicated IOR of each trader service instance, along with the Replicator IOR for each instance, should be added to the configuration as the values of the variables of the form:

```
replication:replica:<replica id>:TradingService:reference  
replication:replica:<replica id>:Replicator:reference
```

In the current example, the IORs returned by preparing the master replica are set as the values of the following variables:

```
replication:replica:0:TradingService:reference  
replication:replica:0:Replicator:reference
```

while the IORs returned by preparing the slave replica are set as the values of these variables:

```
replication:replica:1:TradingService:reference  
replication:replica:1:TradingService:reference
```

Step 7: Running the trader service

Run itrader

Additional Configuration Information

There are a couple of additional configuration settings to be aware of:

trader:database:dir="/traderdb0";

This variable should be modified to contain the pathname (absolute or relative to where the trader is launched from) of where the trader database will reside for each replica of the service.

replication:replica_id = "0";

This is a numeric ID for the instance of the trader being configured in the current scope.

Each replica should have a unique `replica_id`. If a replica's `replication:replica_id` is the same value as `replication:master` then it is the master replica.

direct_persistence

This variable specifies if the service runs using direct or indirect persistence. the default value is `FALSE`, meaning indirect persistence.

iiop:port

This variable specifies the port that the service listens on when running using direct persistence.

Getting Started with the Trader Service

This chapter shows an example of a simple printer service to illustrate most of the common functionality in the Trader Service. A printer server makes a printer available for general use. Then, a client application asks the Trader Service for a suitable printer, and uses it to print a document.

In this chapter

This chapter contains the following sections:

Starting the Trader Service	page 22
The Printer Application	page 23
Trader Service Programming	page 25

Starting the Trader Service

Starting the Trader Service

To start the trader, enter the following command.

```
ittrader run
```

Synopsis

```
ittrader [-launcher_help]
         [-ORBconfig_dir config_dir_value]
         [-ORBconfig_domains_dir config_domains_dir_value]
         [-ORBdomain_name domain_name_value]
         [-ORBproduct_dir product_dir_value]
         [-ORBlicense_file license_file]
         [-bg | -background]
         [-show_java_command]
         [-version]
         [run | prepare [publish_to_file = filename]]
```

Stopping the Trader Service

```
itadmin trd_admin stop
```

The Printer Application

Overview

The print server creates a Printer service type, and exports the descriptions of several printers to the trader. A client allows the user to execute queries and “print” files.

Interaction with the trader

Figure 3 shows the typical interactions clients and servers have with the trader:




Figure 3: *Typical Interactions with the trader*

1. An offer server adds a service type (`Printer`) to the trader. The `Printer` type describes properties that office printers have, such as pages per minute. The service type names differ from the IDL interface names in this example, mainly to make their use clearer. For example, there could also be a `book_printer` service type that uses the `PrintServer` IDL interface, but it could have quite different properties such as options for hard or soft book binding.
2. The printer server creates a `printer_if` object. It exports and object reference to this object to the Trader Service as an *offer* of type `Printer`. It then waits for incoming requests, as normal.

3. The client process queries the Trader Service for a `Printer` offer.
 4. The client process then uses the object reference in the offer obtained to invoke the printer server.
-

The IDL specification

The example application uses the following `PrintServer` IDL interface to describe the interface to a printer object:

```
// IDL
// This interface represents a print server that manages queues
// for several printers.
//
module TraderDemo
{
    interface PrintServer
    {
        typedef unsigned long JobID;

        // Add a file to a printer's queue.
        //
        JobID print (in string queue, in string file);
    };
};
```

Trader Service Programming

This section outlines the three major programming steps used to interact with the trader. These steps are:

1. Add a service type using the offer server:
 - i. Create a service offer type if a corresponding one doesn't already exist within the Trader Service. This example creates an `Printer` service offer type.
2. Register a service offer using the printer server:
 - i. Create an object, for example, an instance of the IDL interface `PrintServer`.
 - ii. Register the object reference with the Trader Service, within a service offer of type `Printer`. The server then accepts incoming object invocations as normal.
3. Get a service offer using the client:
 - i. Query the Trader Service to get back a service offer.
 - ii. Use the object reference specified in the service offer to invoke the object on the server.

Note that for simplicity, exception handling is omitted in the sample code.

Connecting to the Trader

Servers need to connect to the trader to add a service offer type, for example, or to register a service offer. Clients need to connect to query the trader for service offers. The trader has a number of components represented by IDL interfaces including `Lookup`, `Register`, and others. The "TradingService" initial reference is a reference to the `CosTrading::Lookup` interface.

Do the following steps to get an object reference to the Trader Service:

```
1 org.omg.CORBA.Object obj =  
  orb.resolve_initial_references("TradingService");  
2 if(obj != null)  
  {  
    org.omg.CosTrading.Lookup trader =  
      org.omg.CosTrading.LookupHelper.narrow(obj);  
  }
```

1. Call `resolve_initial_references()` which returns a `org.omg.CORBA.Object`.
2. Narrow the object reference.

Adding a New Service Offer Type

An offer server inserts a service offer type called `printer` into the Trader Service. This is essentially a type declaration of an offer. Other servers may then use this type to register `printer` objects by creating instances of this type. Operations on service offer types are handled by the Service Offer Type Repository component of the Trader Service.

Do the following steps to add an offer type to the Offer Type Repository:

```
1 org.omg.CORBA.Object obj = trader.type_repos();
2 org.omg.CosTradingRepos.ServiceTypeRepository trader_repos_obj =
  org.omg.CosTradingRepos.ServiceTypeRepositoryHelper.narrow(obj);
3 org.omg.CosTradingRepos.ServiceTypeRepository.PropStruct[] props =
  new org.omg.CosTradingRepos.ServiceTypeRepository.PropStruct[3];

props[0] = new
  org.omg.CosTradingRepos.ServiceTypeRepository.PropStruct();
props[0].name = "name";
props[0].value_type =
  orb.get_primitive_tc(org.omg.CORBA.TCKind.tk_string);
props[0].mode = PropertyMode.PROP_MANDATORY_READONLY;

props[1] = new
  org.omg.CosTradingRepos.ServiceTypeRepository.PropStruct();
props[1].name = "location";
props[1].value_type =
  orb.get_primitive_tc(org.omg.CORBA.TCKind.tk_string);
props[1].mode = PropertyMode.PROP_MANDATORY;

props[2] = new
  org.omg.CosTradingRepos.ServiceTypeRepository.PropStruct();
props[2].name = "page_per_min";
props[2].value_type =
  orb.get_primitive_tc(org.omg.CORBA.TCKind.tk_long);
props[2].mode = PropertyMode.PROP_NORMAL;

String[] superTypes = new String[0];
```

```

4 type_repos_obj.add_type(
    "Printer" // Service Type
    "IDL:TraderDemo/PrintServer:1.0", // IDL type name
    props, // offer properties
    superTypes // no supertypes
);

```

The code is described as follows:

1. Get a reference to the Service Offer Type Repository.
2. The type `CosTrading::TypeRepository_var` is a typedef of `CORBA::Object`, and is essentially a forward reference. After obtaining a reference of this type, narrow it to `org.omg.CosTradingRepos.ServiceTypeRepository`.
3. Construct the property information of a service offer type. In this example there are three properties: `name`, `location`, and `page_per_min`. The main parts of a service offer type include the following:
 - ◆ The name of the service type.
 - ◆ The IDL interface id for this service.
 - ◆ The properties which are a description of the offer. These are as follows:

```

enum PropertyMode {
    PROP_NORMAL, PROP_READONLY,
    PROP_MANDATORY, PROP_MANDATORY_READONLY
};
struct PropStruct {
    CosTrading::PropertyName name;
    TypeCode value_type;
    PropertyMode mode;
};
typedef sequence<PropStruct> PropStructSeq;

```

4. Invoke the `add_type()` function and pass it the relevant parameters.

Exporting a Service Offer

When a server wants to make its service offers available, it registers with the Trader Service by exporting service offers. The code in [Example 1](#) demonstrates the steps to export a service offer.

Example 1: *Exporting a service offer*

```

1 PrintServer_Impl print_server_impl = new PrintServer_Impl();
  PrintServer print_server = print_server_impl._this(orb);
2 org.omg.CORBA.Object trader =
    orb.resolve_initial_references("TradingService");
  org.omg.CosTrading.Lookup lookup =
    org.omg.CosTrading.LookupHelper.narrow(trader);
  org.omg.CosTrading.Register register = lookup.register_if();
3 org.omg.CosTrading.Property[] props = new
    org.omg.CosTrading.Property[3];

  props[0] = new org.omg.CosTrading.Property();
  props[0].name = "name";
  props[0].value = orb.create_any();
  props[0].value.insert_string("laser4");

  props[1] = new org.omg.CosTrading.Property();
  props[1].name = "location";
  props[1].value = orb.create_any();
  props[1].value.insert_string("near coffee machine");

  props[2] = new org.omg.CosTrading.Property();
  props[2].name = "ppm";
  props[2].value = orb.create_any();
  props[2].value.insert_long(50);

4 String id = reg.export(
    print_server, // object reference to the CORBA object
    "Printer",    // the service type
    props        // the service's properties
  );

```

1. The printer server first creates an instance of the printer object.
2. The printer server connects to the Trader Service (as described in [“Connecting to the Trader” on page 26](#)) and gets a `trader_lookup_var`. It then uses this to access the Trader Service’s register component, which handles exporting of service offers.

3. The server initializes the service offer properties with relevant values.
4. The server finally invokes the `export ()` function to register the service offer.

Querying for a Service Offer

Once offers have been exported to the trader service, clients can use the lookup interface to request services. [Example 2](#) demonstrates a basic query that requests a printer that can print more than 5 pages per minute and uses the first offer returned by the trader.

Example 2: *Querying for a service offer*

```
// Trader Service reference, trader, acquired earlier

org.omg.CosTrading.Policy[] policies = new
    org.omg.CosTrading.Policy[0];
org.omg.CosTrading.LookupPackage.SpecifiedProps desiredProps =
    new org.omg.CosTrading.LookupPackage.SpecifiedProps();
desiredProps.__default(org.omg.CosTrading.LookupPackage.HowManyP
    rops.all);

org.omg.CosTrading.OfferSeqHolder offers = new
    org.omg.CosTrading.OfferSeqHolder();
org.omg.CosTrading.OfferIteratorHolder iter = new
    org.omg.CosTrading.OfferIteratorHolder();
org.omg.CosTrading.PolicyNameSeqHolder limits = new
    org.omg.CosTrading.PolicyNameSeqHolder();

1 trader.query(
    "Printer",           // the service type
    "ppm >5",          // the constraint to match
    "random",           // the order to sort the results
    policies,           // no special policies
    desiredProps,       // set to return all properties
    50,                 // max offers to return
    offers,              // offers returned
    iter,               // remaining offers
    limits               // polices applied by the trader
);
2 org.omg.CosTrading.Offer[] offer = offers.value;
if (offer.length() != 0)
{
    PrintServer printer_obj =
        PrinterServerHelper.narrow(offer[0].reference);
3     printer_obj.print(doc, job_id);
}
```

Example 2: *Querying for a service offer*

```
4 // we are only interested in a single offer, so we
// destroy the offer iterator, if the Trader created one for us
if(iter.value != null)
    iter.value.destroy();
```

1. The client queries the Trader Service for a service offer matching certain criteria. In this example:
 - ◆ The constraint is that the offers returned have a `page_per_min` value that is greater than 5 pages per minute.
 - ◆ The results are returned in random order.
 - ◆ The default policies are used.
 - ◆ All properties are returned with the offer.
 - ◆ A limit is set for the number of offers returned in the `offers` parameter. The trader will make find all of the possible matches, and return the remainder in the `iter` parameter.
2. The client selects a service offer from those returned in the query and invokes on the server. This simple example uses the first offer in the sequence.
3. The client uses the service offer to invoke on the object. In this case, the document is printed using the selected printer offer.
4. Any resources created by the trader for the iterator must be explicitly freed up.

Querying for Service Offers

In order for clients to find out about and use services offered by the Trader Service, the client code performs queries to obtain one or more service offers. A service offer contains, among other things, an object reference to a service. Clients then use the object reference to access a desired service.

In this chapter

This chapter contains the following sections:

How the Trader Service Processes a Query	page 34
A Basic Query for Service Offers	page 36
Selecting a Service from Query Results	page 39
Forming Constraints for Queries	page 41
Setting Preferences to Sort Service Offers	page 44
Refining the Properties a Query Returns	page 46

How the Trader Service Processes a Query

Overview

It is easy to see how the set of offers that a trader contains can get quite large. In addition, traders can be linked together (federated) to search each other for service offers. This means that a query needs to have controls that complete a search in a reasonable amount of time. A query also needs controls that limit the amount of data returned.

Format of a query

A query starts with a service type name. A query then limits a search for appropriate offers by using a constraint on one or more properties of the service. You can also specify other limiting factors including the number of offers returned, a preference on the sort order, and the property values actually returned.

Figure 4 shows how the Trader Service uses these factors to process a query and generate a sequence of desired service offers.




Figure 4: *How Query Parameters Affect Offers Gathered*

When the Trader Service processes a query, it gathers a sequence of offers together by narrowing down the set of all potential offers in all linked traders. The Trader Service uses query input to determine the following:

1. Uses the service name to determine if an offer is of an appropriate service type.
 2. Uses the property constraints to determine if the offer matches the criteria specified by the client.
 3. Uses preferences to determine the order in which to place the offer in the sequence of offers created.
 4. Uses desired properties to determine which of the offer's property values (if any) are returned.
-

Policies

The Trader Service uses policies to control its behavior. For example, the maximum number of offers that can be searched for. You can also include one or more policies and values in a query to control the search behavior for a specific query.

A Basic Query for Service Offers

Connecting to the trader

Clients need to connect to the Trader Service before they query for service offers. Do the following in your client to get an object reference to the trader:

```
// Java
org.omg.CORBA.Object trader_obj =
    orb.resolve_initial_references("TradingService");
if(trader_obj != null)
{
    org.omg.CosTrading.Lookup lookup =
        org.omg.CosTrading.LookupHelper.narrow(obj);
}
```

First, call `resolve_initial_references()` which returns a `org.omg.CORBA.Object`. Then, narrow the object reference to a trader `Lookup` object.

Querying the trader

After connecting to the trader, clients can query the trader for service offers that match any desired criteria.

```
// Java
lookup.query(
// Query input
1  "IDL:printer:1.0", // service type name
2  "(page_per_min > 5) and (page_type == 'A4')", // constraint
3  "random", // preference sort order
4  default_policies, // policies desired
5  return_properties, // properties to return
6  10, // Initial number of offers wanted
// Query Output
offers, // offers returned
iterator, // remaining offers
limits_reached // Limits reached during query
);
```

The input parameters to a query are explained in detail as follows:

1. The service type name parameter specifies the service type of the offers required. If the `exact_type_match` import policy is specified as true, only the service type is considered and no subtypes. If the `exact_type_match` policy is false or unspecified then subtypes are considered.
2. The constraint parameter specifies the constraint for restricting suitable offers. The constraint is a string that conforms to the OMG Constraint Language. Use an empty string if no constraints are required. See [“Forming Constraints for Queries” on page 41](#) for more constraint examples.
3. A preference parameter specifies the order of the returned sequence of offers. You can sort offers by the following criteria:
 - ◆ In the order in which the Trader Service finds the offers. (This is the default.)
 - ◆ In descending order based on property values.
 - ◆ In ascending order based on property values.
 - ◆ All offers that meet a constraint first, followed by those offers that do not meet the constraint.
 - ◆ In random order.Use an empty string if no sort preference is required. See [“Setting Preferences to Sort Service Offers” on page 44](#) for sort preference examples.
4. For now, default policies are used for the policies parameter. Policies are discussed in [Chapter 5](#).
5. A return-properties parameter specifies the properties to return for the sequence of offers. You can choose to have none, some, or all properties returned. For example, if for your application it is adequate to use the first valid service offer, you can improve efficiency by returning no properties for the returned offers. See [“Refining the Properties a Query Returns” on page 46](#) for an example of how to specify some properties to return.
6. The how-many-offers parameter specifies the number of offers to be initially returned via the `offers` out parameter. This example requests 10 initial offers.

The `offers` are returned as a sequence of offers. You can check for more offers and obtain them by using the `iterator` output parameter. If the Trader Service reached any policy limits during its search, the policy name is returned in the `limits_reached` output parameter. The `query()` output and how to use it is described in the next section.

Selecting a Service from Query Results

Overview

The previous section described how the input parameters to the `query()` operation controls the offers you get. This section describes details of the output from `query()`.

Output parameters

The output parameters include a sequence of offers, an iterator object to obtain more offers, and a sequence of policy limits that the Trader Service may have encountered as it collected the offers.

```
// Java
lookup.query(
// Query Input

// Query Output
    offers,           // offers returned
    iterator,        // remaining offers
    limits_reached   // Limits reached during query
);
```

offers

The `offers` parameter contains the returned sequence of offers. The client selects a service offer from those returned in the query and invokes on the desired server. The following example simply uses the first offer in the sequence:

```
// Java
org.omg.CosTrading.Offer[] offer = offers.value;
if (offer.length != 0)
{
    PrintServer printer_obj =
    PrintServerHepler.narrow(offer[0].reference);
    printer_obj.print(doc, job_id);
}
```

iterator

The `iterator` parameter is an object reference to an `OfferIterator` interface. If all offers are returned in the `offers` parameter then the `iterator` parameter has a null reference value. However, recall that a query specifies the number of

offers to be returned. If the number of offers requested is lower than the number the Trader Service found, then an `OfferIterator` object reference is returned and the remaining offers can be retrieved via that object.

The following example shows how to peruse the remaining sequence of offers. In this example, the names of properties are printed:

```
// Java
String name;

boolean more_offers = TRUE;
while (more_offers)
{
    more_offers = iterator.next_n(2, offers);
    org.omg.CosTrading.Offer[] offer = offers.value;

    for (long i = 0; i < offer.length(); i++)
    {
        name = offer[i].properties[0].value.extract_string();
        System.out.println(name);
    }
}

// free up the resources used by the iterator
iterator.destroy();
```

Once you are done with the iterator, you must use its `destroy()` function to release the resources it uses.

limits_applied

The `limits_applied` parameter is a sequence of policy names. If the Trader Service encounters any policy limits during a query, it returns the names of the policies in this sequence. For example, if a query generates more offers than the maximum number of offers the trader is allowed to search for, the name `max_search_card` is returned in the sequence. The values of the policies are not returned.

Forming Constraints for Queries

Using the constraint language

This section describes how to use more features of the OMG constraint language to construct effective constraint expressions when querying for service offers. See [“The OMG Constraint Language” on page 113](#) for a complete specification of the constraint language.

Although service properties can be defined using the great variety of IDL data types available, not all can be queried with the OMG constraint language. You can use the constraint language for properties defined with the following simple IDL data types:

```
boolean
short, unsigned short
long, unsigned long
float, double
char, Ichar
string, Istring
```

You can also use the constraint language for properties defined with sequences of the above data types.

Evaluating property values

A constraint contains a comparison of property values. The result of a comparison is a `boolean`. Thus, a potential offer is a match if the Trader Service evaluates the constraint as `true`.

Comparison operators

Use the operators `==`, `!=`, `>`, `>=`, `<`, or `<=` to compare two of the same simple types. For example, the following constraint compares a float property with a float constant value:

```
float_property == 1.0
```

Substring operator

Use the operator `~` to determine if the right operand is a substring of the left operand. The left operand is a property of type `string` or `Istring`, and the right operand is another string or string constant. For example:

```
string_property ~ 'String data'
```

String constants are delineated with apostrophes. To embed an apostrophe in a string, precede the apostrophe with a backslash (\').

Sequence operators

Use the `in` operator to test if a value is in a sequence of values. The left operand must be a simple IDL type and the right operand must be a sequence of the same simple IDL type. For example:

```
'duplex' in output_options
```

Combining expressions

Constraints can include combinations of expressions by using the keywords `and`, `or`, and `not`. For example, the following shows a constraint to obtain printers that produce output at a rate greater than 5 pages per minute and that support an A4 page type:

```
(page_per_min > 5) and (page_type == 'A4')
```

The following constraint is to obtain printers that do not produce output at a rate less than 5 pages per minute:

```
not (page_per_min < 5)
```

You can use parentheses to group expressions for clarity or to override the precedence relations of the constraint language.

Testing for a property's existence

A constraint can test any service type property for its existence, even if the IDL data type used to define it is not a simple data type or sequence of a simple data type. Use the `exist` keyword to test whether a property exists for given offer:

```
exist page_per_min
```

Because properties with a mandatory mode must exist, it does not make sense to test for their existence. However, searching for the existence of optional properties can provide a powerful means of limiting the offers returned.

Using arithmetic expressions

Constraints can include arithmetic expressions by using the standard operators `*/+-`. However, you can only use these operators between numbers and not between property names. For example:

```
page_per_min > 2 * 5
```

You can use float and double values where appropriate. Exponential notation is also valid.

Setting Preferences to Sort Service Offers

Creating a preference string

When querying for service offers, you can set preferences to make the offers return in a particular order. Create a preference string using one of the following formats:

```
first
max numerical_expression
min numerical_expression
with constraint_expression
random
```

A preference string consists of a keyword and, in some cases, an expression. You cannot specify combinations of preferences by using more than one keyword in a single preference string.

Constructing preference expressions

Use the OMG constraint language to construct the preference expressions for `max`, `min`, and `with` formats. When you submit a query with one of these preference expressions, the Trader Service associates a sort value with each offer by evaluating the expression. The offers are then sorted with respect to the sort value and the type of preference as follows:

- A `max` preference sorts the offers in descending order from the maximum sort value evaluated.
- A `min` preference sorts the offers in ascending order from the minimum sort value evaluated.
- A `with` preference returns the offers that evaluate to true before the offers that evaluate to false.

If the Trader Service cannot evaluate the expression for a particular offer (for example, an expression that is based on an optional property may not evaluate), the offers are not discarded but are grouped after those offers that can be evaluated.

Returning offers in the order of discovery

The default behavior of the Trader Service is to return offers in the same order in which they were discovered. You can also specify this behavior by using the `first` preference.

Returning offers in descending order

Use the preference string format “*max numerical_expression*” to sort the returned service offers in descending order. For example:

```
max page_per_min
```

In this example, printers with the highest `page_per_min` value are returned first. The rest of the offers are returned in a descending order based on the sort value calculated in the numerical expression. Any offers that do not have a value for `page_per_min` are returned last.

Returning offers in ascending order

Use the preference string format “*min numerical_expression*” to sort the returned service offers in ascending order. For example:

```
min (jobs_in_queue)
```

In this example, printers with the lowest number of `jobs_in_queue` are returned first, followed in ascending order.

Note: The `max` and `min` preference formats do not constrain the offers returned to a maximum or minimum value. For example, the following is an incorrect expression that does not limit a sort to the offers with a minimum `page_per_min` value of 8:

```
min (page_per_min == 8) This is an incorrect format
```

Returning offers by constraint

Use the preference string format “*with constraint_expression*” to order the returned service offers based on a constraint expression. A constraint expression evaluates to either true or false. The offers with a constraint preference that evaluates to true precede those that evaluate to false. For example:

```
with (page_per_min > 10)
```

This example sorts the returned offers into two groups: the first group has pages per minute values greater than 10 and the second group has pages per minute values of less than or equal to 10.

Returning offers in random order

Use the `random` preference to make the Trader Service return offers in random order.

Refining the Properties a Query Returns

Specifying returned properties

You can specify which properties you want returned in the sequence of offers. For example, if your application does not need to use all properties to determine which services to use, it can be more efficient for your memory and network traffic to return only those properties you need.

[Example 3](#) shows how to specify the properties to return.

Example 3: *Specifying the return of properties*

```
// Java
1 org.omg.CosTrading.LookupPackage.SpecifiedProps desiredProps =
  new org.omg.CosTrading.LookupPackage.SpecifiedProps();
  desiredProps._default(org.omg.CosTrading.LookupPackage.HowManyPr
    ops.some);

2 org.omg.CosTrading.PropertyName[] properties = new
  org.omg.CosTrading.PropertyName[2];
  properties[0] = new org.omg.CosTrading.PropertyName("location");
  properties[1] = new org.omg.CosTrading.PropertyName("ppm");
3 desiredProps.prop_names(properties);

lookup.query(
  "IDL:printer:1.0",
  "(page_per_min > 5) and (page_type == 'A4')",
  "random",
  default_policies,
4 desiredProps,           // properties to return
  10,
  offers,
  iterator,
  limits_reached
);
```

The code is described as follows:

1. You first declare a `SpecifiedProps` union for properties.

To return all properties use the following code and go to step 4:

```
// Java
org.omg.CosTrading.LookupPackage.SpecifiedProps desiredProps =
    new org.omg.CosTrading.LookupPackage.SpecifiedProps();
desiredProps.__default(org.omg.CosTrading.LookupPackage.HowManyP
    rops.all);
```

To return no properties use the following code and go to step 4:

```
// Java
org.omg.CosTrading.LookupPackage.SpecifiedProps desiredProps =
    new org.omg.CosTrading.LookupPackage.SpecifiedProps();
desiredProps.__default(org.omg.CosTrading.LookupPackage.HowManyP
    rops.none);
```

2. If you want specific properties returned, create a property name sequence, `property_seq`. Make the sequence long enough to contain the names of all properties to be returned and fill it with the names of the desired properties.
3. Fill the `desired_properties` object with the list of properties to be returned.
4. Use the `desired_properties` object as a parameter in the `query()` function call.

Understanding Trader Service Policies

Trader policies affect how the Trader Service works. Most policies control the scope of a search for offers. A few policies determine certain functionality that applies to the trader itself, including whether a trader supports modifiable properties, whether it supports dynamic properties, and whether it supports proxy offers.

In this chapter

This chapter contains the following sections:

Overview	page 50
Policies that Affect Queries	page 51
Policies that Affect Trader Functionality	page 54
Using Policies in a Query	page 55
Setting a Trader's Global Policies	page 57

Overview

What is a policy?

A policy is a data structure containing a pre-defined policy name and a value for that policy. The value's data type depends on the particular policy. For example, the `supports_modifiable_properties` policy can have a `boolean` value. A value of 0 means that for the particular trader, properties of service offers cannot be changed after an offer is exported to the trader. A value of 1 means that the trader allows changes to its service offer properties.

Policies that Affect Queries

Query semantics

Most policies that affect queries are scoping policies. These policies relate to the scope of a search when a query is submitted to the trader. Here are the high-level semantics when the trader processes a query:

1. Consider the number of initial offers to be searched.
 2. Match the offers against the constraints specified in the query.
 3. Consider the number of “hops” between linked traders during a search.
 4. Order the results according to the preference supplied in the query. (No policies relate to this.)
 5. Return these offers to the user.
-

Search policies

The following policies govern the scope of this search:

<code>search_card</code>	Consider at most this number of offers for the search.
<code>match_card</code>	Match at most this number of offers before returning them to be ordered.
<code>hop_count</code>	Allow at most this number of hops from one trader to another linked trader.
<code>return_card</code>	Return at most this number of offers to the client.

These policies can be optionally specified in a query. Each of these policies have “tuning” policies associated with them in the trader. The trader tuning policies are called `def_policy` and `max_policy` where *policy* is the name of one of the policies listed above. For example, the `search_card` policy may be specified in a query and the `def_search_card` and `max_search_card` policies have initial values in the Trader Service when it starts up. The trader policies may be changed using functions from the `CosTrading::Admin` interface.

If a query doesn’t specify a value for a policy, then the appropriate `def_policy` value of the trader applies. If the query specifies a value for a policy, then it applies for the duration of that query, except where it exceeds the trader’s `max_policy` value, in which case the value `max_policy` is used. For example, suppose that in the trader, `def_search_card` is 50, and `max_search_card` is 500:

- If the query doesn't specify a `search_card`, then at most 50 offers will be considered in the initial search.
- If the query specifies "`search_card = 100`", then 100 offers will be initially considered.
- If the query specifies "`search_card = 600`", then, since this exceeds the trader's maximum, at most 500 offers will be initially considered.

Return policy

The policy `exact_type_match` may also be defined in a query. The value of this policy is a `boolean`. If it is specified as `true`, then only offers that exactly match the specified service type are considered; super-types are omitted. Otherwise, offers of any conforming service type are considered.

List of query policies

Table 2 shows the policies you can set in a query, along with the associated trader policies that affect the query policy. (A complete list and description of each policy is in the *CORBA Programmer's Reference*.)

Table 2: *Query policies and Trader Service policies*

Policies You Can Set in a Query	Related Trader Service Policies
<i>Searching Service Offers</i>	
<code>exact_type_match</code>	
<code>search_card</code>	<code>def_search_card</code> <code>max_search_card</code>
<i>Matching Query Constraints</i>	
<code>match_card</code>	<code>def_match_card</code> <code>max_match_card</code>
<i>Number of Returned Offers</i>	
<code>return_card</code>	<code>def_return_card</code> <code>max_return_card</code>
<i>Links Between Traders</i>	
<code>hop_count</code>	<code>def_hop_count</code> <code>max_hop_count</code>

Table 2: *Query policies and Trader Service policies*

Policies You Can Set in a Query	Related Trader Service Policies
link_follow_rule	default_follow_rule ^a def_follow_policy limiting_follow_rule ^a link_follow_rule max_follow_policy
request_id_stem	request_id_stem
starting_trader	
<i>Optional Trader Capabilities</i>	
use_dynamic_properties	supports_dynamic_properties
use_modifiable_properties	supports_modifiable_properties
use_proxy_offers	supports_proxy_offers

a. These are set in the links created between traders. See [“Managing Links Between Traders”](#) on page 78.

Policies that Affect Trader Functionality

Overview

A trader may support some optional functionality. These include *modifiable properties*, *dynamic properties*, and *proxy offers*. In a particular query, a client may choose not to consider offers that require such functionality, even if the trader supports it (for example, to optimize the speed of a query).

Evaluating policies

To find out if a trader supports any of this functionality, the following attributes are provided in the `CosTrading::SupportAttributes` interface. The `get` function for these attributes return a `boolean` representing the value of the policy:

- `supports_modifiable_properties(default: true)`
 - `supports_dynamic_properties(default: true)`
 - `supports_proxy_offers(default: true)`
-

Query policies

In a query, these policies are specified using the following `boolean` variables. If the trader does not support the functionality, then the corresponding query policy is ignored.

- `use_modifiable_properties`
- `use_dynamic_properties`
- `use_proxy_offers`

Using Policies in a Query

Policies parameter

You can use the `policies` parameter in a query to control the query and override some of the default Trader Service policies. A `Policy` data structure contains two members:

- A `PolicyName` is a pre-defined `string` identifier used by a trader to identify a policy.
- A `PolicyValue` is the value specified for a policy. The `PolicyValue` is of type `any`. The type of the `any` value should match the type of the corresponding policy.

An application may manipulate policies by using a `PolicySeq`, which is a sequence of `Policy` data structures.

Creating a policy list

[Example 4](#) shows how to create a policy sequence and pass it to a `query()`:

Example 4: *Creating a policy sequence*

```
// Java
1 org.omg.CosTrading.Policy[] policies = new
  org.omg.CosTrading.Policy[2];
2 org.omg.CORBA.Any any = org.omg.CORBA.ORB.create_any();
  any.insert_long(50);
  policies[0] = new org.omg.CosTradingPolicy("search_card", any);
3 any.insert_boolean(false);
  policies[1] = new
    org.omg.CosTradingPolicy("use_dynamic_properties", any);

4 lookup.query("IDL:printer:1.0", "page_per_min > 5", "first",
  policies,
  desired_properties,
  how_many_offers,
  offers,
  offer_itr,
5 limits_applied
  );
```

1. First create a sequence of `Policy` structures, and set the number of policies you want to specify for the query. This example uses just two policies.

2. Setting the `search_card` policy to 50 means that the query should look at a maximum of 50 offers initially before matching this query.
3. Setting the `use_dynamic_properties` policy to `false` means that the query should not consider offers with dynamic properties.
4. Use the policy sequence as a parameter in the `query()` function.
5. If the Trader Service encounters any policy limits during a query, it returns the names of the policies in this parameter as a sequence of policy names. For example, if a query generates more offers than the maximum number of offers the trader is allowed to search for, the name `max_search_card` is returned in the sequence. The values of the policies are not returned.

Policy types

Table 3 shows the policies you can set and the associated IDL data type for each policy:

Table 3: *Policies You Can Set for a Query*

Policy Name	IDL Type
<code>exact_type_match</code>	boolean
<code>hop_count</code>	unsigned long
<code>link_follow_rule</code>	<code>CosTrading::FollowOption</code>
<code>match_card</code>	unsigned long
<code>request_id_stem</code>	<code>CosTrading::OctetSeq</code>
<code>return_card</code>	unsigned long
<code>search_card</code>	unsigned long
<code>starting_trader</code>	<code>CosTrading::TraderName</code>
<code>use_dynamic_properties</code>	boolean
<code>use_modifiable_properties</code>	boolean
<code>use_proxy_offers</code>	boolean

Setting a Trader's Global Policies

Setting global policies

For each policy in the trader, the `CosTrading::Admin` interface has an associated set function that you can use to set the policy value. The set functions take the form `set_policy_name(value)`, where `policy_name` is the policy you wish to set. For example, you can use the `Admin::set_max_match_card()` function to set the `max_match_card` attribute of the `ImportAttributes` interface.

Also see “[Setting policies for linked traders](#)” on page 78 for another example of how to set policies.

Global policies

[Table 4](#) summarizes the global trader policies an administration application can set:

Table 4: *Trader policies*

Policy Name	Type
<code>default_follow_rule</code>	<code>CosTrading::FollowOption</code>
<code>def_follow_policy</code>	<code>CosTrading::FollowOption</code>
<code>def_hop_count</code>	unsigned long
<code>def_search_card</code>	unsigned long
<code>def_match_card</code>	unsigned long
<code>def_return_card</code>	unsigned long
<code>max_follow_policy</code>	<code>CosTrading::FollowOption</code>
<code>max_hop_count</code>	unsigned long
<code>max_search_card</code>	unsigned long
<code>max_link_follow_policy</code>	<code>CosTrading::FollowOption</code>
<code>max_list</code>	unsigned long
<code>max_match_card</code>	unsigned long

Table 4: *Trader policies*

Policy Name	Type
max_return_card	unsigned long
request_id_stem	CosTrading::OctetSeq
supports_dynamic_properties	boolean
supports_modifiable_properties	boolean
supports_proxy_offers	boolean

Exporting and Managing Service Offers

Application servers can advertise their services by exporting service offers to the Trader Service. Servers can also manage their service offers in the Trader Service by getting offer information, modifying an offer's properties, and withdrawing an offer.

In this chapter

This chapter contains the following sections:

Overview	page 60
Initializing Service Offer Properties	page 61
Exporting a Service Offer to Trader	page 63
Getting Service Offer Data from Trader	page 65
Modifying a Service Offer	page 66
Withdrawing a Service Offer from Trader	page 68

Overview

Server tasks

This chapter describes the following service offer tasks for servers:

- How to initialize service offer properties prior to exporting to the Trader Service.
 - How to export service offers to the Trader Service.
 - How to get service offer data from the Trader Service.
 - How to modify a service offer already in the Trader Service.
 - How to withdraw a service offer from the Trader Service.
-

Environment

All of this chapter's discussion and associated programming examples can be done within a specific application server, such as the printer server shown in the examples here. However, you might just as likely do this programming with a management server that is separate from the servers supplying specific resources. Whether it is better for your server to export and manage its own offer or for a separate management program to do it depends on your programming style and application design.

Initializing Service Offer Properties

Property structure

Offer properties are stored as a sequence of property structures, where each property is a name-value pair, as follows:

```
// IDL
typedef Istring PropertyName;
typedef any PropertyValue;
struct Property {
    PropertyName name;
    PropertyValue value;
};
typedef sequence<Property> PropertySeq;
```

Getting an offer type's property list

Information about all services that the Trader Service can support is stored as service types in the Trader Service repository. When you develop a server for a specific service, you will need to have the information about the service type's properties. There may be documentation describing these properties or you may need to extract the information from the Trader Service. The section, "[Managing the Service Type Repository](#)" on page 70 explains how to add service types to a trader and how to list a trader's service type property information.

Before a server can export an offer to a trader, it must initialize the offer's properties. A server initializes the service offer properties with relevant values. For example:

```
// Java
org.omg.CosTrading.Property[] props = new
    org.omg.CosTrading.Property[3];

props[0] = new org.omg.CosTrading.Property();
props[0].name = "name";
props[0].value = orb.create_any();
props[0].value.insert_string("laser4");

props[1] = new org.omg.CosTrading.Property();
props[1].name = "location";
props[1].value = orb.create_any();
props[1].value.insert_string("near coffee machine");

props[2] = new org.omg.CosTrading.Property();
props[2].name = "ppm";
props[2].value = orb.create_any();
props[2].value.insert_long(50);
```

Read-only and mandatory properties

Before you initialize an offer's properties, check the service type information for any *mandatory* properties and any *readonly* properties. You must set a value for mandatory properties in order to successfully export an offer. Readonly properties cannot be modified once the offer is exported. Each property has assigned to it one of the following modes:

normal	A service offer need not supply a value for this property.
readonly	A service offer need not supply a value for this property. However if it does, the value cannot be modified after its offer is exported.
mandatory	A value for this property must always be provided when a service offer is exported.
mandatory and readonly	A value for this property must be supplied and it cannot be modified after it is exported.

Exporting a Service Offer to Trader

Overview

Servers use the `export()` operation to register a service offer with the Trader Service.

Synopsis

The `export()` operation takes the following form:

```
// Java
org.omg.CosTrading.Register.export (
    org.omg.CORBA.Object service_object,
    String service_type,
    org.omg.CosTrading.Property[] properties)
```

It takes the following parameters:

<code>service_object</code>	A reference to the object providing the service
<code>service_type</code>	The name of the service type that represents the service being offered
<code>properties</code>	A sequence of <code>Property</code> which describes the offer's properties. See “Initializing Service Offer Properties” on page 61 for more information.

`export()` returns a `CosTrading::OfferId` which uniquely identifies the service offer within the trader. This value is needed to modify or withdraw the service offer.

Example

[Example 5](#) shows how to export a service offer:

Example 5: *Exporting a service offer*

```
// Java
1 PrintServer_impl impl = new PrintServer_impl();
  PrintServer print_server = impl._this(orb);

2 org.omg.CORBA.Object trader =
  orb.resolve_initial_references("TradingService");
  org.omg.CosTrading.Lookup lookup =
  org.omg.CosTrading.LookupHelper.narrow(trader);
```

Example 5: *Exporting a service offer*

```
3 org.omg.CosTrading.Register register = lookup.regester_if();  
4 String offer_id = register.export(  
    print_server, // the object itself  
    "Printer", // service type  
    properties // initialized in previous example  
);
```

Do the following programming steps to export the service offer:

1. Create an instance of the service object. For example, this application uses a printer service.
2. Connect to the Trader Service. Call the function `resolve_initial_references()` to get an object reference to the trader and narrow the returned value to get the trader's `Lookup` object.
3. Narrow the `Lookup` object to get the trader's `Register` component, which handles service offer exporting.
4. Invoke the `export()` function to export the service offer.

Getting Service Offer Data from Trader

Reviewing offer information

After a server exports an offer, you can review the information contained in the offer by using the `describe()` operation of the `Register` interface. This function takes an `OfferId` as input and returns an `OfferInfo` structure representing offer information. The following example continues from the previous one:

```
// Java
org.omg.CosTrading.Register.OfferInfo offer_info =
    register.describe(offer_id);
```

The `CosTrading::Admin` interface includes an `list_offers()` function you can use to obtain a list of all offers held by the Trader Service.

Modifying a Service Offer

Using modify()

You can modify any properties of an offer, other than those declared read-only, by using the `modify()` operation of the trader's `Register` object to delete, add, or change its properties.

`modify()` takes the following parameters:

<code>offer_id</code>	The <code>OfferId</code> returned by the trader when the offer was exported.
<code>delete_list</code>	A sequence of <code>PropertyName</code> specifying which properties to delete from the offer.
<code>change_list</code>	A sequence of <code>Property</code> specifying the properties to modify, along with their new values. New properties can be included in this list and they will be added to the offer.

Example

Example 6 shows how to delete a property and how to change the value of a property.

Example 6: *Deleting property*

```

// Java
1 org.omg.CosTrading.PropertyName[] delete_list = new
  PropertyName[1]
  delete_list[0] = new org.omg.CosTrading.PropertyName("ppm");

2 org.omg.CosTrading.Property[] change_list = new
  org.omg.CosTrading.Property[1]

  change_list[0] = new org.omg.CosTrading.Property();
  change_list[0].name = "location";
  change_list[0].value = orb.create_any();
  change_list[0].value.insert_string("A-wing, first floor");

3 register.modify(offer_id, delete_list, change_list);

```

1. Create a sequence of the property names to be deleted.
2. Create the sequence of the properties to be added or modified.
3. Finally, call the `modify()` function

Readonly properties

For situations in which you need to change readonly properties, you can withdraw an offer and then export a new offer, but this changes the offer ID which may affect applications that already hold the current offer.

Policy for supporting modifiable properties

The `supports_modifiable_properties` policy is a boolean attribute that indicates whether or not a specific trader supports modifiable properties. Servers and administration applications can turn support for modifiable properties on or off by using `CosTrading::Admin::set_supports_modifiable_properties()`. To obtain the current value of this policy, query the `CosTrading::SupportAttributes::supports_modifiable_properties` attribute.

Withdrawing a Service Offer from Trader

When it is necessary to withdraw an offer from the Trader Service, use the `CostTrading::Register::withdraw()` function. The function requires as input the `offer_id`, which is obtained as a result of the `export()` function:

```
register.withdraw(offer_id);
```

Administration applications can use the following function to withdraw multiple offers satisfying a specified service type and constraint:

```
register.withdraw_using_constraint(type_name, my_constraint);
```

Programming Topics

This chapter is a brief introduction to some advanced programming topics and features of the Trader Service. These topics include adding service types, using dynamic properties, and managing links between traders.

In this chapter

This chapter contains the following sections:

Managing the Service Type Repository	page 70
Using Dynamic Property Values	page 74
Managing Links Between Traders	page 78

Managing the Service Type Repository

Overview

Servers cannot export service offers to the Trader Service unless the appropriate service types are stored in the Service Type Repository. You use the operations of the `ServiceTypeRepository` interface of the `CosTradingRepos` module to manage service types in a trader. Service types are added to a trader only occasionally, and usually by a management type of server. Service types are rarely removed from a trader.

Creating service type properties

You create service type properties and then you add these properties along with other information to the Trader Service. [Example 7](#) shows how to create service type properties.

Example 7: *Creating service type properties*

```
// Java
1 org.omg.CosTradingRepos.ServiceTypeRepository.PropStruct[] props
  = new
    org.omg.CosTradingRepos.ServiceTypeRepository.PropStruct[3];

2 props[0] = new
  org.omg.CosTradingRepos.ServiceTypeRepository.PropStruct();
3 props[0].name = "name";
4 props[0].value_type =
  orb.get_primitive_tc(org.omg.CORBA.TCKind.tk_string);
5 props[0].mode = PropertyMode.PROP_MANDATORY_READONLY;

props[1] = new
  org.omg.CosTradingRepos.ServiceTypeRepository.PropStruct();
props[1].name = "location";
props[1].value_type =
  orb.get_primitive_tc(org.omg.CORBA.TCKind.tk_string);
props[1].mode = PropertyMode.PROP_MANDATORY;

props[2] = new
  org.omg.CosTradingRepos.ServiceTypeRepository.PropStruct();
props[2].name = "page_per_min";
props[2].value_type =
  orb.get_primitive_tc(org.omg.CORBA.TCKind.tk_long);
props[2].mode = PropertyMode.PROP_NORMAL;
```

The code is described as follows:

1. Create a new sequence of property structures and set the length of the sequence to equal the number of properties for the service type.
2. For each property, create a new instance to contain it.
3. For each property, assign a character string to represent the name of the property. This printer example has three properties named `name`, `location`, and `page_per_min`.
4. Set the data type for the value of each property. This is standard Orbix programming for setting values for typecodes.
5. Set the mode for each property.
 - ◆ A `PROP_MANDATORY_READONLY` mode means the property *must* be set when exporting a service offer of this service type, but once it is exported, it cannot be changed.
 - ◆ A `PROP_MANDATORY` mode means the property *must* be set when exporting a service offer, but its value may be changed later if needed, after the service offer is exported.
 - ◆ A `PROP_READONLY` mode (not shown) means the property may be set when exporting a service offer, but once it is exported, it cannot be changed.
 - ◆ A `PROP_NORMAL` mode means the property may be set in a service offer but it is not required. It can be changed later.

Adding a service type

[Example 8](#) adds a service type named `IDL:printer:1.0` to a trader. The interface type name from the IDL file is `IDL:TraderDemo/PrintServer:1.0`. The properties, created in [Example 7](#) are the next parameter. The `super_types` parameter is a list of types from which this service type is derived. A subtype must support properties of its supertypes. In this example, there are no supertypes.

Example 8: *Adding a service type*

```
// Java
```

Example 8: *Adding a service type*

```

1 org.omg.CORBA.Object trader =
    orb.resolve_initial_references("TraderService");
org.omg.CosTrading.Lookup lookup =
    org.omg.CosTrading.LookupHelper.narrow(trader);
org.omg.CORBA.Object obj = lookup.type_repos();
org.omg.CosTradingRepos.ServiceTypeRepository trader_repos_obj =
    org.omg.CosTradingRepos.ServiceTypeRepositoryHelper.narrow(obj);

2 String[] superTypes = new String[0];

3 type_repos_obj.add_type(
    "IDL:printer:1.0" // Service Type
    "IDL:TraderDemo/PrintServer:1.0", // IDL type name
    properties, // offer properties
    superTypes // no supertypes
);

```

The code is described as follows:

1. Connect to the trader using `resolve_initial_references`, narrow the returned object to a `Lookup` object, and use that to get a reference to the Trader Service's Service Type Repository.
2. Create a list of the supertypes which define the service type being created. For this example, there are no supertypes.
3. Call `add_type` to add the service type to the Service Type Repository.

Managing service types

After a service type is added to the Trader Service, applications can use other operations of the `CosTradingRepos::ServiceTypeRepository` interface to manage service types. These include `remove_type()` and `list_types()`. The `describe_type()` operation returns information that describes the type, and the `fully_describe_type()` operation searches recursively to return information on all the supertypes for this type.

You can also hide service types from outside the service type repository by using the `mask_type()` operation. This may be used, for example, where a type is no longer needed, but it is the supertype of other types in the type repository. Use the `unmask_type()` operation if you need to make a masked service type visible again.

See also the `SupportAttributes::type_repos` attribute and the `Admin::set_type_repos()` operation. These get a reference to the type repository interface and set the type repository interface in a trader.

Using Dynamic Property Values

Dynamic property values

Exported offers can contain dynamic property values. These are values that can change at runtime. For example, the number of print jobs in a printer queue. This is done by exporting an object reference that can be invoked to retrieve the current value from the server. Clients and the trader can then dynamically determine the length of the printer queue at the time of a query. This is not as fast as using static values, but it can greatly increase the flexibility involved. The fact that a property has a dynamic value is only relevant at export time. There is no difference when defining the property in the service type.

Exporting a dynamic property value

When a dynamic property value is being exported, then the type `CostTradingDynamic::DynamicProp` is used rather than the expected type. The trader recognizes this as a special type, and treats it accordingly.

The following code shows how to set properties, including a dynamic property, and then export the offer that contains the dynamic property.

Example 9: *Setting dynamic properties*

```
// Java
org.omg.CosTrading.Property[] props = new
    org.omg.CosTrading.Property[4];

props[0] = new org.omg.CosTrading.Property();
props[0].name = "name";
props[0].value = orb.create_any();
props[0].value.insert_string("laser4");

props[1] = new org.omg.CosTrading.Property();
props[1].name = "location";
props[1].value = orb.create_any();
props[1].value.insert_string("near coffe machine");

props[2] = new org.omg.CosTrading.Property();
props[2].name = "ppm";
props[2].value = orb.create_any();
props[2].value.insert_long(50);

org.omg.CosTradingDynamic.DynamicProp dp = new
    org.omg.CosTradingDynamic.DynamicProp();
1 QueueLengthEval evalImpl = new QueueLengthEval(orb, printer);
dp.eval_if = evalImpl._this(orb);
2 dp.returned_type =
    orb.get_primitive_tc(org.omg.CORBA.TCKind.tk_short);
dp.extra_info = orb.create_any();

props[3] = new org.omg.CosTrading.Property();
props[3].name = "queue_length";
props[3].value = orb.create_any();
3 org.omg.CosTradingDynamic.DynamicPropHelper.insert(props[3].valu
    e, dp);

register_obj.export(
    obj, // object reference
    "IDL:printer:1.0", // service type name
    props // seq of properties
);
```

The code is described as follows:

1. `eval_if` is essentially a callback object in the server. It implements the IDL interface `CosTradingDynamic::DynamicPropEval`, which contains one operation `evalDP`, which returns the current value of the property in the server when invoked.
2. The `returned_type` must be the same type as the corresponding property type defined in the service type. `extra_info` is essentially ignored by the trader, but may be used by users to carry additional information.
3. The dynamic value is assigned to the property value.

Using a dynamic property value

Clients may need to check if the value in a property is dynamic or not, if it is possible that the value may be either a static or dynamic value.

Example 10: Using a dynamic property value

```
// Java
org.omg.CosTrading.Property prop = props[2];

short length;
if(prop.value.containsType(org.omg.CORBA.TCKind.tk_short))
{
    length = prop.value.extract_short();
    System.out.println("static queue_length ", length);
}
else if
(prop.value.containsType(org.omg.CosTradingDynamic._tc_DynamicProp))
{
    org.omg.CosTradingDynamic dynam_prop =
    org.omg.CosTradingDynamicHelper.extract(prop.value);

    org.omg.CosTradingDynamic:DynamicPropEval dynam_eval =
    dynam_prop.eval_if;

    org.omg.CORBA.Any any_length = dynam_eval.evalDP(
        prop.name,
        dynam_prop.returned_type,
        dynam_prop.extra_info);

    length = any_length.extract_short();
    System.out.println("dynamic queue_length ", length);
}
```

Note that if the trader itself evaluates the dynamic property value, because it is used in a constraint expression (for example, “queue_length < 10”), then it will return the static value at the time of evaluation in the offer’s properties. This is to minimize the evaluation times on dynamic properties.

Allowing dynamic properties

While the Trader Service allows dynamic properties by default, a specific trader may be set to not allow dynamic properties. The

`CosTrading::SupportAttributes::supports_dynamic_properties` policy is a boolean attribute that indicates whether or not the trader allows dynamic properties. Servers and administration applications can set this policy value by using the operation

```
org.omg.CosTrading.Admin.set_supports_dynamic_properties().
```

Managing Links Between Traders

Linked traders

A linked trader shares information about its service offers with one or more other traders. Linked traders allow administrators to organize service types and service offers in logical and more efficient ways for specific environments.

This section describes the following Link function tasks:

- Setting link trader policies.
- Adding and removing links.
- Listing links to other traders.

Setting policies for linked traders

[Chapter 5](#) introduced several policies that relate to linked traders including `hop_count`, `link_follow_rule`, and `default_follow_rule`. A client query can set some of these policies to control the search for offers, but other policies relating to linked traders control the links and may override the query policies.

[Example 11](#) shows the use of `request_id_stem`. This should be a unique value per trader. It will be used in queries sent to other traders, to prevent infinite looping. When a trader sees an incoming query with its own request id stem, it does not process the query, and returns a result of zero offers to the calling trader.

Example 11: *Using request_id_stem*

```
// Java
//set request_id_stem to "1"
byte[] stem = new byte[1];
stem[0]="1";

// admin_obj is a pointer to the Admin interface of the Trader
Service
admin_obj.set_request_id_stem(stem);
```

The following code shows how to set other trader policies relating to links:

```
// Java
// set the following options
org.omg.CosTrading.FollowOption max_follow =
    org.omg.CosTrading.FollowOption.always
org.omg.CosTrading.FollowOption max_link_follow =
    org.omg.CosTrading.FollowOption.always;
org.omg.CosTrading.FollowOption def_follow =
    org.omg.CosTrading.FollowOption.always;

// set options for hops between traders
int max_hop = 10;
int def_hop = 10;

admin_obj.set_max_follow_policy(max_follow);
admin_obj.set_def_follow_policy(def_follow);
admin_obj.set_max_link_follow_policy(max_link_follow);
admin_obj.set_def_hop_count(def_hop);
admin_obj.set_max_hop_count(max_hop);
```

Adding links

[Example 12](#) shows how to add a link from one trader to another. The `trader1` establishes a link to `trader2`. The link is called `link_to_trader2`.

Example 12: *Linking from one trader to another*

```
// Java
org.omg.CosTrading.LinkName name = "link_to_trader2"

// set CosTrading.FollowOptions for add_link
org.omg.CosTrading.FollowOption def_pass_on_follow_rule =
    org.omg.CosTrading.FollowOption.always;
org.omg.CosTrading.FollowOption limiting_follow_rule =
    org.omg.CosTrading.FollowOption.always;

// link_var is a pointer to the Link Interface of trader1
// target is a pointer to trader2 Lookup Interface
link_var.add_link(
    name,
    target,
    def_pass_on_follow_rule,
    limiting_follow_rule);
```

Removing links

[Example 13](#) shows how to remove a link. The link removed is the one created in [Example 12](#):

Example 13: *Removing a link*

```
// Java
// set LinkName
org.omg.CosTrading.LinkName name = "link_to_trader2";

// link_var is a pointer to the Link Interface of trader1
link_var.remove_link(name);
```

Creating lists of links

[Example 14](#) shows how to create a listing of the links to other traders:

Example 14: *Creating a list of links to traders*

```
// Java
// lists links of trader1
org.omg.CosTrading.LinkName[] link_names = link_names =
    link_var.list_links();

// This prints the link names
for(int i = 0; i < link_names.length; i++)
    System.out.println(link_names[i]);
```

Trader Service Console

The Trader Service Console allows you to manage all aspects of the Trader Service, including service types, offers, proxy offers and links. It also lets you perform queries, and configure the trader attributes.

In this chapter

This chapter contains the following sections:

Starting the Trader Console	page 83
Main Window	page 84
Managing Service Types	page 89
Managing Offers	page 93
Managing Proxy Offers	page 98
Managing Links	page 100
Configuring the Trader Attributes	page 102
Admin Attributes	page 107

Executing Queries	page 108
Connecting to a New Trader	page 111

Starting the Trader Console

How to start the console

Run the following command in a command window:

```
ittrader_console
```

Main Window

GUI appearance

The Trader Service Console main window appears as shown in [Figure 5](#).




Figure 5: *The Trader Console main window*

Window elements


The main window includes the following elements:

Menu bar	Provides access to all of the application's features
Toolbar	Shortcuts for the most common menu commands
Item type selector	Selects which type of item is shown in the item list
Item list	Displays the names or identifiers of all items contained in the trader
Item description	Provides a textual summary of the selected item

Status bar Displays information about the trader to which the console is currently connected, including the host, port and IDL interface

The Toolbar

The toolbar contains buttons for the most common menu commands.



Terms used in trader console

The Trader Service Console uses the term *item* to generically refer to the four types of data managed by a trader service:

- Service types
- Offers
- Proxy offers
- Links

The console window is used to browse these items. The window only shows one type of item at a time, which you can change with the **item type selector** drop-down list or by selecting a type from the **View** menu. When a new *item type* is selected, the current list of items is retrieved from the trader service and displayed in the **item list**.

The Trader Console Menus

The Console menu

You use the commands in the **Console** menu to manage the console windows.

New Window	Creates a new console window, connected to the current trader.
Connect	Opens the Connect dialog box, allowing you to connect to a different trader service.
Close	Closes the current console window. If this window is the last console window present, the application exits.
Exit	Quits the application.

The Edit menu

The console supports the typical notion of a clipboard, which can be manipulated with cut, copy and paste commands. However, the console does not use the system clipboard, and therefore the application clipboard can only be accessed by windows from the same execution of the application. In other words, if you start two instances of the application, you cannot cut and paste between them. You can cut and paste if you start a single instance of the application, and create multiple windows with the **Console/New Window** command.

Cut	Copies the selected items to the clipboard and then permanently removes the selected items
Copy	Copies the selected items to the clipboard
Paste	Pastes the items from the clipboard into the current trader
Select All	Selects all of the items in the item list
Clone	Creates a clone of the selected item. The appropriate dialog box is displayed to allow you to create a new item, but the fields of the dialog box are initialized with the values from the selected item.
Modify	Edits the currently selected item
Delete	Permanently removes the selected items

Using the cut, copy and paste commands

There are some issues to be aware of when using the cut, copy and paste operations:

- Service types and links must have unique names; therefore, you will not be able to paste one of these items if an item already exists in the trader with the same name.
 - A certain amount of forethought is advised when you wish to cut and paste service types. Since service types can inherit from other service types, you cannot cut a service type that has subtypes. If you wish to cut or delete a number of service types, and if inheritance relationships exist between any of them, you must cut the types that don't have any subtypes first. The same principle applies to pasting service types, in that you cannot paste a type if its supertypes do not exist or have not yet been pasted. It is recommended that you only operate on one service type at a time when using the cut, copy, paste or delete commands.
-

Using the Clone and Modify commands

Note the following when using the clone and modify operations:

- Some types of items, namely service types and proxy offers, cannot be modified. The **Modify** command (and its toolbar equivalent) are disabled while these types are displayed.
 - The **Clone** and **Modify** commands operate on a single item at a time. If more than one item is currently selected, the application uses the first of the selected items.
-

The View menu

You use the **View** menu to select the type of items you wish to be displayed in the item list. Selecting a new type of item from this menu is equivalent to changing the setting of the item type selector.

The **Refresh** command causes the application to retrieve an updated list of items from the trader and display them in the item list. This command can be useful if you know (or suspect) that the list of items has been changed by some other client of the trader service.

The Insert menu

You use the **Insert** menu when you want to create a new item. It displays a dialog box in which you can supply the information about the new item. If you need to create a new item that is similar to an existing item, you can also use the **Edit/Clone** command.

The Tools menu

The commands available in the **Tools** menu provide access to additional features of the trader service.

Query	Perform query operations on the trader and review the matching offers
Attributes	Configure the trader attributes
Withdraw Offers	Removes offers using a constraint expression
Mask Type	Masks the selected service type
Unmask Type	Unmasks the selected service type

Managing Service Types

IDL type support

Although the Trader Service supports properties with user-defined IDL types, the console only supports simple IDL types and sequences of simple IDL types. Refer to [“Service Types” on page 4](#) for more information on service types.

Adding a new service type

To add a new service type:

1. Select **Insert/Service Type**. The **New Service Type** dialog box appears as shown below.




The screenshot shows a dialog box titled "New Service Type". It has a standard Windows-style title bar with a close button (X). The dialog is divided into several sections:

- Service type name:** A single-line text input field.
- Interface:** A single-line text input field followed by a "Browse..." button.
- Super types:** A list box (currently empty) with "Add..." and "Delete" buttons to its right.
- Properties:** A list box (currently empty) with "Add...", "Edit...", and "Delete" buttons to its right.


At the bottom of the dialog are "OK" and "Cancel" buttons.

2. Enter a name for the service type in the **Service type name** text box. The name must be unique among all of the service types managed by the trader.


3. Enter an interface repository identifier in the **Interface** text box. If the interface repository service is available, clicking the **Browse...** button displays an interface repository browser as shown below.



4. The browser displays only modules and interfaces. When you select an interface, its identifier is displayed in the **ID** text box below. Click **OK** to accept the identifier you have selected.
5. Use the **Add...** and **Delete** buttons to add and remove super types. Clicking the **Add...** button displays the **Super Types** dialog box as shown below. Select any service types you wish to use as super types for the new type and click **OK**. The order in which you add super types is not important.



- Use the **Add...**, **Edit...** and **Delete** buttons to manipulate the properties for this service type. Clicking the **Add...** or **Edit...** buttons displays the **Property** dialog box as shown below. Enter a name for the property, select a property type, and use the checkboxes to indicate the mode of this property. Click **OK** to add the new property.



- Click **OK** on the **New Service Type** dialog box to add the new service type.

Removing a service type

To remove a service type, do the following:

- Select **View/Service Types** to display the service types in the item list.
- Select the service type you wish to remove.
- Select **Edit/Delete**. A confirmation dialog appears.
- Click **Yes** to permanently remove the service type.

Note: If a service type has subtypes, you will not be able to remove the type until all of its subtypes have been removed.

Masking a service type

To mask a service type, do the following:

- Select **View/Service Types** to display the service types in the item list.
- Select the service type you wish to mask.
- Select **Tools/Mask Type**.

Unmasking a service type

To unmask a service type, do the following:

1. Select **View/Service Types** to display the service types in the item list.
2. Select the service type you wish to unmask.
3. Select **Tools/Unmask Type**.

Managing Offers

Adding a new offer

To add a new offer, do the following:

1. Select **Insert/Offer**. The **New Offer** dialog box appears as shown below.

The 'New Offer' dialog box contains the following elements:


- Service type:** A dropdown menu currently showing 'Printer'.
- Object Reference:** Two radio buttons, 'IOR' (selected) and 'From file'. A 'Browse...' button is next to the 'From file' option. Below these is a text input field.
- Properties Table:**

Property	Value
<input checked="" type="checkbox"/> bldg	
<input checked="" type="checkbox"/> color	
<input checked="" type="checkbox"/> cost_per_page	
<input checked="" type="checkbox"/> ppm	
<input checked="" type="checkbox"/> queue	
- Buttons:** 'Add...', 'Dynamic...', and 'Reset' buttons are located to the right of the Properties table. 'OK' and 'Cancel' buttons are at the bottom of the dialog.

2. Select a service type from the drop-down list. Each time you select a service type, the **Properties** table is updated to reflect the properties defined for that service type.
3. Select a method for specifying the object reference for this offer. Select the **IOR** toggle if you want to paste the stringified interoperable object reference into the text box. If you want the application to read the reference from a file, select **From file** and enter the filename in the text box, or click the **Browse...** button to display a file selection dialog box. If the trader service is configured to allow `nil` objects, and you do not wish to specify an object reference for this offer, you may leave the object reference blank.
4. Enter values for the properties in the **Properties** table. All properties have a checkbox to the left of the property name. For a mandatory property, the checkbox is disabled, meaning that a value must be provided for this property. For an optional property, you can use the checkbox to indicate whether this property should be included with the offer. To enter a value

for a property, double-click on the property value field. For properties with sequence types, you can enter multiple values by separating them with commas. Press **Return** when you are finished entering the value for a property.


5. Click the **Add...** button if you wish to add a property that is not defined by the service type. The **Add Property** dialog box appears as shown below. Enter a name for the property, select the property's type from the drop-down list, and enter a value in the text box. The name you use for the property must not be the same as any existing properties. Click **OK** to add the property to the **Properties** table.



Note: Once the property has been added to the **Properties** table, you can edit it directly, just as you can with any other property. If you later decide that you do not want to include the property with the offer, simply uncheck the property's checkbox.

6. If you wish to make a property dynamic, select the property and click the **Dynamic...** button. The **Dynamic Property** dialog box appears as shown below. Select a method for specifying an object reference as outlined in step 3 above. If you wish to include additional data, select a type from the

drop-down list and enter a value in the text box. Click **OK** to save the dynamic property. The property table displays <dynamic> as the value of a dynamic property.



7. To clear the value of a property, select the property and click **Reset**. You can use this command to convert a property from a dynamic property to a regular property.
8. Click **OK** to add the new offer. The application validates the information and reports any errors in a dialog box.


Note: For properties of type `string`, an empty value is accepted as a valid value, even for mandatory properties.

Modifying an offer

To modify an offer, do the following:

1. Select **View/Offers** to display the offers in the item list.
2. Select the offer you wish to modify.

3. Select **Edit/Modify**. The **Edit Offer** dialog box appears as shown below.



4. You can modify a property by double-clicking on the property value. Press **Return** when you have finished editing a property value.
5. You can remove an existing property from the offer (if it is an optional property) by unchecking its checkbox. Similarly, you can add a property to the offer by checking its checkbox and entering a value for the property.
6. See the discussion of adding a new offer above for details on adding new properties and configuring dynamic properties.
7. Click **OK** to update the offer.


Withdrawing offers

There are two distinct ways to withdraw offers. The first way is by selecting individual offers, as outlined below:

1. Select **View/Offers** to display the offers in the item list.
2. Select the offer(s) you wish to withdraw.
3. Select **Edit/Delete**. A confirmation dialog appears.
4. Click **Yes** to withdraw the offers.

The above method is suitable for withdrawing a limited number of specific offers. A more efficient method for removing a large quantity of offers for a single type, or for removing offers without having to manually search for the right ones, is by withdrawing offers with a constraint expression:

1. Select **Tools/Withdraw Offers**. The **Withdraw Offers** dialog box appears as shown below.



2. Select the service type from the drop-down list. Offers with this service type or a subtype of this service type are considered for withdrawal.
3. Enter a constraint expression in the text box. See [“Service Types” on page 4](#) for more information on constraint expressions.
4. Click **OK** to withdraw the offers. Only offers that match the constraint expression are withdrawn. An error message appears if no matching offers were found.

Note: A simple way to remove all of the offers for a service type is to use **TRUE** for the constraint expression.

Managing Proxy Offers

Adding a new proxy offer

To add a new proxy offer, do the following:

1. Select **Insert/Proxy Offer**. The **New Proxy Offer** dialog box appears as shown below.

The screenshot shows the 'New Proxy Offer' dialog box. The 'Service type:' dropdown is set to 'Printer'. The 'Target Lookup IOR' radio button is selected. The 'Properties' table is as follows:

Property	Value
<input checked="" type="checkbox"/> bldg	
<input checked="" type="checkbox"/> color	
<input checked="" type="checkbox"/> cost_per_page	
<input checked="" type="checkbox"/> ppm	
<input checked="" type="checkbox"/> queue	

2. Select a service type from the drop-down list. Each time you select a service type, the property table is updated to reflect the properties defined for that service type.
3. Select a method for specifying the object reference of the target `CosTrading::Lookup` object for this proxy offer. Select the **IOR** toggle if you want to paste the stringified interoperable object reference into the text

- box. If you want the application to read the reference from a file, select **From file** and enter the filename in the text box, or click the **Browse...** button to display a file selection dialog box.
4. Enter the constraint recipe in the text box.
 5. Select **If match all** if a matching service type is all that is required for this proxy offer to be considered a match during a query.
 6. Enter values for the properties in the **Properties** table. See [“Adding a new offer” on page 93](#) for more information on entering offer properties.
 7. Use the **Add...**, **Edit...** and **Delete** buttons to manipulate the policies to be passed on to the target object. Clicking the **Add...** or **Edit...** buttons displays the **Policy** dialog box as shown below.

8. Click **OK** to add the new proxy offer. The application validates the information and reports any errors in a dialog box.

Withdrawing proxy offers

To withdraw a proxy offer, do the following:


1. Select **View/Proxy Offers** to display the proxy offers in the item list.
2. Select the proxy offer you wish to withdraw.
3. Select **Edit/Delete**. A confirmation dialog appears.
4. Click **Yes** to withdraw the proxy offer.

Managing Links

Adding a new link

To add a new link, do the following:

1. Select **Insert/Link**. The **New Link** dialog box appears as shown below.



2. Enter a name for this link in the text box.
3. Select a method for specifying the target trader's object reference for this link. Select the **IOR** toggle if you want to paste the stringified interoperable object reference into the text box. If you want the application to read the reference from a file, select **From file** and enter the filename in the text box, or click the **Browse...** button to display a file selection dialog box.
4. Select the appropriate link-follow rules from the drop-down lists.
5. Click **OK** to add the new link.

Modifying a link

To modify a link, do the following:

1. Select **View/Links** to display the links in the item list.
2. Select the link you wish to modify.
3. Select **Edit/Modify**. The **Edit Link** dialog box appears.
4. Update the settings for the link-follow rules.
5. Click **OK** to update the link.

Removing a link


To remove a link, do the following:

1. Select **View/Links** to display the links in the item list.
2. Select the link you wish to remove.
3. Select **Edit/Delete**. A confirmation dialog appears.
4. Click **Yes** to remove the link.

Configuring the Trader Attributes

Configuring attributes

To configure the trader attributes, select **Tools/Attributes**. The **Attributes** dialog box appears, containing a tabbed folder with four tabs.



The tabs provide access to the attributes from the following four IDL interfaces:

- `CosTrading::SupportAttributes`
- `CosTrading::ImportAttributes`
- `CosTrading::LinkAttributes`
- `CosTrading::Admin`

Each of the tabs is described below. Click **OK** when you have finished modifying the attributes.

Support Attributes

Supports modifiable properties

If enabled, the trader considers offers with modifiable properties (that is, properties that are not read-only) during a query, unless the importer requests otherwise with the `use_modifiable_properties` policy. If disabled, the trader does not consider offers with modifiable properties, regardless of the importer's wishes. This setting also determines the behavior of the `modify` operation in the `CosTrading::Register` interface. If enabled, the server allows modification of offers. If disabled, the `modify` operation raises the `NotImplemented` exception.

Supports dynamic properties

If enabled, the trader considers offers with dynamic properties during a query, unless the importer requests otherwise with the `use_dynamic_properties` policy. If disabled, the trader does not consider offers with dynamic properties, regardless of the importer's wishes. The trading service specification does not define the behavior of a trader when this option is disabled and an offer is exported that contains dynamic properties; however, the Trader Service always accepts offers containing dynamic properties.

Supports proxy offers

If enabled, the trader considers proxy offers during a query, unless the importer requests otherwise with the `use_proxy_offers` policy. If disabled, the trader does not consider proxy offers, regardless of the importer's wishes. This setting also determines the behavior of the `proxy_if` attribute in the `CosTrading::SupportAttributes` interface. If enabled, `proxy_if` returns the reference of the server's `CosTrading::Proxy` object. If disabled, `proxy_if` returns `nil`.

Service type repository

The IOR of the service type repository currently in use by the trader is displayed in the text box. In order to change the service type repository, you first need to select a method for specifying its object reference. Select the **IOR** toggle if you want to paste the stringified IOR into the text box. If you want the application to read the reference from a file, select **From file** and enter the filename in the text box, or click the **Browse...** button to display a file selection dialog box.

Import Attributes

Import attributes

Many of the Import attributes have default and maximum values. The default value is used if an importer does not supply a value for the corresponding importer policy. The maximum value is used as the allowable upper limit for the importer policy. If an importer supplies a policy value that is greater than the maximum value, the importer's policy value is overridden and the maximum value is used instead.

	Default	Maximum
Search cardinality	2147483647	2147483647
Match cardinality	2147483647	2147483647
Return cardinality	2147483647	2147483647
Link hop count	2147483647	2147483647
Link follow policy	Always	Always
Maximum list count	2147483647	

Search cardinality

The number of offers to be searched during a query. The corresponding importer policy is `search_card`.

Match cardinality

The number of matched offers to be ordered during a query. The corresponding importer policy is `match_card`.

Return cardinality

The number of ordered offers to be returned by a query. The corresponding importer policy is `return_card`.

Link hop count

The depth of links to be traversed during a query. The corresponding importer policy is `hop_count`.

Link follow policy

The trader's behavior when considering whether to follow a link during a query. The default value is used if an importer does not specify a value for the `link_follow_rule` policy. The maximum value overrides the policy established for a link as well as the `link_follow_rule` policy proposed by an importer.


Maximum list count

The maximum number of items to be returned from any operation that returns a list, such as the `list_offers` operation in `CosTrading:Admin` or the `next_n` operation in `CosTrading:OfferIterator`. This attribute may override the number of items requested by a client.

Link Attributes

Link attributes

The following is the Link Attributes pane.




Maximum link follow policy

Determines the server's upper bound on the value of a link's limiting follow rule at the time of creation or modification of a link. The server raises the `LimitingFollowTooPermissive` exception if a link's limiting follow rule exceeds the value of this attribute.

Admin Attributes

Admin attributes

The following is the Admin attributes pane.



Request identifier stem


The request identifier stem is used as a prefix by the server to generate unique request identifiers during a federated query. Although the IDL attribute `request_id_stem` returns a sequence of octets, this property is defined in terms of a string, with the characters of the string comprising the octets of the stem. You need to provide a value for this property only if the server will have links to other traders and you want to ensure that circular links are handled correctly.

Executing Queries

Executing a query

To execute a query, do the following:

1. Select **Tools/Query**. The **Query** dialog box appears as shown below.




2. Select a service type from the drop-down list.
3. Enter a constraint expression in the **Constraint** text box.
4. (Optional) Enter a preference expression in the **Preference** text box. If this field is blank, the trader uses a default preference expression of "first".
5. If you wish to specify which properties are returned in the matching offers, click **Desired properties** to activate the text box below and enter the names of the properties in the text box. Use commas to separate the property names.

- To include importer policies, click the **Policies...** button. The **Policies** dialog box appears as shown below. Next to each field label is a checkbox. You must check the box for a policy for it to be included in your query. Click the **Defaults** button to load the trader's default import attributes into the fields of the dialog box. Click **OK** to accept your changes.

Policy	Value	Action
<input type="checkbox"/> Exact type match	No	OK
<input type="checkbox"/> Use modifiable properties	Yes	Cancel
<input type="checkbox"/> Use dynamic properties	Yes	Defaults
<input type="checkbox"/> Use proxy offers	Yes	
<input type="checkbox"/> Search cardinality	2147483647	
<input type="checkbox"/> Match cardinality	2147483647	
<input type="checkbox"/> Return cardinality	2147483647	
<input type="checkbox"/> Link follow policy	Always	
<input type="checkbox"/> Link hop count	2147483647	

- Click **Query** to execute the query operation. If matching offers were found, the **Query Results** dialog box appears as shown below. You can scroll through the matching offers with the < and > buttons. Click **Close** when you have finished examining the results.



Note: The Query Results dialog box cannot be used to edit offers.

Connecting to a New Trader

Connecting to a new trader

When the console is started, the first console window to appear is already connected to the trader you specified using the command line options. If you are managing multiple traders, you can connect to a different trader with the **Console/Connect** command. The **Connect** dialog appears as shown below.



There are three methods of connecting to the trader.

1. To provide the stringified object reference, select the **Trader IOR** option and paste the IOR into the text box.
2. To obtain the stringified object reference from a file, select **IOR from file** and enter the filename in the text box, or click the **Browse...** button to display a file selection dialog box.
3. To connect to a linked trader, select the **Link** option and choose the link from the drop-down list.

Click **OK** to connect to the trader. The contents of the current console window are updated to reflect the new trader.

Note: If you want to be connected to two or more traders at the same time, use the **Console/New Window** command to create a new console window, then select **Console/Connect** to connect the new window to another trader.

The OMG Constraint Language

This appendix provides the BNF specification of the CORBA standard constraint language (reproduced from Annex B in the OMG Trading Object Specification with the kind permission of the OMG). It is used for specifying both the constraint and preference expression parameters to various operations in the trader interfaces.

In this appendix

This appendix contains the following sections:

Introduction	page 114
Language Basics	page 115
The Constraint Language BNF	page 118

Introduction

Statement

A statement in this language is an `Istring`. Other constraint languages may be supported by a particular trader implementation; the constraint language used by a client of the trader is indicated by embedding “`<<Identifier major.minor>>`” at the beginning of the string. If such an escape is not used, it is equivalent to embedding “`<<OMG 1.0>>`” at the beginning of the string.

Language Basics

Basic elements

Both the constraint and preference expressions in a query can be constructed from property names of conforming offers and literals. The constraint language in which these expressions are written consists of the following items (examples of these expressions are shown in square brackets below each bulleted item):

- Comparative functions:

`==` (equality)

`!=` (inequality)

`>`, `>=`, `<`, `<=`

`~` (substring match),

`in` (element in sequence)

The result of applying a comparative function is a `boolean` value. [`Cost < 5`] implies only consider offers with a `Cost` property value less than 5; [`'visa' in CreditCards`] implies only consider offers in which the `CreditCards` property, consisting of a set of strings, contains the string `'visa'`]

- Boolean connectives:

`and`

`or`

`not`

[`Cost >= 2 and Cost <= 5`] implies only consider offers where the value of the `Cost` property is in the range `2 <= Cost <= 5`]

- Property existence:

`exist`

- Property names
- Numeric and string constants
- mathematical operators:

`+`, `-`, `*`, `/`

[`10 < 12.3 * MemSize + 4.6 * FileSize`] implies only consider offers for which the arithmetic function in terms of the value of the `MemSize` and `FileSize` properties exceeds 10]

- grouping operators:

()

Note that the keywords in the language are case sensitive.

Precedence relations

The following precedence relations hold in the absence of parentheses, in the order of highest to lowest:

```
( ) exist unary-minus
not
* /
+ -
~
in
== != < <= > >=
and
or
```

Legal property value types

While one can define properties of service types with arbitrarily complex IDL value types, only the following property value types can be manipulated using the constraint language:

- `boolean`, `short`, `unsigned short`, `long`, `unsigned long`, `float`, `double`, `char`, `Ichar`, `string`, `Istring`
- sequences of the above types

The `exist` operator can be applied to any property name, regardless of the property's value type.

Operator restrictions

<code>exist</code>	can be applied to any property
<code>~</code>	can only be applied if left operand and right operand are both strings or both <code>Istrings</code>
<code>in</code>	can only be applied if the left operand is one of the simple types described above and the right operand is a sequence of the same simple type
<code>==</code>	can only be applied if the left and right operands are of the same simple type
<code>!=</code>	can only be applied if the left and right operands are of the same simple type

<	can only be applied if the left and right operands are of the same simple type
<=	can only be applied if the left and right operands are of the same simple type
>	can only be applied if the left and right operands are of the same simple type
>=	can only be applied if the left and right operands are of the same simple type
+	can only be applied to simple numeric operands
-	can only be applied to simple numeric operands
*	can only be applied to simple numeric operands
/	can only be applied to simple numeric operands

The comparative functions <, <=, >, >= imply use of the appropriate collating sequence for characters and strings; `TRUE` is greater than `FALSE` for booleans.

Representation of literals

boolean	<code>TRUE</code> or <code>FALSE</code>
integers	sequences of digits, with a possible leading + or -
floats	digits with decimal point, with optional exponential notation
characters	<code>char</code> and <code>Ichar</code> are of the form ' <code><char></code> ', <code>string</code> and <code>Istring</code> are of the form ' <code><char><char>+</code> '; to embed an apostrophe in a string, place a backslash (<code>\</code>) in front of it; to embed a backslash in a string, use <code>\\</code> .

The Constraint Language BNF

The constraint language proper in terms of lexical tokens

```

<constraint> := /* empty */
  | <bool>

<preference> := /* <empty> */
  | min <bool>
  | max <bool>
  | with <bool>
  | random
  | first

<bool> := <bool_or>

<bool_or> := <bool_or> or <bool_and>
  | <bool_and>

<bool_and> := <bool_and> and <bool_compare>
  | <bool_compare>

<bool_compare> := <expr_in> == <expr_in>
  | <expr_in> != <expr_in>
  | <expr_in> < <expr_in>
  | <expr_in> <= <expr_in>
  | <expr_in> > <expr_in>
  | <expr_in> >= <expr_in>
  | <expr_in>

<expr_in> := <expr_twiddle> in <Ident>
  | <expr_twiddle>

<expr_twiddle> := <expr> ~ <expr>
  | <expr>

<expr> := <expr> + <term>
  | <expr> - <term>
  | <term>

<term> := <term> * <factor_not>
  | <term> / <factor_not>
  | <factor_not>

<factor_not> := not <factor>
  | <factor>

```

```

<factor> := ( <bool_or> )
| exist <Ident>
| <Ident>
| <Number>
| - <Number>
| <String>
| TRUE
| FALSE

```

**“BNF” for lexical tokens up to
character set issues**

```

<Ident> := <Leader> <FollowSeq>

<FollowSeq> := /* <empty> */
| <FollowSeq> <Follow>

<Number> := <Mantissa>
| <Mantissa> <Exponent>

<Mantissa> := <Digits>
| <Digits> .
| . <Digits>
| <Digits> . <Digits>

<Exponent> := <Exp> <Sign> <Digits>

<Sign> := +
| -

<Exp> := E
| e

<Digits> := <Digits> <Digit>
| <Digit>

<String> := ' <TextChars> '

<TextChars> := /* <empty> */
| <TextChars> <TextChar>

<TextChar> := <Alpha>
| <Digit>
| <Other>
| <Special>

<Special> := \\
| \'

```

Character set issues

The previous BNF has been complete up to the non-terminals <Leader>, <Follow>, <Alpha>, <Digit>, and <Other>. For a particular character set, one must define the characters which make up these character classes.

Each character set which the trading service is to support must define these character classes. This annex defines these character classes for the ASCII character set.

```
<Leader> := <Alpha>
```

```
<Follow> := <Alpha>  
          | <Digit>  
          | -
```

<Alpha> is the set of alphabetic characters [A-Za-z]

<Digit> is the set of digits [0-9]

<Other> is the set of ASCII characters that are not <Alpha>, <Digit>, or <Special>

Glossary

A

ART

Adaptive Runtime Technology. IONA's modular, distributed object architecture, which supports dynamic deployment and configuration of services and application code. ART provides the foundation for IONA software products.

C

CFR

See [configuration repository](#).

client

An application (process) that typically runs on a desktop and requests services from other applications that often run on different machines (known as server processes). In CORBA, a client is a program that requests services from CORBA objects.

configuration

A specific arrangement of system elements and settings.

configuration domain

Contains all the configuration information that Orbix ORBs, services and applications use. Defines a set of common configuration settings that specify available services and control ORB behavior. This information consists of configuration variables and their values. Configuration domain data can be implemented and maintained in a centralised Orbix configuration repository or as a set of files distributed among domain hosts. Configuration domains let you organise ORBs into manageable groups, thereby bringing scalability and ease of use to the largest environments. See also [configuration file](#) and [configuration repository](#).

configuration file

A file that contains configuration information for Orbix components within a specific configuration domain. See also [configuration domain](#).

configuration repository

A centralised store of configuration information for all Orbix components within a specific configuration domain. See also [configuration domain](#).

configuration scope

Orbix configuration is divided into scopes. These are typically organized into a root scope and a hierarchy of nested scopes, the fully-qualified names of which map directly to ORB names. By organising configuration properties into various scopes, different settings can be provided for individual ORBs, or common settings for groups of ORB. Orbix services, such as the naming service, have their own configuration scopes.

CORBA

Common Object Request Broker Architecture. An open standard that enables objects to communicate with one another regardless of what programming language they are written in, or what operating system they run on. The CORBA specification is produced and maintained by the OMG. See also [OMG](#).

CORBA objects

Self-contained software entities that consist of both data and the procedures to manipulate that data. Can be implemented in any programming language that CORBA supports, such as C++ and Java.

D**deployment**

The process of distributing a configuration or system element into an environment.

I**IDL**

Interface Definition Language. The CORBA standard declarative language that allows a programmer to define interfaces to CORBA objects. An IDL file defines the public API that CORBA objects expose in a server application. Clients use these interfaces to access server objects across a network. IDL interfaces are independent of operating systems and programming languages.

IFR

See [interface repository](#).

IIOP

Internet Inter-ORB Protocol. The CORBA standard messaging protocol, defined by the OMG, for communications between ORBs and distributed applications. IIOP is defined as a protocol layer above the transport layer, TCP/IP.

implementation repository

A database of available servers, it dynamically maps persistent objects to their server's actual address. Keeps track of the servers available in a system and the hosts they run on. Also provides a central forwarding point for client requests. See also [location domain](#) and [locator daemon](#).

IMR

See [implementation repository](#).

installation

The placement of software on a computer. Installation does not include configuration unless a default configuration is supplied.

Interface Definition Language

See [IDL](#).

interface repository

Provides centralised persistent storage of IDL interfaces. An Orbix client can query this repository at runtime to determine information about an object's interface, and then use the Dynamic Invocation Interface (DII) to make calls to the object. Enables Orbix clients to call operations on IDL interfaces that are unknown at compile time.

invocation

A request issued on an already active software component.

IOR

Interoperable Object Reference. See [object reference](#).

L**location domain**

A collection of servers under the control of a single locator daemon. Can span any number of hosts across a network, and can be dynamically extended with new hosts. See also [locator daemon](#) and [node daemon](#).

locator daemon

A server host facility that manages an implementation repository and acts as a control center for a location domain. Orbix clients use the locator daemon, often in conjunction with a naming service, to locate the objects they seek. Together with the implementation repository, it also stores server process data for activating servers and objects. When a client invokes on an object, the client ORB sends this invocation to the locator daemon, and the locator daemon searches the implementation repository for the address of the server object. In addition, enables servers to be moved from one host to another without disrupting client request processing. Redirects requests to the new location and transparently reconnects clients to the new server instance. See also [location domain](#), [node daemon](#), and [implementation repository](#).

N**naming service**

An implementation of the OMG Naming Service Specification. Describes how applications can map object references to names. Servers can register object references by name with a naming service repository, and can advertise those names to clients. Clients, in turn, can resolve the desired objects in the naming service by supplying the appropriate name. The Orbix naming service is an example.

node daemon

Starts, monitors, and manages servers on a host machine. Every machine that runs a server must run a node daemon.

O**object reference**

Uniquely identifies a local or remote object instance. Can be stored in a CORBA naming service, in a file or in a URL. The contact details that a client application uses to communicate with a CORBA object. Also known as interoperable object reference (IOR) or proxy.

OMG

Object Management Group. An open membership, not-for-profit consortium that produces and maintains computer industry specifications for interoperable enterprise applications, including CORBA. See www.omg.com.

ORB

Object Request Broker. Manages the interaction between clients and servers, using the Internet Inter-ORB Protocol (IIOP). Enables clients to make requests and receive replies from servers in a distributed computer environment. Key component in CORBA.

P**POA**

Portable Object Adapter. Maps object references to their concrete implementations in a server. Creates and manages object references to all objects used by an application, manages object state, and provides the infrastructure to support persistent objects and the portability of object implementations between different ORB products. Can be transient or persistent.

protocol

Format for the layout of messages sent over a network.

S**server**

A program that provides services to clients. CORBA servers act as containers for CORBA objects, allowing clients to access those objects using IDL interfaces.

T**trader service**

An implementation of the OMG CORBA Trading Object Service Specification. Facilitates the offering and the discovery of services. Other objects can use it to advertise their capabilities and to match their needs against those of advertised services.

Index

A

`add_link()`
 usage 79
Admin interface
 in OMG stand-alone trader 10
administration
 setting Trader policies 57
advertising services 59

B

basic query 36
BNF specification, constraint language 113

C

connecting to Trader 64
constraint parameter, `query()` 37
constraints 41
 and IDL data types 41
 arithmetic expressions 42
 comparing property values 41
 connecting expressions together 42
 testing whether property exists 42
 when withdrawing offers 68
CORBA 113
CORBA Trading Object Service 1
creating service type properties 70

D

`describe()`
 usage 65
`describe_type()` 72
dynamic properties 74
 setting for a service offer 74, 76

E

`exact_type_match` policy
 usage 37
`export()`
 usage 64
 usage, with a dynamic property 75
export an offer 2

exporting service offers 59, 63

F

federated traders 34, 78
FollowOption type
 usage 79
full-service trader 10
`fully_describe_type()` 72

H

`hop_count` policy 51
`how-many-offers` parameter, `query()` 37

I

IDL data types and constraints 41
initialising service offer properties 61
iterator parameter, `query()` 39

K

kinds of traders 9

L

`limits_applied` parameter, `query()` 40
linked trader 10, 34
linked traders 78
 setting policies for 78
Link interface
 in OMG linked trader 10
LinkNameSeq sequence
 usage 80
`list_links()`
 usage 80
`list_offers()` 65
`list_types()` 72
Lookup interface
 in OMG query trader 9

M

mandatory properties 62
`mask_type()` 72
`match_card` policy 51

max_search_card policy 40
 modes 62
 setting 71
 modify()
 usage 66
 modifying service offers 66
 multiple service offers, withdrawing 68

N

_narrow(), usage 64
 narrowing object reference 64

O

object reference, to Trader 36
 object reference narrowing 64
 OfferInfo structure
 usage 65
 OfferIterator type
 usage 39
 offers parameter, query() 39

P

plugins:trader:direct_persistence 20
 plugins:trader:iioport:port 20
 policies 49
 set in a query 52
 setting for a trader 57
 setting for linked traders 78
 that affect queries 51
 that affect trader functionality 54
 using in a query 55
 you can set, with data types 56
 preference parameter, query() 37
 properties of service offers
 modifying 66
 property modes, setting 71
 PropertyNameSeq sequence
 usage 47, 66
 PropertySeq sequence
 usage 61
 PROP_MANDATORY mode 71
 PROP_MANDATORY_READONLY mode 71
 PROP_NORMAL mode 71
 PROP_READONLY mode 71
 PropStructSeq sequence
 usage 71
 Proxy interface
 in OMG proxy trader 10

proxy trader 10

Q

query
 basics 36
 forming constraints 41
 limiting returned properties 46
 results of 39
 setting policies 52
 query()
 input parameters to 36
 output from 39
 usage 47
 querying for service offers 33
 query processing by Trader 34
 query trader 9

R

readonly properties 62
 changing 67
 Register interface
 in OMG simple trader 9
 remove_link()
 usage 80
 remove_type() 72
 resolve_initial_references()
 usage 64
 return_card policy 51
 return-properties parameter, query() 37

S

search_card policy 51
 searching for offers 49
 selecting a service 39
 sequence of offers 40
 service offers 2
 exporting and managing 59
 exporting to Trader 63
 initialising properties 61
 modifying 66
 multiple withdraw 68
 querying for 33
 setting dynamic properties 74, 76
 sorting 44
 withdrawing from Trader 68
 service type name parameter, query() 37
 ServiceTypeNameSeq sequence
 usage 71

- Service Type Repository 2, 72
- ServiceTypeRepository interface
 - usage 70
- service types 2
 - adding 71
 - adding to Trader 70
 - creating properties for 70
 - definition 4
 - hiding 72
 - masking 72
 - supertypes 71
- set_def_follow_policy()
 - usage 79
- set_def_hop_count()
 - usage 79
- set_max_follow_policy()
 - usage 79
- set_max_hop_count()
 - usage 79
- set_max_link_follow_policy()
 - usage 79
- set_supports_modifiable_properties() 67
- set_type_repos() 73
- simple trader 9
- sorting service offers 37, 44
 - ascending 45
 - by constraint 45
 - decending 45
 - in random order 45
- SpecifiedProps union
 - usage 46
- stand-alone trader 10
- supertypes, of service types 71
- SupportAttributes
 - supports_dynamic_properties policy 54
 - supports_proxy_offers policy 54
 - upports_modifiable_properties policy 54
- SupportAttributes interface 54
- supports_dynamic_properties policy 54
- supports_modifiable_properties policy 54, 67
- supports_proxy_offers policy 54

T

- Trader
 - as OMG linked trader 10
 - connecting to 36, 64
 - multiple traders 78
 - policies to set 57
 - processing a query 34

- usage by clients and servers 2
- Trader Console 81
- traders
 - links between 78
- traders, kinds of 9
- typecodes 71
- type_repos attribute 73
- types of traders 9

U

- unmask_type() 72
- use_dynamic_properties policy 54
- use_modifiable_properties policy 54
- use_proxy_offers policy 54

W

- withdraw()
 - usage 68
- withdrawing service offers 68
- withdraw multiple offers 68
- withdraw_using_constraint()
 - usage 68

