

Artix® ESB

Bindings and Transports, C++ Runtime

Version 5.5 December 2008

Bindings and Transports, C++ Runtime

Version 5.5

Published 12 Feb 2009 Copyright © 2008 IONA Technologies PLC, a wholly-owned subsidiary of Progress Software Corporation.

Legal Notices

Progress Software Corporation and/or its subsidiaries may have patents, patent applications, trademarks, copyrights, or other intellectual property rights covering subject matter in this publication. Except as expressly provided in any written license agreement from Progress Software Corporation, the furnishing of this publication does not give you any license to these patents, trademarks, copyrights, or other intellectual property. Any rights not expressly granted herein are reserved.

Progress, IONA, IONA Technologies, the IONA logo, Orbix, High Performance Integration, Artix;, FUSE, and Making Software Work Together are trademarks or registered trademarks of Progress Software Corporation and/or its subsidiaries in the US and other countries.

Java and J2EE are trademarks or registered trademarks of Sun Microsystems, Inc. in the United States and other countries. CORBA is a trademark or registered trademark of the Object Management Group, Inc. in the US and other countries. All other trademarks that appear herein are the property of their respective owners.

While the information in this publication is believed to be accurate Progress Software Corporation makes no warranty of any kind to this material including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose. Progress Software Corporation shall not be liable for errors contained herein, or for incidental or consequential damages in connection with the furnishing, performance or use of this material.

All products or services mentioned in this manual are covered by the trademarks, service marks, or product names as designated by the companies who market those products.

No part of this publication may be reproduced, stored in a retrieval system or transmitted, in any form or by any means, photocopying, recording or otherwise, without prior written consent of IONA Technologies PLC. No third-party intellectual property right liability is assumed with respect to the use of the information contained herein. IONA Technologies PLC assumes no responsibility for errors or omissions contained in this publication. This publication and features described herein are subject to change without notice. Portions of this document may include Apache Foundation documentation, all rights reserved.

Table of Contents

Preface	13
What is Covered in This Book	14
Who Should Read This Book	15
How to Use This Book	
The Artix ESB Documentation Library	17
I. Bindings	19
Understanding Bindings in WSDL	23
Using SOAP 1.1 Messages	25
Adding a SOAP 1.1 Binding	
Adding SOAP Headers to a SOAP 1.1 Binding	
Using SOAP 1.2 Messages	
Adding a SOAP 1.2 Binding	
Adding Headers to a SOAP 1.2 Message	
Sending Binary Data Using SOAP with Attachments	45
Sending Binary Data with SOAP MTOM	
Defining Data Types to use MTOM	
Enabling MTOM	
Using Tuxedo's FML Buffers	
Using XML Documents	
Using Fixed Length Records	
Using Tagged Data	
Using RMI	
Using Tibco Rendezvous Messages	
Defining a TibrvMsg Binding	
Default Mappings for TibrvMsg	
Defining Array Mapping Policies	
Defining a Custom TibrvMsg Mapping	
Adding Context Information to a TibrvMsg	
Using the Pass Through Binding	
II. Transports	
Understanding How Endpoints are Defined in WSDL	
Using HTTP	
Configuring an HTTP Endpoint to a Contract	
Introduction	
Specifying a Username and a Password	
Configuring Keep-Alive Behavior	
Managing Cookies in Artix Clients	
Using the Java Messaging System	

Defining a JMS Endpoint	170
Introduction	
Basic Endpoint Configuration	
Client Endpoint Configuration	176
Server Endpoint Configuration	
Using the Command Line Tool	
Migrating to the 4.x JMS WSDL Extensions	181
Using ActiveMQ as Your JMS Provider	
Using IIOP	183
Using FTP	187
Adding an FTP Endpoint	
Coordinating Requests and Responses	190
Introduction	
Implementing the Client's Coordination Logic	
Implementing the Server's Coordination Logic	196
Using Properties to Control Coordination Behavior	201
Using WebSphere MQ	205
Adding a WebSphere MQ Endpoint	
Websphere MQ Connection Settings	212
Specifying the WebSphere Library to Load	213
Using Queues on Remote Hosts	215
Setting a Value of the Message Descriptor's Format Field	
Using TIBCO Rendezvous	219
Using Tuxedo	
III. Other Artix ESB Features	229
Working with CORBA	
Adding a CORBA Binding	234
Creating a CORBA Endpoint	240
Procedure	241
Configuring an Artix CORBA Endpoint	242
Generating CORBA IDL	246
Using the Artix Transformer	
Using the Artix Transformer as a Service	250
Using Artix to Facilitate Interface Versioning	252
WSDL Messages and the Transformer	257
Writing XSLT Scripts	260
Elements of an XSLT Script	261
XSLT Templates	263
Common XSLT Functions	269
Using Codeset Conversion	
Index	

List of Figures

	Artix Cookie Processing	167
2.	MQ Remote Queues	216

List of Tables

1. soap12:header Attributes	39
2. mime:content Attributes	
3. FML Type Support	55
4. Attributes of the FML Binding's Field Element	60
5. Attributes for fixed:binding	
6. Attributes for fixed:body	72
7. Attributes Used to Define a Tagged Binding	88
8. Attributes for tagged:operation	
9. Attributes for tagged:field	90
10. Attributes for tagged:sequence	92
11. Attributes for tagged:choice	93
12. Attributes for tibrv:binding	107
13. Attributes for tibrv:input	108
14. Attributes for tibrv:output	109
15. TIBCO to XSD Type Mapping	
16. Effect of tibrv:array	117
17. Attributes for tibrv:array	118
18. Functions Used for Specifying TibrvMsg Array Element	
Names	
19. Valid Casts for TibrvMsg Binding	
20. Attributes for tibrv:msg	
21. Attributes for tibrv:field	
22. Options for Adding an HTTP Endpoint	
23. Settings for CacheControl on an HTTP Server Endpoint	
24. Settings for CacheControl on HTTP Client Endpoint	
25. JMS Port Attributes	
26. Attributes for Configuring a JMS Client Endpoint	176
27. Attributes for COnfiguring a JMS Server Endpoint	
28. Command Line Options for Creating a JMS Endpoint	
29. Options for Adding a WebSphere MQ Endpoint	
30. WebSphere MQ Server_Client Attribute Settings	
31. WebSphere MQ Format Attribute Settings	
32. Supported TIBCO Rendezvous Features	
33. Options for Adding a TIB/RV Endpoint	
34. Options for Adding a Tuxedo Service	
35. Options for Adding a CORBA Binding	
36. Attributes of corba:param	
37. Options for Adding a CORBA Endpoint	244
38. Options for Generating IDL	
39. Attributes for the i18n-context:server Element	
40 Attributes for the i18n-context-client Flement	273

List of Examples

1. Ordering System Interface	27
2. SOAP 1.1 Binding for orderWidgets	
3. SOAP Header Syntax	29
4. SOAP 1.1 Binding with a SOAP Header	30
5. SOAP 1.1 Binding for orderWidgets with a SOAP Header	32
6. Ordering System Interface	37
7. SOAP 1.2 Binding for orderWidgets	38
8. SOAP Header Syntax	
9. SOAP 1.2 Binding with a SOAP Header	40
10. SOAP 1.2 Binding for orderWidgets with a SOAP Header	42
11. MIME Namespace Specification in a Contract	45
12. Contract using SOAP with Attachments	47
13. Message for MTOM Using XML Schema Types	50
14. Using XMime Attributes to Specify the Contents of a Binary	
Field	
15. Message for MTOM Using MIME Binary Types	
16. Configuration for Enabling MTOM	
17. personnelInfo Field Table File	57
18. personnelInfo C++ header	
19. Logical description of personnelnfo FML buffer	
20. personnelInfo Lookup Interface	
21. Flattened Message for FML	
22. personalInfo FML binding	
23. Valid XML Binding Message	
24. Invalid XML Binding Message	
25. Invalid XML Document	65
26. XML Binding with rootNode set	
27. XML Document generated using the rootNode attribute	
28. Using xformat:body	
29. Fixed String Message	
30. Fixed String Mapping	
31. Fixed Record Numeric Message	74
32. Mapping Numerical Data to a Fixed Binding	
33. Fixed Date Message	
34. Fixed Format Date Mapping	
35. fixedValue Mapping	
36. Enumeration Logical Mapping	
37. Fixed Ice Cream Mapping	
38. Using the discriminatorName Attribute	
39. Mapping a Union to a Fixed Record Length Message	
40 Using counterName	81

	Mapping a Sequence to a Fixed Record Length Message	
42.	Fixed Record Length Message Binding	82
	Ice Cream Enumeration	
44.	Tagged Data Ice Cream Mapping	91
45.	Mapping a Sequence to a Tagged Data Format	92
46.	Mapping a Union to a Tagged Data Format	94
47.	Tagged Data Format Binding	95
48.	RMI Endpoint	100
	Service for Using RMI	
50.	Client Using RMI	102
51.	Default TibrvMsg Binding	110
52.	TibrvMsg Binding with Array Policies Set	119
	TibrvMsg Contract Elements	
	Casting in a TibrvMsg Binding	
55.	TibrvMsg Binding with Binding-only Elements	127
56.	TibrvMsg with a Header	127
	Default TibrvMsg Example	
58.	TibrvMsg with added TibrvMsg Example	129
59.	TibrvMsg Binding with an Added Binding-only Element	132
	TibrvMsg for a String	
	TibrvMsg with a TibrvMsg with a String	
	TibrvMsg Binding with an Extra TibrvMsg Level	
	TibrvMsg with Custom TibrvMsg Wrapping	
64.	Binding of a Complex Type with an Extra TibrvMsg Level	135
65.	Using Context Data in a TibrvMsg Binding	139
	Pass Through Binding Example	
	SOAP 1.1 Port Element	
68.	SOAP 1.2 Port Element	150
	Artix HTTP Extension Namespaces	
	Generic HTTP Port	
	Setting the SendTimeout Attribute	
	Setting the ReceiveTimeout Attribute	
	Specifying Just a Usernamre	
	Specifying that the HTTP Connection is Closed	
	Rejecting Keep-Alive Requests	
	JMS Extension's Namespace	
	Artix JMS Port with DynamicQueues	
	Artix JMS Port with Non-dynamic Queues	
	JMS Port with Alternate InitialContextFactory Specification	
	Running the Transformer with the JMS Migration Script	
	CORBA personalInfoLookup Port	
	Defining an FTP Endpoint	
	Client-Side Filename Factory Interface	
	Reply Lifecycle Interface	

85. Configuring an FTP Client Endpoint	195
86. Server-Side Filename Factory Interface	196
87. Request Lifecycle Interface	
88. Configuring an FTP Server Endpoint	199
89. FTP Endpoint with Custom Properties	201
90. Using Custom FTP Properties	202
91. Constructor for FilenameFactoryPropertyMetaData	203
92. Populating the Filename Properties Metadata	204
93. Sample WebSphere MQ Port	211
94. Granting the MQ Transport Authorization	212
95. ARTIX MQ Endpoint Using MQ Client Library	214
96. Setting Up WebSphere MQ Ports for Intercommunication	
97. WebSphere MQ Client Talking to the Mainframe	218
98. TIB/RV Port Description	223
99. Tuxedo Port Description	
100. personalInfo lookup port type	
101. personalInfoLookup CORBA Binding	
102. CORBA personalInfoLookup Port	245
103. Composite WSDL	
104. Versioning Interface	
105. WSDL Fragment for Transformer	
106. Transformer Input Message	
107. Transformer Output Message	
108. XSLT Script Stylesheet Element	
109. Simple XSLT Script	
110. Sample XML Document	
111. XSLT Script with Root Element Template	
112. XSLT Script without Root Element Template	
113. XSLT Template with HTML	
114. XSLT Template Using apply-templates	
115. Bill XML Document	
116. XSLT Script for widgetBill	
117. Processed Bill XML Document	
118 Specifying Codeset Conversion	273

Preface

What is Covered in This Book	14
Who Should Read This Book	15
How to Use This Book	16
The Artix ESB Documentation Library	17

What is Covered in This Book

This book discusses the bindings and transports supported by the Artix ESB C++ Runtime. It describes how the combination of WSDL elements and configuration is used to set-up a binding or a transport. It also discusses the advantages of using each of the bindings and transports. In the case of transports, such as Websphere MQ, it also discusses how to access some of the transports more advanced features.

Who Should Read This Book

This book is intended for people who are developing the contracts for endpoints that are going to be deployed into the Artix ESB C++ Runtime. It assumes a working knowledge of WSDL and XML. It also assumes a working knowledge of the underlying middleware technology being discussed.

How to Use This Book

This book is broken into three parts:

- Part I on page 19 describes how to work with the message bindings.
- Part II on page 143 describes how to work with the transports.
- Part III on page 229 describes how to use other Artix ESB features that are contract driven. This includes codeset conversion and XSLT.

The Artix ESB Documentation Library

For information on the organization of the Artix ESB library, the document conventions used, and where to find additional resources, see Using the Artix ESB Library

[http://www.iona.com/support/docs/artix/5.5/library_intro/index.htm].

Part I. Bindings

Understanding Bindings in WSDL	23
Using SOAP 1.1 Messages	
Adding a SOAP 1.1 Binding	
Adding SOAP Headers to a SOAP 1.1 Binding	
Using SOAP 1.2 Messages	
Adding a SOAP 1.2 Binding	
Adding Headers to a SOAP 1.2 Message	
Sending Binary Data Using SOAP with Attachments	45
Sending Binary Data with SOAP MTOM	
Defining Data Types to use MTOM	50
Enabling MTOM	54
Using Tuxedo's FML Buffers	55
Using XML Documents	
Using Fixed Length Records	69
Using Tagged Data	87
Using RMI	99
Using Tibco Rendezvous Messages	105
Defining a TibrvMsg Binding	106
Default Mappings for TibrvMsg	112
Defining Array Mapping Policies	117
Defining a Custom TibrvMsg Mapping	122
Adding Context Information to a TibrvMsg	138
Using the Pass Through Binding	141

Understanding Bindings in WSDL

Bindings map the logical messages used to define a service into a concrete payload format that can be transmitted and received by an endpoint.

Overview

Bindings provide a bridge between the logical messages used by a service to a concrete data format that an endpoint uses in the physical world. They describe how the logical messages are mapped into a payload format that is used on the wire by an endpoint. It is within the bindings that details such as parameter order, concrete data types, and return values are specified. For example, the parts of a message can be reordered in a binding to reflect the order required by an RPC call. Depending on the binding type, you can also identify which of the message parts, if any, represent the return type of a method.

Port types and bindings

Port types and bindings are directly related. A port type is an abstract definition of a set of interactions between two logical services. A binding is a concrete definition of how the messages used to implement the logical services will be instantiated in the physical world. Each binding is then associated with a set of network details that finish the definition of one endpoint that exposes the logical service defined by the port type.

To ensure that an endpoint defines only a single service, WSDL requires that a binding can only represent a single port type. For example, if you had a contract with two port types, you could not write a single binding that mapped both of them into a concrete data format. You would need two bindings.

However, WSDL allows for a port type to be mapped to several bindings. For example, if your contract had a single port type, you could map it into two or more bindings. Each binding could alter how the parts of the message are mapped or they could specify entirely different payload formats for the message.

The WSDL elements

Bindings are defined in a contract using the WSDLbinding element. The binding element has a single attribute, name, that specifies a unique name for the binding. The value of this attribute is used to associate the binding with an endpoint as discussed in "Understanding How Endpoints are Defined WSDL" on page 195.

The actual mappings are defined in the children of the binding element.

These elements vary depending on the type of payload format you decide to

use. The different payload formats and the elements used to specify their mappings are discussed in the following chapters.

Adding to a contract

Artix provides a number of tools for adding bindings to your contracts. These include:

- Artix Designer has wizards that lead you through the process of adding bindings to your contract.
- A number of the bindings can be generated using command line tools.

The tools will add the proper elements to your contract for you. However, it is recommended that you have some knowledge of how the different types of bindings work.

You can also add a binding to a contract using any text editor. When you hand edit a contract, you are responsible for ensuring that the contract is valid.

Supported bindings

Artix ESB C++ Runtime supports the following bindings:

- SOAP
- CORBA
- · Fixed record length
- Pure XML
- Tagged (variable record length)
- TibrvMsg (a TIBCO Rendezvous format)
- Tuxedo's Field Manipulation Language (FML)

Using SOAP 1.1 Messages

Artix provides a tool to generate a SOAP 1.1 binding which does not use any SOAP headers. However, you can add SOAP headers to your binding using any text or XML editor. In addition, you can define a SOAP binding that uses MIME multipart attachments.

Adding a SOAP 1.1 Binding	26
Adding SOAP Headers to a SOAP 1.1 Binding	29

Adding a SOAP 1.1 Binding

Overview

Artix provides two ways to add a SOAP 1.1 binding for a logical interface:

- 1. Use Artix Designer as discussed in Using Artix Designer on page 26.
- Use the command line tool wsdltosoap as described in Using wsdltosoap on page 26.

Using Artix Designer

Artix Designer provides three ways of adding a SOAP 1.1 binding to a contract:

- 1. Select Artix Designer \rightarrow SOAP Enable.
- 2. Select Artix Designer → New Binding.
- 3. Select **New Binding** from the context menu available in diagram view.

For more information on using Artix Designer, see Artix Designer's on-line help.

Using wsdltosoap

To generate a SOAP 1.1 binding using wsdltosoap use the following command:

wsdltosoap {-i portType} {-n namespace} [-b binding] [-d dir] [-0 file]
[-style {[document] | [rpc]}] [-use {[literal] | [encoded]}] [-quiet] [-verbose]
[-h] [-v] wsdl file

The command has the following options:

-i portType	Specifies the name of the port type being mapped to a SOAP 1.1 binding.
-n namespace	Specifies the namespace to use for the SOAP 1.1 binding.
-b binding	Specifies the name for the generated SOAP binding. Defaults to portTypeBinding.
-d dir	Specifies the directory into which the new WSDL file is written.
-o file	Specifies the name of the generated WSDL file. Defaults to <code>wsdl_file-soap.wsdl</code> .

-style	Specifies the encoding style to use in the SOAP binding. Defaults to document.
-use	Specifies how the data is encoded. Default is literal.
-quiet	Specifies that the tool runs in quiet mode.
-verbose	Specifies that the tool runs in verbose mode.
-h	Specifies that the tool will display a usage message.
-v	Displays the tool's version.

wsditosoap does not support the generation of document/encoded SOAP bindings.

Example

If your system had an interface that took orders and offered a single operation to process the orders it would be defined in an Artix contract similar to the one shown in Example 1 on page 27.

Example 1. Ordering System Interface

```
<?xml version="1.0" encoding="UTF-8"?>
<definitions name="widgetOrderForm.wsdl"</pre>
   targetNamespace="http://widgetVendor.com/widgetOrderForm"
   xmlns="http://schemas.xmlsoap.org/wsdl/"
   xmlns:soap="http://schemas.xmlsoap.org/wsdl/soap/"
   xmlns:tns="http://widgetVendor.com/widgetOrderForm"
   xmlns:xsd="http://www.w3.org/2001/XMLSchema"
   xmlns:xsd1="http://widgetVendor.com/types/widgetTypes"
   xmlns:SOAP-ENC="http://schemas.xmlsoap.org/soap/encoding/">
<message name="widgetOrder">
 <part name="numOrdered" type="xsd:int"/>
</message>
<message name="widgetOrderBill">
 <part name="price" type="xsd:float"/>
</message>
<message name="badSize">
 <part name="numInventory" type="xsd:int"/>
</message>
<portType name="orderWidgets">
 <operation name="placeWidgetOrder">
   <input message="tns:widgetOrder" name="order"/>
   <output message="tns:widgetOrderBill" name="bill"/>
   <fault message="tns:badSize" name="sizeFault"/>
```

```
</p
```

The SOAP binding generated for orderWidgets is shown in Example 2 on page 28.

Example 2. SOAP 1.1 Binding for orderWidgets

This binding specifies that messages are sent using the document/literal message style.

Adding SOAP Headers to a SOAP 1.1 Binding

Overview

SOAP headers are defined by adding <code>soap:header</code> elements to your default SOAP 1.1 binding. The <code>soap:header</code> element is an optional child of the <code>input</code>, <code>output</code>, and <code>fault</code> elements of the binding. The SOAP header becomes part of the parent message. A SOAP header is defined by specifying a message and a message part. Each SOAP header can only contain one message part, but you can insert as many SOAP headers as needed.

Syntax

The syntax for defining a SOAP header is shown in Example 3 on page 29. The message attribute of soap:header is the qualified name of the message from which the part being inserted into the header is taken. The part attribute is the name of the message part inserted into the SOAP header. Because SOAP headers are always document style, the WSDL message part inserted into the SOAP header must be defined using an element. Together the message and the part attributes fully describe the data to insert into the SOAP header.

Example 3. SOAP Header Syntax

As well as the mandatory message and part attributes, soap:header also supports the namespace, the use, and the encodingStyle attributes. These optional attributes function the same for soap:header as they do for soap:body.

Splitting messages between body and header

The message part inserted into the SOAP header can be any valid message part from the contract. It can even be a part from the parent message which is being used as the SOAP body. Because it is unlikely that you would want

to send information twice in the same message, the SOAP binding provides a means for specifying the message parts that are inserted into the SOAP body.

The soap:body element has an optional attribute, parts, that takes a space delimited list of part names. When parts is defined, only the message parts listed are inserted into the SOAP body. You can then insert the remaining parts into the SOAP header.



Note

When you define a SOAP header using parts of the parent message, Artix ESB automatically fills in the SOAP headers for you.

Example

Example 4 on page 30 shows a modified version of the orderWidgets service shown in Example 1 on page 27. This version has been modified so that each order has an xsd:base64binary value placed in the SOAP header of the request and response. The SOAP header is defined as being the keyVal part from the widgetKey message. In this case you are responsible for adding the SOAP header to your application logic because it is not part of the input or output message.

Example 4. SOAP 1.1 Binding with a SOAP Header

```
<?xml version="1.0" encoding="UTF-8"?>
<definitions name="widgetOrderForm.wsdl"</pre>
   targetNamespace="http://widgetVendor.com/widgetOrderForm"
   xmlns="http://schemas.xmlsoap.org/wsdl/"
   xmlns:soap="http://schemas.xmlsoap.org/wsdl/soap/"
   xmlns:tns="http://widgetVendor.com/widgetOrderForm"
   xmlns:xsd="http://www.w3.org/2001/XMLSchema"
   xmlns:xsd1="http://widgetVendor.com/types/widgetTypes"
   xmlns:SOAP-ENC="http://schemas.xmlsoap.org/soap/encoding/">
<types>
 <schema targetNamespace="http://widgetVendor.com/types/widgetTypes"</pre>
          xmlns="http://www.w3.org/2001/XMLSchema"
           xmlns:wsdl="http://schemas.xmlsoap.org/wsdl/">
   <element name="keyElem" type="xsd:base64Binary"/>
 </schema>
</types>
<message name="widgetOrder">
```

```
<part name="numOrdered" type="xsd:int"/>
</message>
<message name="widgetOrderBill">
 <part name="price" type="xsd:float"/>
</message>
<message name="badSize">
 <part name="numInventory" type="xsd:int"/>
</message>
<message name="widgetKey">
 <part name="keyVal" element="xsd1:keyElem"/>
</message>
<portType name="orderWidgets">
 <operation name="placeWidgetOrder">
   <input message="tns:widgetOrder" name="order"/>
   <output message="tns:widgetOrderBill" name="bill"/>
   <fault message="tns:badSize" name="sizeFault"/>
 </operation>
</portType>
<binding name="orderWidgetsBinding" type="tns:orderWidgets">
 <soap:binding style="document" transport="http://schemas.xmlsoap.org/soap/http"/>
   <operation name="placeWidgetOrder">
     <soap:operation soapAction="" style="document"/>
     <input name="order">
       <soap:body use="literal"/>
       <soap:header message="tns:widgetKey" part="keyVal"/>
     </input>
     <output name="bill">
       <soap:body use="literal"/>
       <soap:header message="tns:widgetKey" part="keyVal"/>
     </output>
     <fault name="sizeFault">
       <soap:body use="literal"/>
     </fault>
 </operation>
</binding>
</definitions>
```

You can modify Example 4 on page 30 so that the header value is a part of the input and output messages as shown in Example 5 on page 32. In this case keyVal is a part of the input and output messages. In the soap:body element's parts attribute specifies that keyVal cannot be inserted into the body. However, it is inserted into the SOAP header.

Example 5. SOAP 1.1 Binding for orderWidgets with a SOAP Header

```
<?xml version="1.0" encoding="UTF-8"?>
<definitions name="widgetOrderForm.wsdl"</pre>
   targetNamespace="http://widgetVendor.com/widgetOrderForm"
   xmlns="http://schemas.xmlsoap.org/wsdl/"
   xmlns:soap="http://schemas.xmlsoap.org/wsdl/soap/"
   xmlns:tns="http://widgetVendor.com/widgetOrderForm"
   xmlns:xsd="http://www.w3.org/2001/XMLSchema"
   xmlns:xsd1="http://widgetVendor.com/types/widgetTypes"
   xmlns:SOAP-ENC="http://schemas.xmlsoap.org/soap/encoding/">
<types>
 <schema targetNamespace="http://widgetVendor.com/types/widgetTypes"</pre>
           xmlns="http://www.w3.org/2001/XMLSchema"
           xmlns:wsdl="http://schemas.xmlsoap.org/wsdl/">
   <element name="keyElem" type="xsd:base64Binary"/>
</types>
<message name="widgetOrder">
 <part name="numOrdered" type="xsd:int"/>
 <part name="keyVal" element="xsd1:keyElem"/>
</message>
<message name="widgetOrderBill">
 <part name="price" type="xsd:float"/>
 <part name="keyVal" element="xsd1:keyElem"/>
</message>
<message name="badSize">
 <part name="numInventory" type="xsd:int"/>
</message>
<portType name="orderWidgets">
 <operation name="placeWidgetOrder">
   <input message="tns:widgetOrder" name="order"/>
   <output message="tns:widgetOrderBill" name="bill"/>
    <fault message="tns:badSize" name="sizeFault"/>
 </operation>
</portType>
<binding name="orderWidgetsBinding" type="tns:orderWidgets">
 <soap:binding style="document" transport="http://schemas.xmlsoap.org/soap/http"/>
   <operation name="placeWidgetOrder">
     <soap:operation soapAction="" style="document"/>
     <input name="order">
        <soap:body use="literal" parts="numOrdered"/>
        <soap:header message="tns:widgetOrder" part="keyVal"/>
      </input>
      <output name="bill">
```

Using SOAP 1.2 Messages

Artix provides tools to generate a SOAP 1.2 binding which does not use any SOAP headers. However, you can add SOAP headers to your binding using any text or XML editor.

Adding a SOAP 1.2 Binding	36
Adding Headers to a SOAP 1.2 Message	39

Adding a SOAP 1.2 Binding

Overview

Artix provides two ways to add a SOAP 1.2 binding for a logical interface:

- use Artix Designer as described in Using Artix Designer on page 36.
- The second is the command line tool wsdltosoap as described in Using wsdltosoap on page 36.



Note

Artix 4.1 only supports literal SOAP 1.2 messages.

Using Artix Designer

Artix Designer provides three ways of adding a SOAP 1.2 binding to a contract:

- 1. Select Artix Designer \rightarrow SOAP Enable.
- 2. Select Artix Designer → New Binding.
- 3. Select **New Binding** from the context menu available in diagram view.

For more information on using Artix Designer, see Artix Designer's on-line help.

Using wsdltosoap

To generate a SOAP 1.2 binding using wsdltosoap use the following command:

The command has the following options:

-soapversion 1.2	Specifies that the generated binding should use SOAP 1.2.
-i portType	Specifies the name of the port type being mapped to a SOAP binding.
-n namespace	Specifies the namespace to use for the SOAP binding.
-b binding	Specifies the name for the generated SOAP binding. Defaults to portTypeBinding.

-d dir	Specifies the directory into which the new WSDL file is written.
-o file	Specifies the name of the generated WSDL file. Defaults to wsdl_file-soap.wsdl.
-style	Specifies the encoding style to use in the SOAP binding. Defaults to document.
-use	Specifies how the data is encoded. Default is literal.
-quiet	Specifies that the tool runs in quiet mode.
-verbose	Specifies that the tool runs in verbose mode.
-h	Specifies that the tool will display a usage message.
-v	Displays the tool's version.



Important

wsditosoap does not support the generation of document/encoded SOAP bindings.

Example

If your system had an interface that took orders and offered a single operation to process the orders it would be defined in an Artix contract similar to the one shown in Example 6 on page 37.

Example 6. Ordering System Interface

```
<?xml version="1.0" encoding="UTF-8"?>
<definitions name="widgetOrderForm.wsdl"
    targetNamespace="http://widgetVendor.com/widgetOrderForm"
    xmlns="http://schemas.xmlsoap.org/wsdl/"
    xmlns:wsoap12="http://schemas.xmlsoap.org/wsdl/soap12/"
    xmlns:tns="http://widgetVendor.com/widgetOrderForm"
    xmlns:xsd="http://www.w3.org/2001/XMLSchema"
    xmlns:xsd1="http://widgetVendor.com/types/widgetTypes"
    xmlns:SOAP-ENC="http://schemas.xmlsoap.org/soap/encoding/">

<message name="widgetOrder">
    <part name="numOrdered" type="xsd:int"/>
    </message>

<message name="widgetOrderBill">
    <part name="price" type="xsd:float"/>
    </message>
</message>
```

The SOAP binding generated for orderWidgets is shown in Example 7 on page 38.

Example 7. SOAP 1.2 Binding for orderWidgets

This binding specifies that messages are sent using the document/literal message style.

Adding Headers to a SOAP 1.2 Message

Overview

SOAP message headers are defined by adding <code>soap12:header</code> elements to your SOAP 1.2 message. The <code>soap12:header</code> element is an optional child of the <code>input</code>, <code>output</code>, and <code>fault</code> elements of the binding. The SOAP header becomes part of the parent message. A SOAP header is defined by specifying a message and a message part. Each SOAP header can only contain one message part, but you can insert as many headers as needed.

Syntax

The syntax for defining a SOAP header is shown in Example 8 on page 39.

Example 8. SOAP Header Syntax

The soap12:header element's attributes are described in Table 1 on page 39.

Table 1. soap12:header Attributes

Attribute	Description
message	A required attribute specifying the qualified name of the message from which the part being inserted into the header is taken.
part	A required attribute specifying the name of the message part inserted into the SOAP header.
use	Specifies if the message parts are to be encoded using encoding rules. If set to encoded the message parts are encoded using the encoding rules specified by the value of the encodingStyle attribute. If set to literal, the message parts are defined by the schema types referenced.

Attribute	Description	
encodingStyle	Specifies the encoding rules used to construct the message.	
namespace	Defines the namespace to be assigned to the header element serialized with use="encoded".	

Splitting messages between body and header

The message part inserted into the SOAP header can be any valid message part from the contract. It can even be a part from the parent message which is being used as the SOAP body. Because it is unlikely that you would send information twice in the same message, the SOAP 1.2 binding provides a means for specifying the message parts that are inserted into the SOAP body.

The soap12:body element has an optional attribute, parts, that takes a space delimited list of part names. When parts is defined, only the message parts listed are inserted into the body of the SOAP 1.2 message. You can then insert the remaining parts into the message's header.



Note

When you define a SOAP header using parts of the parent message, Artix ESB automatically fills in the SOAP headers for you.

Example

Example 9 on page 40 shows a modified version of the orderWidgets service shown in Example 6 on page 37. This version is modified so that each order has an xsd:base64binary value placed in the header of the request and the response. The header is defined as being the keyVal part from the widgetKey message. In this case you are responsible for adding the application logic to create the header because it is not part of the input or output message.

Example 9. SOAP 1.2 Binding with a SOAP Header

```
<?xml version="1.0" encoding="UTF-8"?>
<definitions name="widgetOrderForm.wsdl"
    targetNamespace="http://widgetVendor.com/widgetOrderForm"
    xmlns="http://schemas.xmlsoap.org/wsdl/"
    xmlns:soap12="http://schemas.xmlsoap.org/wsdl/soap12/"
    xmlns:tns="http://widgetVendor.com/widgetOrderForm"
    xmlns:xsd="http://www.w3.org/2001/XMLSchema"
    xmlns:xsd1="http://widgetVendor.com/types/widgetTypes"
    xmlns:SOAP-ENC="http://schemas.xmlsoap.org/soap/encoding/">
```

```
<types>
 <schema targetNamespace="http://widgetVendor.com/types/widgetTypes"</pre>
           xmlns="http://www.w3.org/2001/XMLSchema"
           xmlns:wsdl="http://schemas.xmlsoap.org/wsdl/">
   <element name="keyElem" type="xsd:base64Binary"/>
 </schema>
</types>
<message name="widgetOrder">
 <part name="numOrdered" type="xsd:int"/>
</message>
<message name="widgetOrderBill">
 <part name="price" type="xsd:float"/>
</message>
<message name="badSize">
 <part name="numInventory" type="xsd:int"/>
</message>
<message name="widgetKey">
 <part name="keyVal" element="xsd1:keyElem"/>
</message>
<portType name="orderWidgets">
 <operation name="placeWidgetOrder">
   <input message="tns:widgetOrder" name="order"/>
   <output message="tns:widgetOrderBill" name="bill"/>
   <fault message="tns:badSize" name="sizeFault"/>
 </operation>
</portType>
<binding name="orderWidgetsBinding" type="tns:orderWidgets">
 <soap12:binding style="document" transport="http://schemas.xmlsoap.org/soap/http"/>
   <operation name="placeWidgetOrder">
     <soap12:operation soapAction="" style="document"/>
     <input name="order">
       <soap12:body use="literal"/>
       <soap12:header message="tns:widgetKey" part="keyVal"/>
     </input>
     <output name="bill">
       <soap12:body use="literal"/>
       <soap12:header message="tns:widgetKey" part="keyVal"/>
     </output>
     <fault name="sizeFault">
       <soap12:body use="literal"/>
     </fault>
 </operation>
</binding>
</definitions>
```

You can modify Example 9 on page 40 so that the header value is a part of the input and output messages, as shown in Example 10 on page 42. In this case keyVal is a part of the input and output messages. In the soap12:body elements the parts attribute specifies that keyVal should not be inserted into the body. However, it is inserted into the header.

Example 10. SOAP 1.2 Binding for orderWidgets with a SOAP Header

```
<?xml version="1.0" encoding="UTF-8"?>
<definitions name="widgetOrderForm.wsdl"</pre>
   targetNamespace="http://widgetVendor.com/widgetOrderForm"
   xmlns="http://schemas.xmlsoap.org/wsdl/"
   xmlns:soap12="http://schemas.xmlsoap.org/wsdl/soap12/"
   xmlns:tns="http://widgetVendor.com/widgetOrderForm"
   xmlns:xsd="http://www.w3.org/2001/XMLSchema"
   xmlns:xsd1="http://widgetVendor.com/types/widgetTypes"
   xmlns:SOAP-ENC="http://schemas.xmlsoap.org/soap/encoding/">
<types>
 <schema targetNamespace="http://widgetVendor.com/types/widgetTypes"</pre>
           xmlns="http://www.w3.org/2001/XMLSchema"
           xmlns:wsdl="http://schemas.xmlsoap.org/wsdl/">
   <element name="keyElem" type="xsd:base64Binary"/>
 </schema>
</types>
<message name="widgetOrder">
 <part name="numOrdered" type="xsd:int"/>
 <part name="keyVal" element="xsd1:keyElem"/>
</message>
<message name="widgetOrderBill">
 <part name="price" type="xsd:float"/>
 <part name="keyVal" element="xsd1:keyElem"/>
</message>
<message name="badSize">
 <part name="numInventory" type="xsd:int"/>
</message>
<portType name="orderWidgets">
 <operation name="placeWidgetOrder">
   <input message="tns:widgetOrder" name="order"/>
   <output message="tns:widgetOrderBill" name="bill"/>
   <fault message="tns:badSize" name="sizeFault"/>
 </operation>
</portType>
<binding name="orderWidgetsBinding" type="tns:orderWidgets">
 <soap12:binding style="document" transport="http://schemas.xmlsoap.org/soap/http"/>
```

```
<operation name="placeWidgetOrder">
      <soap12:operation soapAction="" style="document"/>
     <input name="order">
       <soap12:body use="literal" parts="numOrdered"/>
       <soap12:header message="tns:widgetOrder" part="keyVal"/>
      </input>
     <output name="bill">
       <soap12:body use="literal" parts="bill"/>
       <soap12:header message="tns:widgetOrderBill" part="keyVal"/>
     </output>
      <fault name="sizeFault">
       <soap12:body use="literal"/>
      </fault>
 </operation>
</binding>
</definitions>
```

Sending Binary Data Using SOAP with Attachments

SOAP attachments provide a mechanism for sending binary data as part of a SOAP message. Using SOAP with attachments requires that you define your SOAP messages as MIME multipart messages.

Overview

SOAP messages generally do not carry binary data. However, the W3C SOAP 1.1 specification allows for using MIME multipart/related messages to send binary data in SOAP messages. This technique is called using SOAP with attachments. SOAP attachments are defined in the W3C's SOAP Messages with Attachments Note [http://www.w3.org/TR/SOAP-attachments].

Namespace

The WSDL extensions used to define the MIME multipart/related messages are defined in the namespace http://schemas.xmlsoap.org/wsdl/mime/.

In the discussion that follows, it is assumed that this namespace is prefixed with mime. The entry in the WSDL definitions element to set this up is shown in Example 11 on page 45.

Example 11. MIME Namespace Specification in a Contract

xmlns:mime="http://schemas.xmlsoap.org/wsdl/mime/"

Changing the message binding

In a default SOAP binding, the first child element of the input, output, and fault elements is a soap:body element describing the body of the SOAP message representing the data. When using SOAP with attachments, the soap:body element is replaced with a mime:multipartRelated element.



Note

WSDL does not support using mime: multipartRelated for fault messages.

The mime:multipartRelated element tells Artix ESB that the message body is going to be a multipart message that potentially contains binary data. The contents of the element define the parts of the message and their contents.

mime:multipartRelated elements in contain one or more mime:part elements that describe the individual parts of the message.

The first mime:part element must contain the soap:body element that would normally appear in a default SOAP binding. The remaining mime:part elements define the attachments that are being sent in the message.

Describing a MIME multipart message

MIME multipart messages are described using a mime:multipartRelated element that contains a number of mime:part elements. To fully describe a MIME multipart message do the following:

- Inside the input or output message you want to send as a MIME multipart message, add a mime:mulipartRelated element as the first child element of the enclosing message.
- 2. Add a mime:part child element to the mime:multipartRelated element and set its name attribute to a unique string.
- 3. Add a soap:body element as the child of the mime:part element and set its attributes appropriately.



Tip

If the contract had a default SOAP binding, you can copy the soap:body element from the corresponding message from the default binding into the MIME multipart message.

- 4. Add another mime:part child element to the mime:multipartReleated element and set its name attribute to a unique string.
- 5. Add a mime: content child element to the mime: part element to describe the contents of this part of the message.

To fully describe the contents of a MIME message part the mime: content element has the following attributes:

Table 2. mime: content Attributes

Attribute	Description
part	Specifies the name of the WSDL message part, from the parent message definition, that is used as
	the content of this part of the MIME multipart message being placed on the wire.
type	The MIME type of the data in this message part. MIME types are defined as a type and a subtype using the syntax $type/subtype$.
	There are a number of predefined MIME types such as <code>image/jpeg</code> and <code>text/plain</code> . The MIME types are maintained by the Internet Assigned Numbers Authority (IANA) and described in detail in <i>Multipurpose Internet Mail Extensions</i> (MIME) Part One: Format of Internet Message Bodies [ftp://ftp.isi.edu/in-notes/rfc2045.txt] and Multipurpose Internet Mail Extensions (MIME) Part Two: Media Types [ftp://ftp.isi.edu/in-notes/rfc2046.txt].

6. For each additional MIME part, repeat steps Step 4 on page 46 and Step 5 on page 46.

Example

Example 12 on page 47 shows a WSDL fragment defining a service that stores X-rays in JPEG format. The image data, xRay, is stored as an xsd:base64binary and is packed into the MIME multipart message's second part, imageData. The remaining two parts of the input message, patientName and patientNumber, are sent in the first part of the MIME multipart image as part of the SOAP body.

Example 12. Contract using SOAP with Attachments

```
<?xml version="1.0" encoding="UTF-8"?>
<definitions name="XrayStorage"
    targetNamespace="http://mediStor.org/x-rays"
    xmlns="http://schemas.xmlsoap.org/wsdl/"
    xmlns:tns="http://mediStor.org/x-rays"
    xmlns:mime="http://schemas.xmlsoap.org/wsdl/mime/"
    xmlns:soap="http://schemas.xmlsoap.org/wsdl/soap/"
    xmlns:xsd="http://schemas.xmlsoap.org/wsdl/soap/"
    xmlns:xsd="http://www.w3.org/2001/XMLSchema">

<message name="storRequest">
    <part name="storRequest">
    <part name="patientNumber" type="xsd:string"/>
    <part name="patientNumber" type="xsd:int"/>
    <part name="xRay" type="xsd:base64Binary"/>
    </message>
    <message name="storResponse">
```

```
<part name="success" type="xsd:boolean"/>
 </message>
 <portType name="xRayStorage">
   <operation name="store">
     <input message="tns:storRequest" name="storRequest"/>
     <output message="tns:storResponse" name="storResponse"/>
   </operation>
 </portType>
  <binding name="xRayStorageBinding" type="tns:xRayStorage">
   <soap:binding style="document" transport="http://schemas.xmlsoap.org/soap/http"/>
     <operation name="store">
     <soap:operation soapAction="" style="document"/>
     <input name="storRequest">
       <mime:multipartRelated>
         <mime:part name="bodyPart">
           <soap:body use="literal"/>
         </mime:part>
         <mime:part name="imageData">
            <mime:content part="xRay" type="image/jpeg"/>
          </mime:part>
       </mime:multipartRelated>
     </input>
     <output name="storResponse">
       <soap:body use="literal"/>
     </output>
   </operation>
 </binding>
 <service name="xRayStorageService">
   <port binding="tns:xRayStorageBinding" name="xRayStoragePort">
     <soap:address location="http://localhost:9000"/>
   </port>
 </service>
</definitions>
```

Sending Binary Data with SOAP MTOM

SOAP Message Transmission Optimization Mechanism (MTOM) is a SOAP 1.2 mechanism for transmitting binary data in SOAP messages. Using MTOM with Artix ESB requires adding the correct schema types to a service's contract and enabling the MTOM optimizations.

Defining Data Types to use MTOM	. 50
Enabling MTOM	54

SOAP Message Transmission Optimization Mechanism (MTOM) specifies a method for sending binary data as part of a SOAP 1.2 message. MTOM uses of XML-binary Optimized Packaging (XOP) packages for transmitting binary data. Using MTOM to send binary data does not require you to fully define the MIME Multipart/Related message as part of the SOAP binding. It does, however, require that you do the following:

- 1. Annotate the data that you are going to send as an attachment.
- 2. Enable the runtime's MTOM support.



Important

MTOM is only supported using the SOAP 1.2 binding and the C++ APIs.

Defining Data Types to use MTOM

Overview

When defining a data type for passing along a block of binary data, such as an image file or a sound file, in WSDL you define the element for the data to be of type xsd:base64Binary or of type xsd:hexBinary. By default, any element of either type results in the generation of a C++ type which can be serialized using MTOM.

You can also specify the MIME type of the binary data using the xmime:contentType attribute or xmime:expectedContentType attributes.

In addition, you can define the types of the elements binary data using xmime versions of the binary data types. When you use the MIME data to an element definition, Artix generates special data types to contain the data.

Using the XML Schema binary types

Example 13 on page 50 shows a WSDL document for a Web service that uses a message which contains one string field, one integer field, and a binary field. The binary field is intended to carry a large image file, so it is not appropriate for sending along as part of a normal SOAP message.

Example 13. Message for MTOM Using XML Schema Types

```
<?xml version="1.0" encoding="UTF-8"?>
<definitions name="XrayStorage"</pre>
   targetNamespace="http://mediStor.org/x-rays"
   xmlns="http://schemas.xmlsoap.org/wsdl/"
   xmlns:tns="http://mediStor.org/x-rays"
   xmlns:soap12="http://schemas.xmlsoap.org/wsdl/soap12/"
   xmlns:xsd1="http://mediStor.org/types/"
   xmlns:xsd="http://www.w3.org/2001/XMLSchema">
 <types>
    <schema targetNamespace="http://mediStor.org/types/"</pre>
            xmlns="http://www.w3.org/2001/XMLSchema">
     <complexType name="xRayType">
        <sequence>
          <element name="patientName" type="xsd:string" />
          <element name="patientNumber" type="xsd:int" />
          <element name="imageData" type="xsd:base64Binary" />
        </sequence>
     </complexType>
     <element name="xRay" type="xsd1:xRayType" />
    </schema>
  </types>
  <message name="storRequest">
```

```
<part name="record" element="xsd1:xRay"/>
 </message>
 <message name="storResponse">
   <part name="success" type="xsd:boolean"/>
 </message>
 <portType name="xRayStorage">
   <operation name="store">
     <input message="tns:storRequest" name="storRequest"/>
     <output message="tns:storResponse" name="storResponse"/>
   </operation>
 </portType>
 <binding name="xRayStorageSOAPBinding" type="tns:xRayStorage">
   <soap12:binding style="document" transport="http://schemas.xmlsoap.org/soap/http"/>
   <operation name="store">
     <soap12:operation soapAction="" style="document"/>
     <input name="storRequest">
       <soap12:body use="literal"/>
     </input>
     <output name="storResponse">
       <soap12:body use="literal"/>
     </output>
   </operation>
 </binding>
</definitions>
```

The data contained in the imageData element of the request message will be sent using MTOM if the consumer is properly configured. The runtime will automatically set the XOP package's Content-Type property to

application/octet-stream.

Using XMime attributes to specifying the content type

Some Java Web Service frameworks use MIME type information to optimize how their runtime manages binary data. This is done using the the ${\tt xmime:expectedContentTypes} \ attribute. \ This \ attributes \ is \ defined \ in \ the$

http://www.w3.org/2005/05/xmlmime namespace. It is placed on the element's schema type definition and specifies the MIME types that the element is expected to contain. The xmime:expectedContentTypes attribute takes a comma separated list of MIME types.

When the C++ code generator sees thise attributes on an element it generates Artix-specific objects to hold the data:

- If the element was defined using xsd:base64Binary the code generator will create an IT Bus::XMimeBase64Binary object for it.
- If the element was defined using xsd:hexBinary the code generator will create an IT Bus::XMimeHexBinary object for it.



Note

The MIME types are maintained by the Internet Assigned Numbers Authority (IANA) and described in detail in *Multipurpose Internet Mail Extensions (MIME) Part One: Format of Internet Message Bodies [ftp://ftp.isi.edu/in-notes/rfc2045.txt]* and *Multipurpose Internet Mail Extensions (MIME) Part Two: Media Types [ftp://ftp.isi.edu/in-notes/rfc2046.txt]*.

Example 14 on page 52 shows how you would modify xRayType from Example 13 on page 50 to specify the type of content passed in the binary data field.

Example 14. Using XMime Attributes to Specify the Contents of a Binary Field

Using the XMime binary types

An alternate approach to specifying the data type of elements that will be passed using MTOM is to define them using the MIME binary types. The MIME binary types, xmime:base64Binary and xmime:hexBinary are defined in the http://www.w3.org/2005/05/xmlmime namespace. They can be used as direct replacements for their respective XML Schema data types.

Example 15 on page 53 shows the xRayType, from Example 13 on page 50, defined using the MIME binary types.

Example 15. Message for MTOM Using MIME Binary Types

The Artix code generator creates Artix-specific data types for elements defined using the MIME binary types:

- Elements of type xmime:base64Binary are mapped to IT Bus::XMimeBase64Binary objects.
- Elements of type xmime:hexBinary are mapped to IT_Bus::XMimeHexBinary objects.

Enabling MTOM

Overview

By default, Artix service consumers do not use MTOM to transmit binary data in SOAP messages. You need to configure them to use this functionality.

Service providers, on the other hand, do not need any special configuration to handle SOAP 1.2 messages that use MTOM. They can receive and send MTOM data by default.

Service consumers

You control the runtime's MTOM support using the plugins:soap12:enable_mtom configuration variable. It is a boolean variable whose default setting is false.

To activate the runtime's MTOM support set this variable to true.

For more information on configuring the Artix ESB C++ Runtime, see Configuring and Deploying Artix Solutions, C++ Runtime [../../deploy/cpp/index.htm].

Example 16 on page 54 shows configuration for an endpoint that is MTOM= enabled.

Example 16. Configuration for Enabling MTOM

```
demos {
  mtom {
    plugins:soap12:enable_mtom = "true";
  };
};
```

Service providers

Artix service providers do not need to be configured to use MTOM. When a service provider receives a SOAP 1.2 request that uses MTOM, it will respond using MTOM.

Using Tuxedo's FML Buffers

Artix can send and receive messages packaged as FML buffers.

Overview

Tuxedo's native data format is FML. The FML buffers used by Tuxedo applications are described in one of two ways:

- A field table file that is loaded at runtime.
- A C header file that is compiled into the application.

A field table file is a detailed and user readable text file describing the contents of a buffer. It clearly describes each field's name, ID number, data type, and a comment. Using the FML library calls, Tuxedo applications map the field table description to usable fldids at runtime.

The C header file description of an FML buffer simply maps field names to their fldid. The fldid is an integer value that represents both the type of data stored in a field and a unique identifying number for that field.

Artix works with this data by mapping the native Tuxedo data descriptions into a WSDL binding element. As part of developing an Artix solution to integrate with legacy Tuxedo applications, you must add an FML binding to the contract describing the integration.

FML/XML Schema support

An FML buffer can only contain the data types listed in Table 3 on page 55.

Table 3. FML Type Support

FML Type	XML Schema Type
short	xsd:short
short	xsd:unsignedShort
long	xsd:int
long	xsd:unsignedInt
float	xsd:float
double	xsd:double
string	xsd:string
string	xsd:base64Binary

FML Type	XML Schema Type
	xsd:hexBinary



Important

Due to FML limitations, support for complex types is limited to xsd:sequence and xsd:all.

Mapping from a field table to an Artix contract

Creating an Artix contract to represent an FML buffer is a two-step process:

- Create the logical data representation of the FML buffer in the Artix contract as described in Mapping to logical type descriptions on page 56.
- Enter the FML binding information using Artix WSDL extensors as described in Adding the FML binding on page 59.

Mapping to logical type descriptions

To create a logical data type to represent data in an FML buffer do the following:

- 1. If the C header file for the FML buffer does not exist, generate it from the field table using the Tuxedo **mkfldhdr** or **mkfldhdr32** utility program.
- 2. For each field in the FML buffer, create an element with the following attribute settings:
 - name is set to a string that identifies the field. This value is used to by the binding to correlate the logical type with the FML field.



Tip

The value of the name attribute does not need to match the name of the physical FML field.

- type is set to the appropriate XML Schema type for the type specified in the field table. See FML/XML Schema support on page 55.
- 3. If your Tuxedo application has data fields that are always used together, you can group the corresponding elements into complex types.



In Tuxedo, a WSDL operation is implicitly bound to the Tuxedo service used. So, when the Tuxedo extensor is configured for the WSDL port there must be a one-to-one mapping between the WSDL operation and the Tuxedo service. You should only group elements into complex types only if they appear together in all exposed Tuxedo services.

Consider a Tuxedo application that returns personnel records on employees that needs to be exposed through a new web interface. The Tuxedo application uses the field table file shown in Example 17 on page 57.

Example 17. personnelInfo Field Table File

# personnel	Info Field	Table		
# name	number	type	flags	comment
empId	100	long	-	
name	101	string	-	
age	102	short	-	
dept	103	string	-	
addr	104	string	-	
city	105	string	-	
state	106	string	-	
zip	107	string	-	

The C++ header file generated by the Tuxedo **mkfldhdr** tool to represent the personnelInfo FML buffer is shown in Example 18 on page 57. Even if you are not planning to access the FML buffer using the compile-time method, you will need to generate the header file when using Artix because this will give you the fldid values for the fields in the buffer.

Example 18. personnelInfo C++ header

```
/* fname fldid */
/* ---- */
#define empId ((FLDID)8293) /* number: 100 type: long */
#define name ((FLDID)41062) /* number: 101 type: string */
#define age ((FLDID)102) /* number: 102 type: short */
#define dept ((FLDID)41064) /* number: 103 type: string */
#define addr ((FLDID)41065) /* number: 104 type: string */
#define city ((FLDID)41066) /* number: 105 type: string */
```

```
#define state ((FLDID)41067) /* number: 106 type: string */
#define zip ((FLDID)41068) /* number: 107 type: string */
```

Before mapping the FML buffer into your contract, you need to look at the operations exposed by the Tuxedo application. Suppose it exposes two operations:

- infoByName() that returns the employee data based on a name search.
- infoByID() that returns the employee data based on the employee's ID number.

Because the employee data is always returned as a unit you can group it into a complex type as shown in Example 19 on page 58.

Example 19. Logical description of personneInfo FML buffer

```
<types>
 <schema targetNamespace="http://soapinterop.org/xsd"</pre>
            xmlns="http://www.w3.org/2001/XMLSchema"
           xmlns:wsdl="http://schemas.xmlsoap.org/wsdl/">
   <complexType name="personnelInfo">
     <sequence>
       <element name="empId" type="xsd:int"/>
       <element name="name" type="xsd:string"/>
       <element name="age" type="xsd:short"/>
       <element name="dept" type="xsd:string"/>
       <element name="addr" type="xsd:string"/>
       <element name="city" type="xsd:string"/>
       <element name="state" type="xsd:string"/>
       <element name="zip" type="xsd:string"/>
     </sequence>
   </complexType>
 </schema>
</types>
```

The interface for your Tuxedo application would be mapped to a portType similar to Example 20 on page 58.

Example 20. personnelInfo Lookup Interface

```
<message name="idLookupRequest">
  <part name="empId" type="xsd:int"/>
  </message>
<message name="nameLookupRequest">
```

Flattened XML and FML

While XML Schema allows you to create structured data that is organized in multiple layers, FML data is flat. All of the elements in a field table exist on the same level. To handle this difference Artix flattens out the XML data when it is passed through the FML binding.

As a result, complex types defined in XML Schema are collapsed into their composite elements. For instance, the message <code>lookupResponse</code>, which uses the complex type defined in Example 19 on page 58, would be equivalent to the message definition in Example 21 on page 59 when processed by the FML binding.

Example 21. Flattened Message for FML

```
<message name="lookupResponse">
  <part name="empId" type="xsd:int"/>
  <part name="name" type="xsd:string"/>
  <part name="age" type="xsd:short"/>
  <part name="dept" type="xsd:string"/>
  <part name="addr" type="xsd:string"/>
  <part name="city" type="xsd:string"/>
  <part name="state" type="xsd:string"/>
  <part name="state" type="xsd:string"/>
  <part name="zip" type="xsd:string"/>
  </message>
```

Adding the FML binding

To add the binding that maps the logical description of the FML buffer to a physical FML binding do the following:

 Add the following line in the definition element at the beginning of the contract.

xmlns:tuxedo="http://schemas.iona.com/transports/tuxedo"

- 2. Create a new binding element in your contract to define the FML buffer's binding.
- 3. Add a tuxedo:binding element to identify that this binding defines an FML buffer.
- 4. Add a tuxedo:fieldTable element to the binding to describe how the element names defined in the logical portion of the contract map to the fldid values for the corresponding fields in the FML buffer.

The tuxedo:fieldTable has a mandatory type attribute. type can be either FML for specifying that the application uses FML16 buffers or FML32 for specifying that the application uses FML32 buffers.

5. For each element in the logical data type, add a tuxedo:field element to the tuxedo:fieldTable element.

tuxedo: field defines how the logical data elements map to the physical FML buffer. It has two mandatory attributes:

Table 4. Attributes of the FML Binding's Field Element

Attribute	Description
name	Specifies the name of the element or message part that describes the field.
id	Specifies the fldid value for the field in the FML buffer

- 6. For each operation in the interface, create a standard WSDL operation element to define the operation being bound.
- 7. For each operation, add a standard WSDL input and output elements to the operation element to define the messages used by the operation.

8. For each operation, add a tuxedo: operation element to the operation element.

For example, the binding for the personalInfo FML buffer, defined in Example 17 on page 57, will be similar to the binding shown in Example 22 on page 61.

Example 22. personalInfo FML binding

```
<?xml version="1.0" encoding="UTF-8"?>
<definitions name="personalInfoService" targetNamespace="ht</pre>
tp://info.org/"
   xmlns="http://schemas.xmlsoap.org/wsdl/"
   xmlns:tns="http://soapinterop.org/"
   xmlns:xsd="http://www.w3.org/2001/XMLSchema"
   xmlns:tuxedo="http://schemas.iona.com/transports/tuxedo">
 <binding name="personelInfoFMLBinding" type="tns:personnelIn</pre>
foLookup">
   <tuxedo:binding/>
   <tuxedo:fieldTable type="FML">
     <tuxedo:field name="empId" id="8293"/>
     <tuxedo:field name="name" id="41062"/>
     <tuxedo:field name="age" id="102"/>
     <tuxedo:field name="dept" id="41064"/>
     <tuxedo:field name="addr" id="41065"/>
     <tuxedo:field name="city" id="41066"/>
     <tuxedo:field name="state" id="41067"/>
     <tuxedo:field name="zip" id="41068"/>
   </fml:idNameMapping>
   <operation name="infoByName">
     <tuxedo:operation/>
     <input name="name"/>
      <output name="return"/>
   </operation>
    <operation name="infoByName">
     <tuxedo:operation/>
     <input name="name"/>
     <output name="return"/>
    </operation>
 </binding>
</definitions>
```

Using XML Documents

The pure XML payload format provides an alternative to the SOAP binding by allowing services to exchange data using straight XML documents without the overhead of a SOAP envelope.

Artix Designer provides a wizard for generating an XML binding from a logical interface. Alternatively, you can create an XML binding using any text or XML editor.

Using Artix Designer

You can add an XML binding to a contract by either selecting **Artix Designer** \rightarrow **New Binding** or selecting **New Binding** from the context menu available in Artix Designer's diagram view. For more information see the on-line help provided with Artix Designer.

Hand editing

To map an interface to a pure XML payload format do the following:

- 1. Add the namespace declaration to include the Artix ESB extensions defining the XML binding. See XML binding namespace on page 64.
- Add a standard WSDL binding element to your contract to hold the XML binding, give the binding a unique name, and specify the name of the WSDL portType element that represents the interface being bound.
- 3. Add an xformat:binding child element to the binding> element to identify that the messages are being handled as pure XML documents without SOAP envelopes.
- Optionally, set the xformat:binding element's rootNode attribute to a valid QName. For more information on the effect of the rootNode attribute see XML messages on the wire on page 64.
- For each operation defined in the bound interface, add a standard WSDL operation element to hold the binding information for the operation's messages.
- 6. For each operation added to the binding, add the input, output, and fault children elements to represent the messages used by the operation. These elements correspond to the messages defined in the interface definition of the logical operation.

7. Optionally add an xformat:body element with a valid rootNode attribute to the added input, output, and fault elements to override the value of rootNode set at the binding level.



Note

If any of your messages have no parts, for example the output message for an operation that returns void, you must set the rootNode attribute for the message to ensure that the message written on the wire is a valid, but empty, XML document.

XML binding namespace

The extensions used to describe XML format bindings are defined in the namespace http://celtix.objectweb.org/bindings/xmlformat. Artix ESB tools use the prefix xformat to represent the XML binding extensions. Add the following line to your contracts:

xmlns:xformat="http://celtix.objectweb.org/bindings/xmlformat"

XML messages on the wire

When you specify that an interface's messages are to be passed as XML documents, without a SOAP envelope, you must take care to ensure that your messages form valid XML documents when they are written on the wire. You also need to ensure that non-Artix participants that receive the XML documents understand the messages generated by Artix ESB.

A simple way to solve both problems is to use the optional rootNode attribute on either the global xformat:binding element or on the individual message's xformat:body elements. The rootNode attribute specifies the QName for the element that serves as the root node for the XML document generated by Artix ESB. When the rootNode attribute is not set, Artix ESB uses the root element of the message part as the root element when using doc style messages, or an element using the message part name as the root element when using rpc style messages.

For example, if the rootNode attribute is not set the message defined in Example 23 on page 65 would generate an XML document with the root element lineNumber.

Example 23. Valid XML Binding Message

```
<type ...>
...
<element name="operatorID" type="xsd:int"/>
...
</types><message name="operator"><part name="lineNumber" element="ns1:operatorID"/>
</message>
```

For messages with one part, Artix ESB will always generate a valid XML document even if the rootNode attribute is not set. However, the message in Example 24 on page 65 would generate an invalid XML document.

Example 24. Invalid XML Binding Message

Without the rootNode attribute specified in the XML binding, Artix will generate an XML document similar to Example 25 on page 65 for the message defined in Example 24 on page 65. The Artix-generated XML document is invalid because it has two root elements: pairName and entryNum.

Example 25. Invalid XML Document

```
<pairName>
  Fred&Linda
</pairName>
<entryNum>
  123
</entryNum>
```

If you set the rootNode attribute, as shown in Example 26 on page 66 Artix ESB will wrap the elements in the specified root element. In this example, the rootNode attribute is defined for the entire binding and specifies that the root element will be named entrants.

Example 26. XML Binding with rootNode set

```
<portType name="danceParty">
    <operation name="register">
        <input message="tns:matildas" name="contestant"/>
        </operation>
</portType>

<binding name="matildaXMLBinding" type="tns:dancingMatildas">
        <xmlformat:binding rootNode="entrants"/>
        <operation name="register">
              <input name="contestant"/>
              <output name="entered"/>
        </binding>
```

An XML document generated from the input message would be similar to Example 27 on page 66. Notice that the XML document now only has one root element.

Example 27. XML Document generated using the rootNode attribute

```
<entrants>
  <pairName>
    Fred&Linda
  <entryNum>
    123
  </entryNum>
</entrants>
```

Overriding the binding's rootNode attribute setting

You can also set the rootNode attribute for each individual message, or override the global setting for a particular message, by using the xformat:body element inside of the message binding. For example, if you wanted the output message defined in Example 26 on page 66 to have a different root element from the input message, you could override the binding's root element as shown in Example 28 on page 66.

Example 28. Using xformat:body

</output>
</operation>
</binding>

Using Fixed Length Records

To make interoperating with mainframes and older systems easy, Artix ESB can send and receive messages formatted as fixed length records.

Overview

The Artix ESB fixed binding is used to represent fixed record length data. Common uses for this type of payload format are communicating with back-end services on mainframes and applications written in COBOL. Artix ESB provides several means for creating a contract containing a fixed binding:

- If you are integrating with an application written in COBOL and have the COBOL copybook defining the data to be used, you can import the copybook to create a contract.
- If you have a description of the fixed data in some form other than a COBOL copybook, you can create a contract by describing the data.
- If you have a logical interface you want to map to a fixed binding you can use Artix Designer to create a fixed binding.
- You can enter the binding information using any text editor or XML editor.

Using Artix Designer

Artix Designer provides a number of tools for creating a contract with a fixed binding:

- 1. You can create a new contract from a COBOL copybook by selecting **New** \rightarrow **File** \rightarrow **WSDL from Dataset** and importing copybook.
- You can create a new contract from a description of the fixed data by selecting New → File → WSDL from Dataset.
- 3. You can add a fixed binding to a contract by selecting Artix Designer \rightarrow New Binding.
- You can add a fixed binding using the context menu available in Artix Designer's diagram view.

For more information see the on-line help provided with Artix Designer.

Hand editing

To map a logical interface to a fixed binding you do the following:

- 1. Add the proper namespace reference to the definition element of your contract. See Fixed binding namespace on page 70.
- Add a WSDL binding element to your contract to hold the fixed binding, give the binding a unique name, and specify the port type that represents the interface being bound.
- 3. Add a fixed:binding element as a child of the new binding element to identify this as a fixed binding and set the element's attributes to properly configure the binding. See fixed:binding on page 70.
- For each operation defined in the bound interface, add a WSDL operation element to hold the binding information for the operation's messages.
- 5. For each operation added to the binding, add a fixed:operation child element to the operation element. See fixed:operation on page 71.
- 6. For each operation added to the binding, add the input, output, and fault children elements to represent the messages used by the operation. These elements correspond to the messages defined in the interface definition of the logical operation.
- 7. For each input, output, and fault element in the binding, add a fixed:body child element to define how the message parts are mapped into the concrete fixed record length payload. See fixed:body on page 71.

Fixed binding namespace

The extensions used to describe fixed record length bindings are defined in the namespace http://schemas.iona.com/bindings/fixed. Artix tools use the prefix fixed to represent the fixed record length extensions. Add the following line to your contract:

xmlns:fixed="http://schemas.iona.com/bindings/fixed

fixed:binding

fixed:binding specifies that the binding is for fixed record length data. Its attributes are described in Table 5 on page 71.

Table 5. Attributes for fixed:binding

Attribute	Description
justification	Specifies the default justification of the data contained in the messages. Valid values are left and right.
	Default is left.
encoding	Specifies the codeset used to encode the text data. Valid values are any valid ISO locale or Internet Internet Assigned Numbers Authority (IANA) codeset name. Default is UTF-8.
padHexCode	Specifies the hex value of the character used to pad the record.

The settings for the attributes on these elements become the default settings for all the messages being mapped to the current binding. All of the values can be overridden on a message-by-message basis.

fixed:operation

fixed: operation is a child element of the WSDL operation element and specifies that the operation's messages are being mapped to fixed record length data.

fixed: operation has one attribute, discriminator, that assigns a unique identifier to the operation. If your service only defines a single operation, you do not need to provide a discriminator. However, if your service has more than one service, you must define a unique discriminator for each operation in the service. Not doing so will result in unpredictable behavior when the service is deployed.

For each message used in the operation, you will need to include a fixed:field on page 73 element whose name attribute is equal to the value of discriminator and whose bindingonly attribute is set to true. This field will hold the the value used by the binding to discriminate between the operations. For more information see fixed:field on page 73.

fixed:body

fixed:body is a child element of the input, output, and fault elements representing the messages being mapped to fixed record length data. It specifies that the message body is mapped to fixed record length data on the wire and describes the exact mapping for the message's parts.

To fully describe how a message is mapped into the fixed message do the following:

1. If the default justification, padding, or encoding settings for the attribute are not correct for this particular message, override them by setting the following optional attributes for fixed:body.

Table 6. Attributes for fixed:body

Attribute	Description
justification	Specifies how the data in the messages are justified. Valid values are left and right.
encoding	Specifies the codeset used to encode text data. Valid values are any valid ISO locale or IANA codeset name.
padHexCode	Specifies the hex value of the character used to pad the record.

2. For each part in the message the fixed:body element is binding, add the appropriate child element to define the part's concrete format on the wire.

The following child elements are used in defining how logical data is mapped to a concrete fixed format message:

- fixed:field maps message parts defined using a simple type. See XML Schema Simple Types in the Writing Artix® ESB Contracts.
- fixed:sequence maps message parts defined using a sequence complex type. Complex types defined using all are not supported by the fixed format binding. See Defining Data Structures in the Writing Artix® ESB Contracts.
- fixed:choice maps message parts defined using a choice complex type. See Defining Data Structures in the Writing Artix® ESB Contracts.

3. If you need to add any fields that are specific to the binding and that will not be passed to the applications, define them using a fixed:field element with its bindingonly attribute set to true.

When bindingonly is set to true, the field described by the fixed:field element is not propagated beyond the binding. For input messages, this means that the field is read in and then discarded. For output messages, you must also use the fixedValue attribute.

The order in which the message parts are listed in the <code>fixed:body</code> element represent the order in which they are placed on the wire. It does not need to correspond to the order in which they are specified in the <code>message</code> element defining the logical message.

fixed: field is used to map simple data types to a fixed length record. To define how the logical data is mapped to a fixed field do the following:

- 1. Create a fixed:field child element to the fixed:body element representing the message.
- 2. Set the fixed:field element's name attribute to the name of the message part defined in the logical message description that this element is mapping.
- 3. If the data being mapped is of type xsd:string, a simple type that has xsd:string as its base type, or an enumerated type set, the size attribute of the fixed:field element.



Note

If the message part is going to hold a date you can opt to use the format attribute described in step Step 4 on page 74 instead of the size attribute.

The size attribute specifies the length of the string record in the concrete fixed message. For example, the logical message part, raverID, described in Example 29 on page 74 would be mapped to a fixed:field similar to Example 30 on page 74.

fixed:field

Example 29. Fixed String Message

```
<message name="fixedStringMessage">
  <part name="raverID" type="xsd:string"/>
  </message>
```

In order to complete the mapping, you must know the length of the record field and supply it. In this case, the field, raverID, can contain no more than twenty characters.

Example 30. Fixed String Mapping

```
<fixed:field name="raverID" size="20"/>
```

4. If the data being mapped is of a numerical type, like xsd:int, or a simple type that has a numerical type as its base type, set the fixed:field element's format attribute.

The format attribute specifies how non-string data is formatted. For example, if a field contains a 2-digit numeric value with one decimal place, it would be described in the logical part of the contract as an xsd:float, as shown in Example 31 on page 74.

Example 31. Fixed Record Numeric Message

```
<message name="fixedNumberMessage">
   <part name="rageLevel" type="xsd:float"/>
   </message>
```

From the logical description of the message, Artix has no way of determining that the value of rageLevel is a 2-digit number with one decimal place because the fixed record length binding treats all data as characters. When mapping rageLevel in the fixed binding the value of the format attribute would be ##.#, as shown in

Example 32 on page 74. This provides Artix with the meta-data needed to properly handle the data.

Example 32. Mapping Numerical Data to a Fixed Binding

```
<fixed:field name="rageLevel" format="##.#"/>
```

Dates are specified in a similar fashion. For example, the value of the format attribute for the date 12/02/72 is MM/DD/YY. When using the

fixed binding it is recommended that dates are described in the logical part of the contract using xsd:string. For example, a message containing a date would be described in the logical part of the contract as shown in Example 33 on page 75.

Example 33. Fixed Date Message

```
<message name="fixedDateMessage">
  <part name="goDate" type="xsd:string"/>
</message>
```

If goDate is entered using the standard short date format for US English locales, mm/dd/yyyy, you would map it to a fixed record field as shown in Example 34 on page 75.

Example 34. Fixed Format Date Mapping

```
<fixed:field name="goDate" format="mm/dd/yyyy"/>
```

- If the justification setting is not correct for this particular field, override it by setting the justification attribute. Valid values are left and right.
- 6. If you want the message part to have a fixed value no matter what data is set in the message part by the application, set the fixed:field element's fixedValue attribute instead of the size or the format attribute.

The fixedvalue attribute specifies a static value to be passed on the wire. When used without bindingOnly="true", the value specified by the fixedvalue attribute replaces any data that is stored in the message part passed to the fixed record binding. For example, if goDate, shown in Example 33 on page 75, were mapped to the fixed field shown in Example 35 on page 75, the actual message returned from the binding would always have the date 11/11/2112.

Example 35. fixedValue Mapping

```
<fixed:field name="goDate" fixedValue="11/11/2112"/>
```

7. If the data being mapped is of an enumerated type, see "Defining Enumerated Types" on page 43, add a fixed:enumeration child element to the fixed:field element for each possible value of the enumerated type.

fixed:enumeration takes two required attributes: value and fixedValue. The value attribute corresponds to the enumeration value as specified in the logical description of the enumerated type. The fixedValue attribute specifies the concrete value that will be used to represent the logical value on the wire.

For example, if you had an enumerated type with the values FruityTooty, Rainbow, BerryBomb, and OrangeTango the logical description of the type would be similar to Example 36 on page 76.

Example 36. Enumeration Logical Mapping

```
<xs:simpleType name="flavorType">
  <xs:restriction base="xs:string">
    <xs:enumeration value="FruityTooty"/>
    <xs:enumeration value="Rainbow"/>
    <xs:enumeration value="BerryBomb"/>
    <xs:enumeration value="OrangeTango"/>
    </xs:restriction>
</xs:simpleType>
```

When you map the enumerated type, you need to know the concrete representation for each of the enumerated values. The concrete representations can be identical to the logical or some other value. The enumerated type in Example 36 on page 76 could be mapped to the fixed field shown in Example 37 on page 76. Using this mapping Artix will write ot to the wire for this field if the enumerations value is set to OrangeTango.

Example 37. Fixed Ice Cream Mapping

```
fixedValue="OT"/>
</fixed:field>
```

Note that the parent fixed: field element uses the size attribute to specify that the concrete representation is two characters long. When mapping enumerations, the size attribute will always be used to represent the size of the concrete representation.

fixed:choice

fixed: choice is used to map choice complex types into fixed record length messages. To map a choice complex type to a fixed: choice do the following:

- 1. Add a fixed:choice child element to the fixed:body element.
- 2. Set the fixed:choice element's name attribute to the name of the logical message part being mapped.
- 3. Set the fixed:choice element's optional discriminatorName attribute to the name of the field used as the discriminator for the union.

The value for discriminatorName corresponds to the name of a binding only fixed:field element that describes the type used for the union's discriminator as shown in Example 38 on page 77. The only restriction in describing the discriminator is that it must be able to handle the values used to determine the case of the union. Therefore the values used in the union mapped in Example 38 on page 77 must be two-digit integers.

Example 38. Using the discriminatorName Attribute

4. For each element in the logical definition of the message part, add a fixed:case child element to the fixed:choice element.

fixed:case

fixed:case elements describe the complete mapping of a choice complex type element to a fixed record length message. To map a choice complex type element to a fixed:case do the following:

- 1. Set the fixed:case element's name attribute to the name of the logical definition's element.
- 2. Set the fixed:case element's fixedValue attribute to the value of the discriminator that selects this element. The value of the fixedValue attribute must correspond to the format specified by the discriminatorName attribute of the parent fixed:choice element.
- Add a child element to define how the element's data is mapped into a fixed record.

The child elements used to map the part's type to the fixed message are the same as the possible child elements of a fixed:body element. As with a fixed:body element, a fixed:sequence is made up of fixed:field elements to describe simple types, fixed:choice elements to describe choice complex types, and fixed:sequence elements to describe sequence complex types.

Example 39 on page 78 shows an Artix contract fragment mapping a choice complex type to a fixed record length message.

Example 39. Mapping a Union to a Fixed Record Length Message

```
<xsd:complexType name="unionStationType">
    <xsd:choice>
      <xsd:element name="train" type="xsd:string"/>
      <xsd:element name="bus" type="xsd:int"/>
      <xsd:element name="cab" type="xsd:int"/>
      <xsd:element name="subway" type="xsd:string"/>
    </xsd:choice>
  </xsd:complexType>
</types>
<message name="fixedSequence">
 <part name="stationPart" type="tns:unionStationType"/>
</message>
<portType name="fixedSequencePortType">
</portType>
<binding name="fixedSequenceBinding"</pre>
        type="tns:fixedSequencePortType">
 <fixed:binding/>
   <fixed:field name="disc" format="##" bindingOnly="true"/>
   <fixed:choice name="stationPart"
                 descriminatorName="disc">
     <fixed:case name="train" fixedValue="01">
       <fixed:field name="name" size="20"/>
     </fixed:case>
     <fixed:case name="bus" fixedValue="02">
       <fixed:field name="number" format="###"/>
     </fixed:case>
     <fixed:case name="cab" fixedValue="03">
       <fixed:field name="number" format="###"/>
     </fixed:case>
     <fixed:case name="subway" fixedValue="04">
       <fixed:field name="name" format="10"/>
     </fixed:case>
   </fixed:choice>
</binding>
```

```
</definition>
```

fixed:sequence

fixed:sequence maps sequence complex types to a fixed record length message. To map a sequence complex type to a fixed:sequence do the following:

- 1. Add a fixed:sequence child element to the fixed:body element.
- 2. Set the fixed:sequence element's name attribute to the name of the logical message part being mapped.
- 3. For each element in the logical definition of the message part, add a child element to define the mapping for the part's type to the physical fixed message.

The child elements used to map the part's type to the fixed message are the same as the possible child elements of a fixed:body element. As with a fixed:body element, a fixed:sequence is made up of fixed:field elements to describe simple types, fixed:choice elements to describe choice complex types, and fixed:sequence elements to describe sequence complex types.

4. If any elements of the logical data definition have occurrence constraints, see Defining Data Structures in the Writing Artix® ESB Contracts on page 34, map the element into a fixed:sequence element with its occurs and counterName attributes set.

The occurs attribute specifies the number of times this sequence occurs in the message buffer. counterName specifies the name of the field used for specifying the number of sequence elements that are actually being sent in the message. The value of counterName corresponds to a binding-only fixed:field with at least enough digits to count to the value specified in occurs as shown in Example 40 on page 81. The value passed to the counter field can be any number up to the value specified by occurs and allows operations to use less than the specified number of sequence elements. Artix ESB will pad out the sequence to the number of elements specified by occurs when the data is transmitted

to the receiver so that the receiver will get the data in the promised fixed format.

Example 40. Using counterName

```
<fixed:field name="count" format="##" bindingOnly="true"/>
<fixed:sequence name="items" counterName="count" occurs="10">
...
</fixed:sequence>
```

For example, a structure containing a name, a date, and an ID number would contain three fixed:field elements to fully describe the mapping of the data to the fixed record message. Example 41 on page 81 shows an Artix contract fragment for such a mapping.

Example 41. Mapping a Sequence to a Fixed Record Length Message

```
<?xml version="1.0" encoding="UTF-8"?>
<definitions name="fixedMappingsample"</pre>
   targetNamespace="http://www.iona.com/FixedService"
   xmlns="http://schemas.xmlsoap.org/wsdl/"
   xmlns:fixed="http://schemas.iona.com/bindings/fixed"
   xmlns:tns="http://www.iona.com/FixedService"
   xmlns:xsd="http://www.w3.org/2001/XMLSchema">
<types>
 <schema targetNamespace="http://www.iona.com/FixedService"</pre>
          xmlns="http://www.w3.org/2001/XMLSchema"
          xmlns:wsdl="http://schemas.xmlsoap.org/wsdl/">
  <xsd:complexType name="person">
     <xsd:sequence>
       <xsd:element name="name" type="xsd:string"/>
      <xsd:element name="date" type="xsd:string"/>
      <xsd:element name="ID" type="xsd:int"/>
  </xsd:complexType>
</types>
<message name="fixedSequence">
 <part name="personPart" type="tns:person"/>
</message>
<portType name="fixedSequencePortType">
</portType>
<binding name="fixedSequenceBinding"</pre>
```

Example

Example 42 on page 82 shows an example of a contract containing a fixed record length message binding.

Example 42. Fixed Record Length Message Binding

```
<?xml version="1.0" encoding="UTF-8"?>
<definitions name="widgetOrderForm.wsdl"</pre>
targetNamespace="http://widgetVendor.com/widgetOrderForm"
xmlns="http://schemas.xmlsoap.org/wsdl/"
xmlns:tns="http://widgetVendor.com/widgetOrderForm"
xmlns:soap="http://schemas.xmlsoap.org/wsdl/soap/"
xmlns:fixed="http://schemas.iona.com/binings/fixed"
xmlns:xsd="http://www.w3.org/2001/XMLSchema"
xmlns:xsd1="http://widgetVendor.com/types/widgetTypes">
    <schema targetNamespace="http://widgetVendor.com/types/widgetTypes"</pre>
    xmlns="http://www.w3.org/2001/XMLSchema"
    xmlns:wsdl="http://schemas.xmlsoap.org/wsdl/">
     <xsd:simpleType name="widgetSize">
        <xsd:restriction base="xsd:string">
         <xsd:enumeration value="big"/>
         <xsd:enumeration value="large"/>
         <xsd:enumeration value="mungo"/>
          <xsd:enumeration value="gargantuan"/>
        </xsd:restriction>
      </xsd:simpleType>
     <xsd:complexType name="Address">
        <xsd:sequence>
          <xsd:element name="name" type="xsd:string"/>
          <xsd:element name="street1" type="xsd:string"/>
```

```
<xsd:element name="street2" type="xsd:string"/>
       <xsd:element name="city" type="xsd:string"/>
       <xsd:element name="state" type="xsd:string"/>
        <xsd:element name="zipCode" type="xsd:string"/>
      </xsd:sequence>
    </xsd:complexType>
   <xsd:complexType name="widgetOrderInfo">
      <xsd:sequence>
        <xsd:element name="amount" type="xsd:int"/>
       <xsd:element name="order date" type="xsd:string"/>
       <xsd:element name="type" type="xsd1:widgetSize"/>
       <xsd:element name="shippingAddress" type="xsd1:Address"/>
      </xsd:sequence>
   </xsd:complexType>
   <xsd:complexType name="widgetOrderBillInfo">
      <xsd:sequence>
        <xsd:element name="amount" type="xsd:int"/>
       <xsd:element name="order date" type="xsd:string"/>
       <xsd:element name="type" type="xsd1:widgetSize"/>
       <xsd:element name="amtDue" type="xsd:float"/>
       <xsd:element name="orderNumber" type="xsd:string"/>
       <xsd:element name="shippingAddress" type="xsd1:Address"/>
     </xsd:sequence>
   </xsd:complexType>
 </schema>
</types>
<message name="widgetOrder">
 <part name="widgetOrderForm" type="xsd1:widgetOrderInfo"/>
</message>
<message name="widgetOrderBill">
 <part name="widgetOrderConformation" type="xsd1:widgetOrderBillInfo"/>
</message>
<portType name="orderWidgets">
 <operation name="placeWidgetOrder">
   <input message="tns:widgetOrder" name="order"/>
    <output message="tns:widgetOrderBill" name="bill"/>
 </operation>
</portType>
<binding name="orderWidgetsBinding" type="tns:orderWidgets">
 <fixed:binding/>
   <operation name="placeWidgetOrder">
      <fixed:operation discriminator="widgetDisc"/>
      <input name="widgetOrder">
```

```
<fixed:bodv>
          <fixed:sequence name="widgetOrderForm">
            <fixed:field name="amount" format="###"/>
            <fixed:field name="order date" format="MM/DD/YYYY"/>
            <fixed:field name="type" size="2">
              <fixed:enumeration value="big" fixedValue="bg"/>
              <fixed:enumeration value="large" fixedValue="lg"/>
              <fixed:enumeration value="mungo" fixedValue="mg"/>
              <fixed:enumeration value="gargantuan" fixedValue="gg"/>
            </fixed:field>
            <fixed:sequence name="shippingAddress">
              <fixed:field name="name" size="30"/>
              <fixed:field name="street1" size="100"/>
             <fixed:field name="street2" size="100"/>
              <fixed:field name="city" size="20"/>
              <fixed:field name="state" size="2"/>
              <fixed:field name="zip" size="5"/>
            </fixed:sequence>
          </fixed:sequence>
        </fixed:body>
      </input>
      <output name="widgetOrderBill">
        <fixed:body>
          <fixed:sequence name="widgetOrderConformation">
            <fixed:field name="amount" format="###"/>
            <fixed:field name="order date" format="MM/DD/YYYY"/>
            <fixed:field name="type" size="2">
              <fixed:enumeration value="big" fixedValue="bg"/>
             <fixed:enumeration value="large" fixedValue="lq"/>
              <fixed:enumeration value="mungo" fixedValue="mg"/>
              <fixed:enumeration value="gargantuan" fixedValue="gg"/>
            </fixed:field>
            <fixed:field name="amtDue" format="####.##"/>
            <fixed:field name="orderNumber" size="20"/>
            <fixed:sequence name="shippingAddress">
              <fixed:field name="name" size="30"/>
              <fixed:field name="street1" size="100"/>
             <fixed:field name="street2" size="100"/>
              <fixed:field name="city" size="20"/>
              <fixed:field name="state" size="2"/>
              <fixed:field name="zip" size="5"/>
            </fixed:sequence>
          </fixed:sequence>
        </fixed:body>
      </output>
 </operation>
</binding>
```

Using Tagged Data

Artix has a binding that reads and writes messages where the data fields are delimited by specified characters.

Overview

The tagged data format supports applications that use self-describing, or delimited, messages to communicate. Artix can read tagged data and write it out in any supported data format. Similarly, Artix is capable of converting a message from any of its supported data formats into a self-describing or tagged data message.

Artix provides several ways of creating a contract with a tagged binding:

- Artix Designer can create a contract with a tagged binding from a description
 of the tagged data.
- Artix Designer can create a tagged binding for an existing interface.
- You can enter the binding information using any text editor or XML editor.

Using Artix Designer

Artix Designer provides a number of tools for creating a contract with a tagged binding:

- 1. You can create a new contract from a description of the tagged data by selecting $\mathbf{New} \to \mathbf{File} \to \mathbf{WSDL}$ from $\mathbf{Dataset}$.
- You can add a tagged binding to a contract by selecting Artix Designer → New Binding.
- 3. You can add a tagged binding using the context menu available in Artix Designer's diagram view.

For more information see the on-line help provided with Artix Designer.

Hand editing

To map a logical interface to a tagged data format do the following:

- 1. Add the proper namespace reference to the definition element of your contract. See Namespace on page 88.
- Add a WSDL binding element to your contract to hold the tagged binding, give the binding a unique name, and specify the interface that represents the interface being bound.

- Add a tagged:binding element as a child of the new binding element
 to identify this as a tagged binding and set the element's attributes to
 properly configure the binding.
- For each operation defined in the bound interface, add a WSDL operation element to hold the binding information for the operation's messages.
- 5. For each operation added to the binding, add a tagged:operation child element to the operation element.
- 6. For each operation added to the binding, add the input, output, and fault children elements to represent the messages used by the operation. These elements correspond to the messages defined in the interface definition of the logical operation.
- 7. For each input, output, and fault element in the binding, add a tagged:body child element to define how the message parts are mapped into the concrete tagged data payload.

Namespace

The extensions used to describe tagged data bindings are defined in the namespace http://schemas.iona.com/bindings/tagged. Artix tools use the prefix tagged to represent the tagged data extensions. Add the following line to the definitions element of your contract:

xmlns:tagged="http://schemas.iona.com/bindings/tagged"

tagged:binding

tagged:binding specifies that the binding is for tagged data format messages. Its ten attributes are explained in Table 7 on page 88.

Table 7. Attributes Used to Define a Tagged Binding

Attribute	Purpose
	Required attribute specifying if the message data on the wire includes the field names. Valid values are true or false. If this attribute is set to false, the setting for fieldNameValueSeparator is ignored.
fieldSeparator	Required attribute that specifies the delimiter the message uses to separate fields. Valid values include any character that is not a letter or a number.

Attribute	Purpose
fieldNameValueSeparator	Specifies the delimiter used to separate field names from field values in self-describing messages. Valid values include any character that is not a letter or a number.
scopeType	Specifies the scope identifier for complex messages. Supported values are tab(\t), curlybrace({data}), and none. The default is tab.
flattened	Specifies if data structures are flattened when they are put on the wire. If selfDescribing is false, then this attribute is automatically set to true.
messageStart	Specifies a special token at the start of a message. It is used when messages require a special character at the start of a the data sequence. Valid values include any character that is not a letter or a number.
messageEnd	Specifies a special token at the end of a message. Valid values include any character that is not a letter or a number.
unscopedArrayElement	Specifies if array elements need to be scoped as children of the array. If set to true, arrays take the form echoArray{myArray=2;item=abc;item=def}. If set to false, arrays take the form echoArray{myArray=2;{0=abc;1=def;}}. Default is false.
ignoreUnknownElements	Specifies if Artix ignores undefined elements in the message payload. Default is false.
ignoreCase	Specifies if Artix ignores the case with element names in the message payload. Default is false.

The settings for the attributes on these elements become the default settings for all the messages being mapped to the current binding.

tagged:operation

 ${\tt tagged:operation}\ is\ a\ child\ element\ of\ the\ WSDL\ operation\ element\ and\ specifies\ that\ the\ operation's\ messages\ are\ being\ mapped\ to\ a\ tagged\ data\ format.\ It\ takes\ two\ optional\ attributes\ that\ are\ described\ in\ Table\ 8\ on\ page\ 89\ .$

Table 8. Attributes for tagged:operation

Attribute	Purpose
	Specifies a discriminator to be used by the Artix runtime to identify the WSDL operation that will be invoked by the message reciever.

Attribute	Purpose
discriminatorStyle	Specifies how the Artix runtime will locate the discriminator as it processes the message. Supported values are msgname, partlist, fieldvalue, and
	fieldname.

tagged:body

tagged:body is a child element of the input, output, and fault messages being mapped to a tagged data format. It specifies that the message body is mapped to tagged data on the wire and describes the exact mapping for the message's parts.

tagged:body will have one or more of the following child elements:

- tagged:field
- tagged:sequence
- tagged:choice

They describe the detailed mapping of the message to the tagged data to be sent on the wire.

tagged: field is used to map simple types and enumerations to a tagged data format. Its two attributes are described in Table 9 on page 90.

Table 9. Attributes for tagged:field

Attribute	Purpose
	A required attribute that must correspond to the name of the logical message part that is being mapped to the tagged data field.
	An optional attribute specifying an alias for the field that can be used to identify it on the wire.

tagged:field

When describing enumerated types tagged:field will have a number of tagged:enumeration child elements.

tagged:enumeration

tagged:enumeration is a child element of tagged:field and is used to map enumerated types to a tagged data format. It takes one required attribute, value, that corresponds to the enumeration value as specified in the logical description of the enumerated type.

For example, if you had an enumerated type, flavorType, with the values FruityTooty, Rainbow, BerryBomb, and OrangeTango the logical description of the type would be similar to Example 43 on page 91.

Example 43. Ice Cream Enumeration

 ${\tt flavorType}$ would be mapped to the tagged data format shown in Example 44 on page 91 .

Example 44. Tagged Data Ice Cream Mapping

```
<tagged:field name="flavor">
  <tagged:enumeration value="FruityTooty"/>
  <tagged:enumeration value="Rainbow"/>
  <tagged:enumeration value="BerryBomb"/>
  <tagged:enumeration value="OrangeTango"/>
  </tagged:field>
```

tagged:sequence

 ${\tt taggeded:sequence} \ \ {\tt maps} \ \ {\tt arrays} \ \ {\tt and} \ \ {\tt sequences} \ \ {\tt to} \ \ {\tt atagged} \ \ {\tt data} \ \ {\tt format}.$ Its three attributes are described in Table 10 on page 92 .

Table 10. Attributes for tagged:sequence

Attributes	Purpose
name	A required attribute that must correspond to the name of the logical message part that is being mapped to the tagged data sequence.
alias	An optional attribute specifying an alias for the sequence that can be used to identify it on the wire.
occurs	An optional attribute specifying the number of times the sequence appears. This attribute is used to map arrays.

A tagged:sequence can contain any number of tagged:field , tagged:sequence , or tagged:choice child elements to describe the data contained within the sequence being mapped. For example, a structure containing a name, a date, and an ID number would contain three tagged:field elements to fully describe the mapping of the data to the fixed record message. Example 45 on page 92 shows an Artix contract fragment for such a mapping.

Example 45. Mapping a Sequence to a Tagged Data Format

```
<?xml version="1.0" encoding="UTF-8"?>
<definitions name="taggedDataMappingsample" targetNamespace="http://www.iona.com/taggedSer</pre>
vice"
    xmlns="http://schemas.xmlsoap.org/wsdl/"
    xmlns:fixed="http://schemas.iona.com/bindings/tagged"
   xmlns:tns="http://www.iona.com/taggedService"
    xmlns:xsd="http://www.w3.org/2001/XMLSchema">
<types>
  <schema targetNamespace="http://www.iona.com/taggedService" xmlns="ht</pre>
tp://www.w3.org/2001/XMLSchema" xmlns:wsdl="http://schemas.xmlsoap.org/wsdl/">
   <xsd:complexType name="person">
    <xsd:sequence>
       <xsd:element name="name" type="xsd:string"/>
      <xsd:element name="date" type="xsd:string"/>
       <xsd:element name="ID" type="xsd:int"/>
    </xsd:sequence>
   </xsd:complexType>
</types>
<message name="taggedSequence">
 <part name="personPart" type="tns:person"/>
</message>
<portType name="taggedSequencePortType">
```

tagged:choice

tagged: choice maps unions to a tagged data format. Its three attributes are described in Table $\,11$ on page $\,93$.

Table 11. Attributes for tagged:choice

Attributes	Purpose
name	A required attribute that must correspond to the name of the logical message part that is being mapped to the tagged data union.
discriminatorName	Specifies the message part used as the discriminator for the union.
alias	An optional attribute specifying an alias for the union that can be used to identify it on the wire.

A tagged:choice may contain one or more tagged:case child elements to map the cases for the union to a tagged data format.

tagged:case

tagged:case is a child element of tagged:choice and describes the complete mapping of a union's individual cases to a tagged data format. It takes one required attribute, name, that corresponds to the name of the case element in the union's logical description.

tagged:case must contain one child element to describe the mapping of
the case's data to a tagged data format. Valid child elements are
tagged:field , tagged:sequence , and tagged:choice .

Example 46 on page 94 shows an Artix contract fragment mapping a union to a tagged data format.

Example 46. Mapping a Union to a Tagged Data Format

```
<?xml version="1.0" encoding="UTF-8"?>
<definitions name="fixedMappingsample" targetNamespace="http://www.iona.com/tagService"</pre>
    xmlns="http://schemas.xmlsoap.org/wsdl/"
    xmlns:fixed="http://schemas.iona.com/bindings/tagged"
    xmlns:tns="http://www.iona.com/tagService"
    xmlns:xsd="http://www.w3.org/2001/XMLSchema">
<tvpes>
 <schema targetNamespace="http://www.iona.com/tagService" xmlns="http://www.w3.org/2001/XMLS</pre>
chema" xmlns:wsdl="http://schemas.xmlsoap.org/wsdl/">
  <xsd:complexType name="unionStationType">
     <xsd:choice>
       <xsd:element name="train" type="xsd:string"/>
      <xsd:element name="bus" type="xsd:int"/>
<xsd:element name="cab" type="xsd:int"/>
       <xsd:element name="subway" type="xsd:string"/>
     </xsd:choice>
   </xsd:complexType>
</types>
<message name="tagUnion">
 <part name="stationPart" type="tns:unionStationType"/>
<portType name="tagUnionPortType">
</portType>
<binding name="tagUnionBinding" type="tns:tagUnionPortType">
 <tagged:binding selfDescribing="false"
                  fieldSeparator="comma"/>
    <tagged:choice name="stationPart" descriminatorName="disc">
      <tagged:case name="train">
        <tagged:field name="name"/>
      </tagged:case>
      <tagged:case name="bus">
        <tagged:field name="number"/>
      </tagged:case>
      <tagged:case name="cab">
        <tagged:field name="number"/>
      </tagged:case>
      <tagged:case name="subway">
        <tagged:field name="name"/>
      </tagged:case>
    </tagged:choice>
```

```
</binding>
...
</definition>
```

Example

Example 47 on page 95 shows an example of an Artix contract containing a tagged data format binding.

Example 47. Tagged Data Format Binding

```
<?xml version="1.0" encoding="UTF-8"?>
<definitions name="widgetOrderForm.wsdl"</pre>
targetNamespace="http://widgetVendor.com/widgetOrderForm"
xmlns="http://schemas.xmlsoap.org/wsdl/"
xmlns:tns="http://widgetVendor.com/widgetOrderForm"
xmlns:soap="http://schemas.xmlsoap.org/wsdl/soap/"
xmlns:taged="http://schames.iona.com/binings/tagged"
xmlns:xsd="http://www.w3.org/2001/XMLSchema"
xmlns:xsd1="http://widgetVendor.com/types/widgetTypes">
 <types>
   <schema targetNamespace="http://widgetVendor.com/types/widgetTypes"</pre>
    xmlns="http://www.w3.org/2001/XMLSchema"
    xmlns:wsdl="http://schemas.xmlsoap.org/wsdl/">
     <xsd:simpleType name="widgetSize">
        <xsd:restriction base="xsd:string">
          <xsd:enumeration value="big"/>
          <xsd:enumeration value="large"/>
          <xsd:enumeration value="mungo"/>
          <xsd:enumeration value="gargantuan"/>
        </xsd:restriction>
      </xsd:simpleType>
      <xsd:complexType name="Address">
        <xsd:sequence>
          <xsd:element name="name" type="xsd:string"/>
          <xsd:element name="street1" type="xsd:string"/>
          <xsd:element name="street2" type="xsd:string"/>
         <xsd:element name="city" type="xsd:string"/>
         <xsd:element name="state" type="xsd:string"/>
          <xsd:element name="zipCode" type="xsd:string"/>
        </xsd:sequence>
      </xsd:complexType>
      <xsd:complexType name="widgetOrderInfo">
        <xsd:sequence>
          <xsd:element name="amount" type="xsd:int"/>
          <xsd:element name="order date" type="xsd:string"/>
         <xsd:element name="type" type="xsd1:widgetSize"/>
          <xsd:element name="shippingAddress" type="xsd1:Address"/>
        </xsd:sequence>
      </xsd:complexType>
```

```
<xsd:complexType name="widgetOrderBillInfo">
      <xsd:sequence>
        <xsd:element name="amount" type="xsd:int"/>
        <xsd:element name="order date" type="xsd:string"/>
        <xsd:element name="type" type="xsd1:widgetSize"/>
        <xsd:element name="amtDue" type="xsd:float"/>
       <xsd:element name="orderNumber" type="xsd:string"/>
        <xsd:element name="shippingAddress" type="xsd1:Address"/>
      </xsd:sequence>
    </xsd:complexType>
 </schema>
</types>
<message name="widgetOrder">
 <part name="widgetOrderForm" type="xsd1:widgetOrderInfo"/>
</message>
<message name="widgetOrderBill">
 <part name="widgetOrderConformation" type="xsd1:widgetOrderBillInfo"/>
</message>
<portType name="orderWidgets">
  <operation name="placeWidgetOrder">
   <input message="tns:widgetOrder" name="order"/>
   <output message="tns:widgetOrderBill" name="bill"/>
  </operation>
</portType>
<binding name="orderWidgetsBinding" type="tns:orderWidgets">
  <tagged:binding selfDescribing="false" fieldSeparator="pipe"/>
    <operation name="placeWidgetOrder">
      <tagged:operation discriminator="widgetDisc"/>
      <input name="widgetOrder">
        <tagged:body>
          <tagged:sequence name="widgetOrderForm">
            <tagged:field name="amount"/>
            <tagged:field name="order date"/>
            <tagged:field name="type" >
              <tagged:enumeration value="big"/>
              <tagged:enumeration value="large"/>
              <tagged:enumeration value="mungo"/>
              <tagged:enumeration value="gargantuan"/>
            </tagged:field>
            <tagged:sequence name="shippingAddress">
              <tagged:field name="name"/>
              <tagged:field name="street1"/>
              <tagged:field name="street2"/>
              <tagged:field name="city"/>
              <tagged:field name="state"/>
              <tagged:field name="zip"/>
            </tagged:sequence>
          </tagged:sequence>
        </tagged:body>
```

```
</input>
       <output name="widgetOrderBill">
          <tagged:body>
            <tagged:sequence name="widgetOrderConformation">
              <tagged:field name="amount"/>
              <tagged:field name="order date"/>
             <tagged:field name="type">
                <tagged:enumeration value="big"/>
                <tagged:enumeration value="large"/>
                <tagged:enumeration value="mungo"/>
                <tagged:enumeration value="gargantuan"/>
             </tagged:field>
              <tagged:field name="amtDue"/>
              <tagged:field name="orderNumber"/>
             <tagged:sequence
name="shippingAddress">
               <tagged:field name="name"/>
                <tagged:field name="street1"/>
                <tagged:field name="street2"/>
               <tagged:field name="city"/>
                <tagged:field name="state"/>
                <tagged:field name="zip"/>
             </tagged:sequence>
            </tagged:sequence>
          </tagged:body>
       </output>
   </operation>
 </binding>
 <service name="orderWidgetsService">
   <port name="widgetOrderPort" binding="tns:orderWidgetsBinding">
     <http:address location="http://localhost:8080"/>
   </port>
 </service>
</definitions>
```

Using RMI

Artix provides a way for Artix Java applications to connect to a remote object using RMI. The remote object does not require a Web services front end, nor does it require the ability to understand SOAP. Artix will handle the message translation.

Procedure

To use RMI you need to do the following:

- 1. Add an RMI binding to the application's WSDL contract.
- 2. Add an RMI port definition to the application's WSDL contract.
- Develop the application so that it uses an interface that extends java.rmi.Remote.
- 4. If you are developing a service, generate the RMI stubs using **rmic**.



Note

If you want to use RMI/IIOP, you need to specify the proper flags to **rmic** and extend the appropriate class.

5. Configure the application to load the RMI plug-in and the Java plug-in.

Namespace

The extensions used for RMI information to a WSDL contract are defined in the namespace http://schemas.iona.com/bindings/rmi. Artix ESB tools use the prefix rmi to represent the RMI extensions. Add the following line to your contracts:

xmlns:rmi="http://schemas.iona.com/bindings/rmi"

Adding RMI information to a contract

A contract for an Artix endpoint that uses RMI is slightly different than other contracts because the RMI connectivity feature of Artix ESB does not use the interface generated from the logical interface definition. Instead, it uses the RMI interface of the object to which it will connect. Therefore, the portType element defining the logical interface can be left empty. If it is fully specified, it will be ignored by the runtime.

To specify that an endpoint is to use RMI you need to add an RMI binding definition and RMI endpoint definition to your contract. This is done using the rmi:class element and the rmi:address element.

The rmi:class element defines an RMI binding and is a child of the WSDL binding element. It has a single attribute, name, that specifies the fully qualified name of the Java interface of the RMI object to which your application connects. This interface must extend java.rmi.Remote.

The rmi:address element defines the connection information for an RMI endpoint. It has a single attribute, url, the specifies the JNDI URL the application will use to talk to remote objects.

Artix Designer provides a tool for adding an RMI binding to a contract. To use this tool select **Artix Designer** \rightarrow **New Binding** or select **New Binding** from the context menu available in diagram view. For more information see the on-line help provided with Artix Designer.

Example 48 on page 100 shows a contract fragment that defines an RMI endpoint.

Example 48. RMI Endpoint

```
...
cyportType name="RMIPortType" />
<binding name="RMIBinding" type="tns:RMIPortType">
    <rmi:class name="foo.bar.MyRemoteInterface"/>
</binding>
```

Writing a service to use RMI

Unlike standard Artix Java services, Artix Java services using RMI do not require that you use the code generated by **wsdltojava**. It does not require that the types adhere to the JAX-RPC mappings. The only requirement is that the service's implementation class must implement an interface that extends java.rmi.Remote.



Note

You can use the interface generated by **wsdltojava** because the generated interface extends <code>java.rmi.Remote</code>.

You will need to generate RMI stubs for your implementation class using Sun's **rmic** compiler. If you want to use RMI/IIOP instead of plain RMI, you need to generate the RMI stubs using the proper flags. For more information on **rmic** see Sun's RMIC documentation

[http://java.sun.com/j2se/1.4.2/docs/tooldocs/solaris/rmic.html].

Once you have implemented your service's application logic and generated the RMI stubs, you need to create a servant for the implementation object register the servant with the Artix bus. This is done using the standard Artix APIs as shown in Example 49 on page 101.

Example 49. Service for Using RMI

```
public interface GreeterInterface extends java.rmi.Remote
{
    ...
}
public class RMIGreeter extends UnicastRemoteObject implements GreeterInterface
{
    ...
}

public class MyRMIService
{
    ...

public static void main (String args[]) throws Exception
    {
         ...
        Servant servant = new SingleInstanceServant(new RMIGreeter(), myWsdlPath, bus);
        bus.registerServant(servant, new QName(tns, "MyRmiService");
         ...
}
```

Writing a client to use RMI

Implementing a client that uses the RMI binding is similar to implementing a standard Artix client in Java. You need to have access to the RMI interface implemented by the service. You use the interface to create a service proxy using the standard Artix createClient() method.

The only difference is that instead of casting the proxy returned from <code>createClient()</code> to the implementation class, you cast it to the RMI interface class as shown in Example 50 on page 102 . This gives you access to all of the remote object's methods including the ones used to manage the remote

object. When the proxy connects to the service, it will download the stubs it needs for communicating.

Example 50. Client Using RMI

For more information see Developing Artix Applications with JAX-RPC [../../jaxrpc pguide/index.htm].

Stub downloading

If the java.rmi.server.codebase property is not set and the RMI plug-in was loaded by a URL classloader, the RMI plug-in will set the codebase to the classpath of the classloader that loaded the plug-in. This effectively makes the server classpath available to the client for loading RMI stubs.

If the client and server are on the same host, the client does not need to have the stub paths explicitly on its classpath. If the RMI stubs are available via an FTP or HTTP url in the server's classpath, the client can download them on a different host.

For more on RMI class loading see http://java.sun.com/j2se/1.4.2/docs/guide/rmi/codebase.html.

Using RMI/IIOP

If you want to use RMI/IIOP instead of plain RMI, you need to do a few things differently:

- Use a corbaname URL as the value of rmi:address in your contract.
- Make sure your servant class extends javax.rmi.PortableRemoteObject.

- Specify the -iiop flag when running **rmic** to generate your stubs. For more information see Sun's RMIC documentation [http://java.sun.com/j2se/1.4.2/docs/tooldocs/solaris/rmic.html].
- Store the remote object's address in a CORBA naming service.

Configuring an application to use RMI

Unlike most Artix bindings, the RMI binding does not cause your application to automatically load the plug-ins it needs. To configure your application to use RMI you must add the following to your application's configuration:

```
orb_plugins=[..., "java", ...];
java plugins=["rmi"];
```

For more information see the Artix Configuration Reference, C++ Runtime [../../config ref/cpp/index.htm].



Note

RMI support is implemented using a JNI layer in the C++ runtime.

Limitations

The RMI support in Artix has the following limitations:

- The RMI support bypasses all Artix interceptors.
- The router does not support RMI.
- Applications using RMI must be explicitly configured to load the RMI plug-in and the Java plug-in. See the Artix Configuration Reference, C++ Runtime [../../config ref/cpp/index.htm].



Note

RMI support is implemented using a JNI layer in the C++ runtime.

- RMI is only available to Artix endpoints developed in Java.
- Artix security features are not available when using RMI.
- The APIs that resolve a service given only a QName do not work for services using RMI.

• You cannot register transient services with RMI.

Logging Errors

For ports that use the RMI binding you may see errors like this in the logs:

(IT_BUS.WSDL:0) E - WSDL for Port hello in service HelloRmiSer vice xmlns="http://www.iona.com/com.iona.jbus.bind ings.rmi.Hello" is not valid. It doesn't have any contents. ([[RmiBinding]])

These can be ignored.

Using Tibco Rendezvous Messages

Tibco Rendezvous applications typically use a Tibco specific data format called a TibrvMsg. Artix ESB provides a very flexible mechanism for mapping messages into the TibrvMsg format. This allows you to integrate with existing Tibco/RV applications by service-enabling them.

The TibrvMsg binding provides default mappings for most XML Schema constructs to simplify defining a TibrvMsg in a WSDL contract. The TibrvMsg binding also supports custom mappings between the messages defined in a WSDL contract and the physical representation of a TibrvMsg. Custom mappings also support the inclusion of static binding-only data.

Defining a TibrvMsg Binding	106
Default Mappings for TibrvMsg	
Defining Array Mapping Policies	
Defining a Custom TibrvMsg Mapping	
Adding Context Information to a TibryMsg	

Defining a TibrvMsg Binding

Overview

The Artix ESB TibrvMsg binding provides a set of default mappings to make writing a binding simple. By default, messages are mapped into a root TibrvMsg such that parts defined using XML Schema native types become TibrvMsgFields of the root TibrvMsg and parts defined using complex types become TibrvMsgs within the root message. The elements comprising a complex type also follow the same default mapping behavior. The default mappings will work for most basic applications. For a detailed explanation of how WSDL types are mapped to TibrvMsg see Default Mappings for TibrvMsg on page 112.

Procedure

To map a logical interface to a TibrvMsg:

- Add the proper namespace reference to the definition element of your contract. See Namespace on page 107.
- Add a WSDL binding element to your contract to hold the TibrvMsg binding, give the binding a unique name, and specify the port type that represents the interface being bound.
- 3. Add a tibrv:binding element as a child of the new binding element to identify this as a TibrvMsg binding and specify any global parameters.
- For each operation defined in the bound interface, add a WSDL operation element to hold the binding information for the operation's messages.
- 5. For each operation in the binding, add a tibrv:operation child element and set its attributes.
- For each operation in the binding, add the input, output, and fault children elements to represent the messages used by the operation. These elements correspond to the messages defined in the port type definition of the logical operation.
- 7. For each input element in the binding, add a tibrv:input child element and set its attributes.

- 8. For each output element in the binding, add a tibrv:output child element and set its attributes.
- To add custom message mappings see Defining a Custom TibrvMsg Mapping on page 122.

Namespace

The extensions used to describe TibrvMsg bindings are defined in the namespace http://schemas.iona.com/transports/tibrv. Artix tools use the prefix tibrv to represent the tagged data extensions. Add the following line to the definitions element of your contract:

xmlns:tibrv="http://schemas.iona.com/transports/tibrv"

tibrv:binding

tibrv:binding is an immediate child of the WSDL binding element and identifies that the data is to be packed into a TibrvMsg. Its attributes are described in Table $\,12$ on page $\,107$.

Table 12. Attributes for tibry:binding

Attribute	Purpose
	An optional attribute that specifies the character set used in encoding string data included in the message. The default value is utf-8.
stringAsOpaque	An optional attribute that specifies how string data is passed in messages. false, the default
	value, specifies that string data is passed as <code>TIRBMSG_STRING</code> . <code>true</code> specifies that string
	data is passed as OPAQUE.

In addition to the above properties, tibrv:binding can also specify a policy for how array data is handled for messages using the binding. The array policy is set using a child tibrv:array element. The array policy set at the binding level can be overridden on a per-operation basis, per-message basis, and a per-type basis. For information on defining array policies see Defining Array Mapping Policies on page 117.

The tibrv:binding element can also define binding-only message data using the tibrv:msg element, the tibrv:field element, or tibrv:context

element. Any binding-only data defined at the binding level is attached to all messages that use the binding.

tibrv:operation

tibry:operation is the immediate child of a WSDL operation element. tibry:operation has no attributes. It can, however, specify an operation-specific array policy using a a child tibry:array element. This array policy overrides any array policy set at the binding level. For information on defining array policies see Defining Array Mapping Policies on page 117.

Within a tibrv:operation element you can also define binding-only message data using the tibrv:msg element, the tibrv:field element, or tibrv:context element. Any binding-only data defined at the operation level is attached to all messages that make up the operation.

tibrv:input

tibrv:input is the immediate child of a WSDL input element and defines a number of properties used in mapping the input message to a TibrvMsg. Its attributes are described in Table 13 on page 108.

Table 13. Attributes for tibry:input

Attribute	Purpose
messageNameFieldPath	An optional attribute that specifies the field path that includes the message name. If this attribute is not specified, the first field in the top level message will be used as the message name and given the value <code>IT_BUS_MESSAGE_NAME</code> .
messageNameFieldValue	An optional attribute that specifies the field value that corresponds to the message name. If this attribute is not specified, the WSDL message's name will be used.
stringEncoding	An optional attribute that specifies the character set used in encoding string data included in the message. This value will override the value set in tibrv:binding.
stringAsOpaque	An optional attribute that specifies how string data is passed in the message. false specifies that string data is passed as TIRBMSG_STRING. true specifies that string data is passed as OPAQUE. This value will override the value set in tibrv:binding.

In addition to the above properties, tibrv:input can also specify a policy for how array data is handled for messages using the binding. The array policy is set using a child tibrv:array element. The array policy set at this level

overrides any policies set at the binding level or the operation level. For information on defining array policies see Defining Array Mapping Policies on page 117.

The tibrv:input element also defines any custom mappings between the WSDL messages defined in the contract and the physical TibrvMsg on the wire. A custom mapping can also include binding-only message data and context information. For information on defining custom data mappings see Defining a Custom TibrvMsg Mapping on page 122.

tibrv:output

tibrv:output is the immediate child of a WSDL output element and defines a number of properties used in mapping the output message to a TibrvMsg. Its attributes are described in Table 14 on page 109.

Table 14. Attributes for tibry:output

Attribute	Purpose			
messageNameFieldPath	An optional attribute that specifies the field path that includes the message name. If this attribute is not specified, the first field in the top level message will be used as the message name and given the value <code>IT_BUS_MESSAGE_NAME</code> .			
messageNameFieldValue	An optional attribute that specifies the field value that corresponds to the message name. If this attribute is not specified, the WSDL message's name will be used.			
stringEncoding	An optional attribute that specifies the character set used in encoding string data included in the message. This value will override the value set in <pre>tibrv:binding</pre> .			
stringAsOpaque	An optional attribute that specifies how string data is passed in the message. false specifies that string data is passed as TIRBMSG_STRING. true specifies that string data is passed as OPAQUE. This value will override the value set in tibrv:binding.			

In addition to the above properties, tibrv:output can also specify a policy for how array data is handled for messages using the binding. The array policy is set using a child tibrv:array element. The array policy set at this level overrides any policies set at the binding level or the operation level. For information on defining array policies see Defining Array Mapping Policies on page 117.

The tibrv:output element also defines any custom mappings between the WSDL messages defined in the contract and the physical TibrvMsg on the

wire. A custom mapping can also include binding-only message data and context information. For information on defining custom data mappings see Defining a Custom TibrvMsg Mapping on page 122.

Example

Example 51 on page 110 shows an example of a contract containing a default TibrvMsg binding.

Example 51. Default TibrvMsg Binding

```
<?xml version="1.0" encoding="UTF-8"?>
<definitions name="widgetOrderForm.wsdl"</pre>
targetNamespace="http://widgetVendor.com/widgetOrderForm"
xmlns="http://schemas.xmlsoap.org/wsdl/"
xmlns:tns="http://widgetVendor.com/widgetOrderForm"
xmlns:soap="http://schemas.xmlsoap.org/wsdl/soap/"
xmlns:tibrv="http://schemas.iona.com/transports/tibrv"
xmlns:xsd="http://www.w3.org/2001/XMLSchema"
xmlns:xsd1="http://widgetVendor.com/types/widgetTypes">
<tvpes>
 <schema targetNamespace="http://widgetVendor.com/types/widgetTypes"</pre>
   xmlns="http://www.w3.org/2001/XMLSchema"
   xmlns:wsdl="http://schemas.xmlsoap.org/wsdl/">
      <xsd:complexType name="Address">
        <xsd:sequence>
          <xsd:element name="name" type="xsd:string"/>
          <xsd:element name="street" type="xsd:string"</pre>
                       minOccurs="1" maxOccurs="5"/>
          <xsd:element name="city" type="xsd:string"/>
          <xsd:element name="state" type="xsd:string"/>
          <xsd:element name="zipCode" type="xsd:string"/>
        </xsd:sequence>
      </xsd:complexType>
      <xsd:complexType name="widgetOrderInfo">
        <xsd:sequence>
          <xsd:element name="amount" type="xsd:int"/>
          <xsd:element name="order date"</pre>
                       type="xsd:string"/>
          <xsd:element name="type" type="xsd:string"/>
          <xsd:element name="shippingAddress"</pre>
                       type="xsd1:Address"/>
        </xsd:sequence>
      </xsd:complexType>
      <xsd:complexType name="widgetOrderBillInfo">
        <xsd:sequence>
          <xsd:element name="amount" type="xsd:int"/>
          <xsd:element name="order date"</pre>
                       type="xsd:string"/>
          <xsd:element name="type" type="xsd:string"/>
```

```
<xsd:element name="amtDue" type="xsd:float"/>
          <xsd:element name="orderNumber"</pre>
                        type="xsd:string"/>
          <xsd:element name="shippingAddress"</pre>
                        type="xsd1:Address"/>
        </xsd:sequence>
      </xsd:complexType>
   </schema>
 </types>
 <message name="widgetOrder">
   <part name="widgetOrderForm"</pre>
          type="xsd1:widgetOrderInfo"/>
 </message>
 <message name="widgetOrderBill">
   <part name="widgetOrderConformation"</pre>
          type="xsd1:widgetOrderBillInfo"/>
 </message>
 <portType name="orderWidgets">
   <operation name="placeWidgetOrder">
     <input message="tns:widgetOrder" name="order"/>
      <output message="tns:widgetOrderBill" name="bill"/>
   </operation>
 </portType>
 <binding name="orderWidgetsBinding"</pre>
           type="tns:orderWidgets">
   <tibrv:binding/>
      <operation name="placeWidgetOrder">
        <tibrv:operation/>
        <input name="widgetOrder">
         <tibrv:input/>
        </input>
        <output name="widgetOrderBill">
          <tibrv:output/>
       </output>
    </operation>
 </binding>
 <service name="orderWidgetsService">
   <port name="widgetOrderPort" binding="tns:orderWidgetsBinding">
    . . .
   </port>
 </service>
</definitions>
```

Default Mappings for TibrvMsg

TIBRVMSG type mapping

Table $\,15\,$ on page $\,112\,$ shows how Artix maps XML Schema types into TibrvMsg data types.

Table 15. TIBCO to XSD Type Mapping

TIBRVMSG	XSD
TIBRVMSG_STRING	xsd:string
TIBRVMSG_BOOL	xsd:boolean
TIBRVMSG_I8	xsd:byte
TIBRVMSG_I16	xsd:short
TIBRVMSG_I32	xsd:int
TIBRVMSG_I64	xsd:long
TIBRVMSG_U8	xsd:unsignedByte
TIBRVMSG_U16	xsd:unsignedShort
TIBRVMSG_U32	xsd:unsignedInt
TIBRVMSG_U64	xsd:unsignedLong
TIBRVMSG_F32	xsd:float
TIBRVMSG_F64	xsd:double
TIBRVMSG_STRING	xsd:decimal
TIBRVMSG_DATETIME a	xsd:dateTime
TIBRVMSG_OPAQUE	xsd:base64Binary
TIBRVMSG_OPAQUE	xsd:hexBinary
TIBRVMSG_STRING	xsd:QName
TIBRVMSG_STRING	xsd:nonPositiveInteger
TIBRVMSG_STRING	xsd:negativeInteger
TIBRVMSG_STRING	xsd:nonNegativeInteger

TIBRVMSG	XSD
TIBRVMSG_STRING	xsd:positiveInteger
TIBRVMSG_STRING	xsd:time
TIBRVMSG_STRING	xsd:date
TIBRVMSG_STRING	xsd:gYearMonth
TIBRVMSG_STRING	xsd:gMonthDay
TIBRVMSG_STRING	xsd:gDay
TIBRVMSG_STRING	xsd:gMonth
TIBRVMSG_STRING	xsd:anyURI
TIBRVMSG_STRING	xsd:token
TIBRVMSG_STRING	xsd:language
TIBRVMSG_STRING	xsd:NMTOKEN
TIBRVMSG_STRING	xsd:Name
TIBRVMSG_STRING	xsd:NCName
TIBRVMSG_STRING	xsd:ID

^aWhile TIBRVMSG_DATATIME has microsecond precision, xsd:dateTime only supports millisecond precision. Therefore, Artix rounds all times to the nearest millisecond.

Sequence complex types

Sequence complex types are mapped to a TibrvMsg message as follows:

- The elements of the complex type are enclosed in a TibrvMsg instance.
- If the complex type is specified as a message part, the value of the part element's name attribute is used as the name of the generated TibrvMsg.
- If the complex type is specified as an element, the value of the element element's name attribute is used as the name of the generated TibrvMsg.
- The TibrvMsg id is 0.

- The elements are the mapped to child TibrvMsgField instances of the wrapping TibrvMsg.
- If an element of the sequence is of a complex type, it will be mapped into a TibrvMsg instance that conforms to the default mapping rules.
- The value of the element element's name attribute is used as the name of the generated TibrvMsgField instance.
- The child fields' ids are 0.
- The child fields are serialized in the same order as they appear in the schema definition.
- The child fields are deserialized in the same order as they appear in schema definition.

All complex types

All complex types are mapped to a TibrvMsg message as follows:

- The elements of the complex type are enclosed in a TibrvMsg instance.
- If the complex type is specified as a message part, the value of the part element's name attribute is used as the name of the generated TibrvMsg.
- If the complex type is specified as an element, the value of the element element's name attribute is used as the name of the generated TibrvMsg.
- The TibrvMsg id is 0.
- The elements are the mapped to child TibrvMsgField instances of the wrapping TibrvMsg.
- If an element of the all is of a complex type, it will be mapped into a TibrvMsg instance that conforms to the default mapping rules.
- The value of the element element's name attribute is used as the name of the generated TibrvMsgField instance.
- The child field's ids are 0.
- The child fields are serialized in the same order as they appear in the schema definition.

• The child fields can be deserialized in any order.

Choice complex types

Choice complex types are mapped to a TibrvMsg message as follows:

- The elements of the complex type are enclosed in a TibrvMsg instance.
- If the complex type is specified as a message part, the value of the part element's name attribute is used as the name of the generated TibrvMsg.
- If the complex type is specified as an element, the value of the element element's name attribute is used as the name of the generated TibrvMsg.
- The TibrvMsg id is 0
- There must only be one and only child field in this TibrvMsg message that corresponds to the active choice element.
- The child field has the name of the corresponding choice's active element name.
- The child field id is zero.
- During deserialization the binding runtime will extract the first child field from this message using index equal to 0 as the key. If no field is found then this choice is considered an empty choice.

NMTOKEN

NMTOKEN schema types are mapped as follows:

- The NMTOKEN is enclosed in a TibrvMsg instance.
- If the NMTOKEN is specified as a message part, the value of the part element's name attribute is used as the name of the generated TibrvMsg.
- If the NMTOKEN is specified as an element, the value of the element element's name attribute is used as the name of the generated TibrvMsg.
- The TibrvMsg id is 0
- Each NMTOKEN is mapped to a child TibrvMsgField instance of this TibrvMsg.

 The names of the children fields are an ever increasing counter values beginning with o.

Default mapping of arrays

XML Schema elements that are not mapped to native Tibrv scalar types and have minOccurs != 1 and maxOccurs != 1 are mapped as follows:

- Array elements are stored in a TibrvMsg instance at the same scope as the sibling elements of this array element.
- Array element names are a result of an expression evaluation. The expression is evaluated for every array element.
- The default array element name expression is concat(xml:attr('name'),
 ' ', counter(1, 1).
- If an instance of an array element has 0 elements then this array instance will have nothing loaded onto the wire. Currently this is not true for scalar arrays that are loaded as a single field.

Default mapping for scalar arrays

The XML Schema elements that are mapped to native Tibrv scalar types and have minOccurs != 1 and maxOccurs != 1 are mapped as follows:

- Array elements are stored in a TibrvMsg instance at the same scope as sibling elements of this array element.
- The binding utilizes the Tibrv native array mapping to store XML Schema arrays. Hence, there will be only one TibrvMsgField with the name equal to that of the XML Schema element name defining this array.

Defining Array Mapping Policies

Overview

Because TibrvMsg does not natively support sparsely populated arrays, the Artix TibrvMsg binding allows you to define how array elements are mapped into a TibrvMsg when they are written to the wire using the tibrv:array element. In addition, the Artix TibrvMsg binding allows you to define the naming schema used for array elements when they are mapped into TibrvMsgField instances.

Policy scoping

The tibrv:array element can define array properties at any level of granularity by making it the child of different TibrvMsg binding elements. Table 16 on page 117 shows the effect of setting tibrv:array at different levels of a binding.

Table 16. Effect of tibry:array

Child of	Effect	
tibrv:binding	Sets the array policies for all messages in the binding.	
tibrv:operation	Array policies set at the operation level only affect the messages defined within the parent operation element. They override any array policies set at the binding level.	
tibrv:input	Array policies set at this level only affect the input message. They override any array policies set at the binding or operation level.	
tibrv:output	Array policies set at this level only affect the output message. They override any array policies set at the binding or operation level.	
tibrv:msg	Array policies set at this level affect only the fields defined within the tibrv:msg element. They override any array policies set at higher levels.	
tibrv:field	Array policies set at this level affect only the TibrvMsg field being defined. They override any array policies set at higher levels.	

Array policies

The array policies are set using the attributes of tibrv:array.

Table 17 on page 118 describes the attributes used to set array policies.

Table 17. Attributes for tibrv:array

Attribute	Purpose				
elementName	Specifies an expression that when evaluated will be used as the name of the TibrvMsg field to which array elements are mapped. The default element naming scheme is to concatenate the value of WSDL element element's name attribute with a counter.				
	For information on specifying naming expressions see Custom array naming expressions on page 119.				
integralAsSingleField	Specifies how scalar array data is mapped into TibrvMsgField instances. true, the				
	default, specifies that arrays are mapped into a single TibrvMsgField. false specifies				
	that each member of an array is mapped into a separate TibrvMsgField.				
loadSize	Specifies if the number of elements in an array is included in the TibrvMsg. true				
	specifies that the number of elements in the array is added as a TibrvMsgField in same TibrvMsg as the array. false, the default, specifies that the number of elem				
	in the array is not included in the TibrvMsg.				
sizeName	Specifies an expression that when evaluated will be used as the name of the TibrvMsgField to which the size of the array is written. The default naming scheme is to concatenate the value of WSDL element element's name attribute with @size.				
	For information on specifying naming expressions see Custom array naming expressions on page 119 .				

Sparse arrays

A sparse array is an array with some of the elements set to nil. For instance, if an array has 10 elements, the 3rd and fifth elements may be nil. Tibco/RV has no way of natively representing sparse arrays or nil element members. This presents two problems:

- Tibco/RV throws an exception when it encounters nil scalar values that are mapped to a TibrvMsgField.
- There is no mechanism for maintaining the element positions of the non-nil members of the array.

To solve both problems you would specify array policies such that the size of the array is written to the wire and that each element of the array is written to the wire as a separate TibrvMsgField. To specify that the array size is written to the wire use loadSize="true". To specify that each member of the array is written in a separate TibrvMsgField use integralAsSingleField="false".

The resulting TibrvMsg would have one field for each non-nil member of the array and a field specifying the size of the array. Artix can use this information

to reconstruct the sparse array when it is passed through the TibrvMsg binding. A Tibco/RV application would need to implement the logic to handle the information.

Custom array naming expressions

When specifying a naming policy for array element names you use a string expression that combines XML properties, strings, and custom naming functions. For example, you could use the expression $concat(xml:attr('name'), '_', counter(1,1))$ to specify that each element in the array street is named street n.

Table 18 on page 119 shows the available functions for use in building array element names.

Table 18. Functions Used for Specifying TibrvMsg Array Element Names

Function	Purpose		
xml:attr('attribute')	Inserts the value of the named attribute.		
concat(item1, item2,)	Concatenates all of the elements into a single string.		
counter(start, increment)	Adds an increasing numerical value. The counter starts at <code>start</code> and increases		
	by increment.		

Example

Example 52 on page 119 shows an example of an Artix contract containing a TibrvMsg binding that uses array policies. The policies are set at the binding level and:

- Force the name of the TibrvMsg containing array elements to be named street0, street1,
- Write out the number of elements in each street array.
- Force each element of a street array to be written out as a separate field.

Example 52. TibrvMsg Binding with Array Policies Set

```
<?xml version="1.0" encoding="UTF-8"?>
<definitions name="widgetOrderForm.wsdl"
  targetNamespace="http://widgetVendor.com/widgetOrderForm"
  xmlns="http://schemas.xmlsoap.org/wsdl/"
  xmlns:tns="http://widgetVendor.com/widgetOrderForm"
  xmlns:soap="http://schemas.xmlsoap.org/wsdl/soap/"
  xmlns:tibrv="http://schemas.iona.com/transports/tibrv"</pre>
```

```
xmlns:xsd="http://www.w3.org/2001/XMLSchema"
xmlns:xsd1="http://widgetVendor.com/types/widgetTypes">
<types>
  <schema targetNamespace="http://widgetVendor.com/types/widgetTypes"</pre>
   xmlns="http://www.w3.org/2001/XMLSchema"
    xmlns:wsdl="http://schemas.xmlsoap.org/wsdl/">
     <xsd:complexType name="Address">
       <xsd:sequence>
         <xsd:element name="name" type="xsd:string"/>
         <xsd:element name="street" type="xsd:string"</pre>
                       minOccurs="1" maxOccurs="5"
                       nillable="true"/>
         <xsd:element name="city" type="xsd:string"/>
         <xsd:element name="state" type="xsd:string"/>
         <xsd:element name="zipCode" type="xsd:string"/>
       </xsd:sequence>
     </xsd:complexType>
  </schema>
</types>
<message name="addressRequest">
  <part name="resident" type="xsd:string"/>
</message>
<message name="addressResponse">
  <part name="address" type="xsd1:Address"/>
</message>
<portType name="theFourOneOne">
  <operation name="lookUp">
     <input message="tns:addressRequest" name="request"/>
     <output message="tns:addressResponse"</pre>
             name="response"/>
  </operation>
</portType>
 <binding name="lookUpBinding" type="tns:theFourOneOne">
  <tibry:binding>
      <tibrv:array elementName="concat(xml:attr('name'), counter(0, 1))"</pre>
                   integralsAsSingleField="false"
                   loadSize="true"/>
  <\tibrv:binding>
  <operation name="lookUp">
     <tibry:operation/>
       <input name="addressRequest">
         <tibrv:input/>
       </input>
       <output name="addressResponse">
         <tibrv:output/>
     </output>
```

Defining a Custom TibrvMsg Mapping

Overview

For instances where the default mappings are insufficient to map the TibrvMsgs to corresponding WSDL messages, you can define custom mappings that allow you to specify exactly how the WSDL message parts are mapped into a TibrvMsg. Custom TibrvMsg mappings allow you to:

- override the native XML Schema type specification of contract elements.
- add binding-only elements to the TibrvMsg placed on the wire.
- place globally used contract elements in higher levels of the binding.
- change how contract elements are mapped into nested TibrvMsg structures.

Custom TibrvMsg binding elements are defined using a combination of tibrv:msg on page 136 elements and tibrv:field on page 136 elements.

Contract elements vs. binding-only elements

A contract element is an atomic piece of a message defined in the logical description of the interface being bound. It can be a native XML Schema type such as xsd:int, in which case it is mapped to a TibrvMsgField. Or it can be an instance of a complex type, in which case it is mapped to a TibrvMsg. For example, if a message has a part that is of type xsd:string, the part is a contract element. In contract fragment shown in Example 53 on page 122, the message part title is a contract element that will be mapped to a TibrvMsgField. The message part tale is a contract element that will be mapped to a TibrvMsg that contains three TibrvMsgField entries.

Example 53. TibrvMsg Contract Elements

A binding-only element is any artifact that is added to the message as part of the binding. The main purpose of a binding-only element is to add data required by a native Tibco application to a message produced by an Artix application. Binding-only elements are not passed back into an Artix application. However, a native Tibco application will have access to binding-only elements.

You can add custom TibrvMsg binding elements to any of the TibrvMsg binding elements. The order in which custom TibrvMsg binding elements are serialized is as follows:

- 1. Immutable root TibrvMsg wrapper.
- 2. Custom elements defined in tibrv:binding are added for all messages.
- 3. Custom elements defined in tibrv:operation for all messages used by the WSDL operation.
- Custom elements defined in tibrv:input or tibrv:output for the specific message.

If you define a binding-only element in the tibrv:binding element, it will be the first field in the TibrvMsg generated for all messages that are generated by the binding. If you also added a binding-only field in the tibrv:operation for the operation getHeader, messages used by getHeader would have both binding-only fields.



Note

If you add a custom mapped contract element at any scope above the tibrv:input or the tibrv:output level, you must be certain that it is part of the logical messages for all elements at a lower scope. For example, if a contract element is given a custom mapping in a tibrv:operation, the corresponding WSDL message must be

Scoping

used by both the input and output messages. If it is not an exception will be thrown.

Casting XMLSchema types

If the default mapping between the type of a contract element and the type of the corresponding TibrvMsgField is not appropriate, you can use the type attribute of tibrv:field to change the type of the contract element. The type attribute allows you to cast one native XML Schema type into another native XML Schema type.

When Artix finds a tibrv:field element whose name attribute corresponds to a part element defined in the contract, or an element of a complex type used as a part, and whose type attribute is set, it will convert the value of the message part into the specified type. For example, given the contract fragment in Example 54 on page 124, the value of input1 would be converted from an int to a string. So if input1 had a value of 3, the TibrvMsg binding would turn it into the string '3'.

Example 54. Casting in a TibrvMsg Binding

```
<definitions ...>
 <message name="request">
   <part name="input1" type="xsd:int"/>
 </message>
 <portType name="castor">
   <operation name="ascend">
     <input message="tns:request" name="day"/>
   </operation>
 </portType>
 <binding name="castorTib" portType="castor">
   <tibrv:binding/>
   <operation name="ascend">
     <tibry:operation/>
     <input message="tns:request" name="day">
       <tibrv:input>
         <tibrv:field name="input1" type="xsd:string"/>
       </tibrv:input>
     </input>
   </operation>
 </binding>
```

</definitions>

Table 19 on page 125 shows the matrix of valid casts for native XML Schema types.

Table 19. Valid Casts for TibrvMsg Binding

Туре	Full Support	Restricted Support ^a	
byte	short, int, long, float, double, decimal, string, boolean	<pre>unsignedByte, usignedShort, unsignedInt, unsignedLong</pre>	
unsignedByte	<pre>short, usignedShort, int, unsignedInt, long, unsignedLong, float, double, decimal, string, boolean</pre>	byte	
short	int, long, float, double, decimal, string, boolean	<pre>byte, unsignedByte, usignedShort, unsignedInt, unsignedLong</pre>	
unsignedShort	byte, unsignedByte, short	<pre>int, unsignedInt, long, unsignedLong, float, double, decimal, string, boolean</pre>	
int	long, decimal, string, boolean	<pre>byte, unsignedByte, short, usignedShort, unsignedInt, unsignedLong, float, double</pre>	
unsignedInt	long, unsignedLong, decimal, string, boolean	<pre>byte, unsignedByte, short, usignedShort, int, float, double</pre>	
long	decimal, string, boolean	<pre>byte, unsignedByte, short, usignedShort, int, unsignedInt, unsignedLong, float, double</pre>	
unsignedLong	decimal, string, boolean	<pre>byte, unsignedByte, short, usignedShort, int, unsignedInt, long, float, double</pre>	
float	double, decimal, string, boolean	<pre>byte, unsignedByte, short, usignedShort, int, unsignedInt, long, unsignedLong</pre>	
double	decimal, string, boolean	<pre>byte, unsignedByte, short, usignedShort, int, unsignedInt, long, unsignedLong, float</pre>	

Туре	Full Support	Restricted Support ^a
decimal	string, boolean	<pre>byte, unsignedByte, short, usignedShort, int, unsignedInt, long, unsignedLong, float, double</pre>
string ^b		<pre>byte, unsignedByte, short, usignedShort, int, unsignedInt, long, unsignedLong, float, double, decimal, boolean, QName, DateTime</pre>
boolean	<pre>byte, unsignedByte, short, usignedShort, int, unsignedInt, long, unsignedLong, float, double</pre>	decimal, string
QName		string
DateTime		string

^aMust be within the appropriate value range.

Adding binding-only elements to a contract

As mentioned in Scoping on page 123, a binding-only element can be added to a TibrvMsg binding at any point in its definition. Before adding a binding-only element you should determine the proper placement for its inclusion in the binding. For example, if you are interoperating with a Tibco system that expects every message to have a header, you would most likely add the header definition in the tibrv:binding element.

However, if the Tibco system required a static footer for every message, you would need to add the footer to the tibrv:input and tibrv:output elements. This is because of the serialization order of the elements in the TibrvMsg binding. Elements are added to the serialized message from the global scope to the local scope in order.

Binding-only elements are specified using a combination of tibrv:msg elements and tibrv:field elements. When specifying a binding-only element you need to specify a value for the alias attribute. The alias attribute specifies the name of the generated TibrvMsg element. For tibrv:field elements you also need to specify values for the type attribute and the value attribute. The type attribute specifies the XML Schema type

^bIn addition to a, the syntax must also conform

of the element being added and the value attribute specifies the value to be placed in the resulting TibrvMsgField.

Example 55 on page 127 shows a TibrvMsg binding that adds a static header to each message that is put on the wire.

Example 55. TibrvMsg Binding with Binding-only Elements

A message generated by the binding in Example 55 on page 127 would have as its first member a TibrvMsg called header as shown in Example 56 on page 127.

Example 56. TibrvMsg with a Header

```
TibrvMsgField
{
    name = "header";
    id = 0;
    data.msg =
    {
        TibrvMsgField
        {
            name = "class";
            id = 0;
            data.str = "greek";
            size = sizeof(data);
            count = 1;
            type = TIBRVMSG_STRING;
        }
        TibrvMsgField
        {
            ribrvMsgField
        }
        }
        TibrvMsgField
        {
            ribrvMsgField
        }
        }
        Count = 1;
        Count = 1;
```

```
name = "form";
   id = 0;
   data.str = "poetry";
   size = sizeof(data);
   count = 1;
   type = TIBRVMSG_STRING;
}
size = sizeof(data);
count = 1;
type = TIBRVMSG_MSG;
}
...
}
```

Placing binding-only elements between contract elements

In addition to adding extra-information at the beginning and end of messages, you can place binding-only elements between contract elements in a message. For example, the default mapping of the message taleResponse, defined in

Example 53 on page 122, would produce the TibrvMsg shown in Example 57 on page 128.

Example 57. Default TibrvMsg Example

```
TibrvMsq
 TibrvMsgField
   name = "tale";
   id = 0;
   data.msg =
     TibrvMsgField
       name = "castor";
       id = 0;
        data.str = "This one is a horse trainer.";
        size = sizeof(data);
       count = 1;
        type = TIBRVMSG STRING;
     TibrvMsgField
       name = "pollux";
        id = 0;
        data.str = "This one is a boxxer.";
        size = sizeof(data);
```

```
count = 1;
    type = TIBRVMSG_STRING;
}
TibrvMsgField
{
    name = "hellen";
    id = 0;
    data.str = "false";
    size = sizeof(data);
    count = 1;
    type = TIBRVMSG_BOOL;
}
size = sizeof(data);
count = 1;
type = TIBRVMSG_MSG;
}
...
}
```

If the Tibco application you are integrating with requires an additional TibrvMsgField or an additional TibrvMsg between pollux and hellen, as shown in Example 58 on page 129, you could add it to the binding by redefining the mapping of the entire contract element to include a binding-only element.

Example 58. TibrvMsg with added TibrvMsg Example

```
TibrvMsgField
{
    name = "tale";
    id = 0;
    data.msg =
    {
        TibrvMsgField
        {
            name = "castor";
            id = 0;
            data.str = "This one is a horse trainer.";
            size = sizeof(data);
            count = 1;
            type = TIBRVMSG_STRING;
        }
        TibrvMsgField
        {
            name = "pollux";
        }
```

```
id = 0;
    data.str = "This one is a boxxer.";
   size = sizeof(data);
   count = 1;
   type = TIBRVMSG STRING;
TibrvMsgField
 name = "clytemnestra";
  id = 0;
  data.msg =
   TibrvMsgField
     name = "father";
     id = 0;
     data.str = "tyndareus";
     size = sizeof(data);
     count = 1;
     type = TIBRVMSG STRING;
   TibrvMsqField
     name = "husbands";
     id = 0;
     data.i32 = 2;
     size = sizeof(data);
     count = 1;
     type = TIBRVMSG I32;
  size = sizeof(data);
  count = 1;
  type = TIBRVMSG MSG;
 TibrvMsgField
  name = "hellen";
  id = 0;
  data.str = "false";
   size = sizeof(data);
   count = 1;
   type = TIBRVMSG BOOL;
} size = sizeof(data);
count = 1;
type = TIBRVMSG_MSG;
```

```
}
```

To add the binding-only element clytemnestra to the default binding of the message leda you would do the following:

- 1. Because the message leda is used as an output message, add a tibrv:msg child element to the tibrv:output element.
- 2. Set the tibrv:msg element's name attribute to the value of the corresponding contract message part that uses the type leda.
- 3. Add a tibrv:field element as a child of the tibrv:msg element.
- 4. Set the new tibrv: field element's name attribute to the value of the corresponding element's name attribute. In this instance, castor.
- 5. Repeat Step 3 on page 131 and Step 4 on page 131 for the second element, pollux, in leda.
- 6. To start the binding-only TibrvMsg element, add a tibrv:msg element after the tibrv:field element for pollux.
- 7. Set the new tibrv:msg element's alias attribute to clytemnestra.
- 8. Add a tibrv:field element as a child of the tibrv:msg element.
- 9. Set the tibry: field element's alias attribute to father.
- 10. Set the tibrv:field element's type attribute to xsd:string.
- 11. Set the tibry: field element's value attribute to tyndareus.
- 12. Repeat Step 8 on page 131 through Step 11 on page 131 for the second TibrvMsgField in clytemnestra.
- 13. On the same level as the tibrv:field elements mapping castor and pollux, add a tibrv:field element to map helen.

Example 59 on page 132 shows a binding for the message shown in Example 58 on page 129.

Example 59. TibrvMsg Binding with an Added Binding-only Element

```
<binging name="tibBinding">
 <tibry:binding/>
 <operation ...>
   <tibry:operation/>
   <input ...>
     <tibrv:input/>
   </input>
   <output name="response" message="tns:taleResponse">
     <tibrv:output>
       <tibry:msq name="tale">
         <tibrv:field name="castor"/>
         <tibrv:field name="pollux"/>
          <tibry:msg alias="clytemnestra">
            <tibrv:field alias="father" type="xsd:string"</pre>
                         value="tyndareus"/>
            <tibry:field alias="husbands" type="xsd:int"
                         value="2"/>
         <tibrv:msq/>
         <tibrv:field name="hellen"/>
       </tibrv:msq>
     </tibry:output>
   </output>
 </operation>
</binding>
```

Creating a custom mapping for a message defined in the contract

Using the tibrv:msg elements and tibrv:field elements you can change how contract elements are broken into TibrvMsgs and TibrvMsgFields. For a detailed discussion of the default TibrvMsg mapping see Default Mappings for TibrvMsg on page 112.

You can alter this default mapping to add more wrapping to the TibrvMsgFields. For instance, if a message consists of a single xsd:string part, it would be mapped to a TibrvMsg similar to the one shown in Example 60 on page 132.

Example 60. TibrvMsg for a String

```
TibrvMsg
{
  TibrvMsgField
  {
```

```
name = "electra";
id = 0;
data.str = "forelorn";
size = sizeof(data);
count = 1;
type = TIBRVMSG_STRING;
}
}
```

However, you could specify that instead of being mapped straight to a TibrvMsgField, it be mapped to a TibrvMsg containing a TibrvMsgField as shown in Example 61 on page 133.

Example 61. TibrvMsg with a TibrvMsg with a String

```
TibrvMsq
 TibrvMsgField
   name = "grandchild";
   id = 0;
   data.msg =
     TibrvMsqField
       name = "electra";
       id = 0;
       data.str = "forelorn";
       size = sizeof(data);
       count = 1;
       type = TIBRVMSG STRING;
     }
   size = sizeof(data);
   count = 1;
   type = TIBRVMSG MSG;
```

To increase the depth of the wrapping of contract elements you define a custom TibrvMsg mapping that adds the desired number of levels. Each new level of wrapping is specified by a tibrv:msg element. To create the message shown in Example 61 on page 133 you would use a binding definition similar to the one shown in Example 62 on page 133 .

Example 62. TibrvMsg Binding with an Extra TibrvMsg Level

```
<binging name="tibBinding">
  <tibrv:binding/>
```

You can also use this feature to alter the wrapping of complex type elements. For example, if you were using the message defined in Example 53 on page 122 the default TibrvMsg would consist of one TibrvMsg, leda, containing 3 fields, one for each element in the structure, wrapped by the root TibrvMsg. You could modify the mapping of the logical message to a TibrvMsg that resembles the one shown in Example 63 on page 134 . The two elements castor and pollux have been wrapped in a TibrvMsg called brothers.

Example 63. TibrvMsg with Custom TibrvMsg Wrapping

```
TibrvMsq
 TibrvMsgField
   name = "tale";
   id = 0;
   data.msg =
     TibrvMsgField
       name = "brothers"
       id = 0;
        data.msg =
          TibrvMsgField
           name = "castor";
           id = 0;
           data.str = "This one is a horse trainer.";
           size = sizeof(data);
           count = 1;
            type = TIBRVMSG STRING;
          TibrvMsgField
```

```
name = "pollux";
         id = 0;
         data.str = "This one is a boxxer.";
         size = sizeof(data);
         count = 1;
         type = TIBRVMSG STRING;
     size = sizeof(data);
     count = 1;
     type = TIBRVMSG MSG;
   TibrvMsgField
    name = "hellen";
     id = 0;
    data.bool = false;
    size = sizeof(data);
     count = 1;
     type = TIBRVMSG BOOL;
 size = sizeof(data);
 count = 1;
 type = TIBRVMSG MSG;
}
```

Adding additional levels of wrapping within a complex type is done the same way as it is done with a message part. You place additional tibrv:msg elements around the contract elements you want to be at a deeper level.
Example 64 on page 135 shows a binding fragment that would create the TibrvMsg shown in Example 63 on page 134.

Example 64. Binding of a Complex Type with an Extra TibrvMsg Level

tibrv:msg

tibrv:msg instructs the binding runtime to create an instance of a TibrvMsg. Its attributes are described in Table 20 on page 136.

Table 20. Attributes for tibrv:msg

Attribute	Purpose			
name	Specifies the name of the contract element from which this TibrvMsg instance gets its value. If this attribute is not present, then the TibrvMsg is considered a binding-only element.			
alias	Specifies the value of the $name$ member of the TibrvMsg instance. If this attribute is not specified, then the binding will use the value of the $name$ attribute.			
element	Used only when tibrv:msg is an immediate child of tibrv:context. Specifies the QName of the element defining the context data to use when populating the TibrvMsg. See Adding Context Information to a TibrvMsg on page 138.			
id	Specifies the value of the id member of the TibrvMsg instance. The default value is 0.			
minOccurs/maxOccurs	Used only with contract elements. The values must be identical to the values specified in the schema definition.			

tibrv:field

 ${\tt tibrv:field}$ instructs the binding to create an instance of a TibrvMsgField. Its attributes are described in Table 21 on page 136 .

Table 21. Attributes for tibry: field

Attribute	Purpose
	Specifies the name of the contract element from which this TibrvMsgField instance gets its value. If this attribute is not present, then the TibrvMsgField is considered a binding-only element.

Attribute	Purpose			
alias	Specifies the value of the name member of the TibrvMsgField instance. If this attribute			
	is not specified, then the binding will use the value of the name attribute.			
element	Used only when tibrv:field is an immediate child of tibrv:context. Specifies the			
QName of the element defining the context data to use when populating the See Adding Context Information to a TibrvMsg on page 138.				
id	Specifies the value of the id member of the TibrvMsgField instance. The default va			
	is 0.			
type	Specifies the XML Schema type of the data being used to populate the data member of			
	the TibrvMsgField instance. For a list of supported types, see Default Mappings for TibrvMsg on page 112.			
value	Specifies the value inserted into the data member of the TibrvMsgField instance when			
	the field is a binding-only element.			
minOccurs/maxOccurs	Used only with contract elements. The values must be identical to the values specified in the schema definition.			

Adding Context Information to a TibrvMsg

Overview

By using Artix contexts, you can define binding-only data that is dynamically generated and consumed by Artix applications. Contexts are a feature of the Artix programming model that allow application developers to pass metadata up and down the messaging chain. When using the TibrvMsg binding, you can instruct your Artix application to use context data to populate outgoing binding-only fields. On the receiving end, the TibrvMsg binding takes the information and uses it to populate a context in the application. For information on using contexts in Artix applications, see Developing Artix Applications with C++ [../../prog_guide/index.htm] or Developing Artix Applications with JAX-RPC [../../jaxrpc pguide/index.htm].

Telling the binding to get information from Artix contexts

When defining a custom TibrvMsg binding, you use the tibrv:context element to inform the binding that the immediate child element is populated from an Artix context. The immediate child of a tibrv:context element must be either a tibrv:msg element or a tibrv:field element depending on what type of information is contained in the context.

You would use tibrv:msg for context data that is an instance of a complex XML Schema type. You could also use tibrv:msg if you want an instance of a native XML Schema type wrapped in a TibrvMsg. You would use tibrv:field to insert context data that was an instance of a native XML Schema type as a TibrvMsgField.

When a tibrv:msg element or a tibrv:field element are used to insert context information into a TibrvMsg they use the element attribute in place of the name attribute. The element attribute specifies the QName used to register the context data with the Artix bus. It must correspond to a globally defined XML Schema element. Also, when inserting context information you cannot specify values for any other attributes except the alias attribute.

Application considerations

When using context data in your TibrvMsg binding there is some application-specific information you need to abide by:

 At least one piece of the integrated solution must be an Artix application to process the context data.

- The Tibrv binding will automatically register, but not create an instance of, any contexts used in its binding definition with the Artix bus. Contexts are registered using the QName of the element specified in the contract.
- For any context data that will be sent in an input message, client-side Artix
 applications are responsible for creating an instance of the appropriate
 context data in the request context container before the message is handed
 off to the binding.
- Context data sent from a client in an input message will be available to server-side Artix applications in the request context once the message has been processed by the binding.
- For any context data that will be sent in an output message, server-side
 Artix applications are responsible for creating an instance of the appropriate
 context data in the reply context container before the message is handed
 off to the binding.
- Context data sent from a server in an output message will be available to client-side Artix applications in the reply context once the message has been processed by the binding.

Example

If you were integrating with a Tibco server that used a header to correlate messages using an ASCII correlation ID, you could use the TibrvMsg binding's context support to implement the correlation ID on the Artix side of the solution. The first step would be to define an XML Schema element called <code>corrID</code> for the context that would hold the correlation ID. Then in your

TibrvMsg binding definition you would include a tibrv:context element in the tibrv:binding element to specify that all messages passing through the binding will have the header. Example 65 on page 139 shows a contract fragment containing the appropriate entries for this scenario.

Example 65. Using Context Data in a TibrvMsg Binding

When you develop the Artix side of the solution, you will need to supply the logic for handling the context data stored in <code>corrID</code>. The context for <code>corrID</code> will be registered with the Artix bus using the QName

"http://widgetVendor.com/types/widgetTypes", "corrID". If the Artix side of your solution is a client, you will need to include logic to set an appropriate corrID in the request context before each request and to read each response's corrID from the response context. If the Artix side of your application is a server, you will need to include logic to read request's corrID from the request context and set an appropriate corrID in the reply context before sending the response.

Using the Pass Through Binding

The pass through binding allows you to send untyped message buffers through the run time as binary blobs. The runtime will make no attempts to interpret the data in the message.

Overview

The pass through binding is a simple binding for sending blobs of data across the wire. The binding makes no attempts to interpret the data and just writes the message to the wire as a string. It is ideal for dealing with data that uses custom encodings that cannot be properly described using one of the other Artix ESB bindings.

When sending data, an application can just simply stuff the binary data into a string buffer. The pass through binding will simply dump the data to the wire.

When reading data, the pass through binding simply reads messages into a string buffer. The string buffer is passed to the application layer. The binding does not make any effort to interpret the data or change it in anyway. The string buffer can be unpacked into an exact copy of the message sent across the wire.

Limitations

Because the pass through binding makes no effort to interpret the message contents and only interacts with string buffers it imposes some limitation on how you define your service's interface:

- Input messages can only have a single string part.
- Output messages can only have a single string part.
- On the server-side, requests are always handled by the first operation defined in the WSDL's portType element.

Namespace

The extensions used to describe the pass though binding are defined in the namespace http://schemas.iona.com/bindings/passthru. Add the following line to your contracts:

xmlns:passthru="http://schemas.iona.com/bindings/passthru"

Describing the binding

You describe a pass through binding by adding a single passthru:binding child to the WSDL binding element.

Example

Example 66 on page 142

Example 66. Pass Through Binding Example

```
<definitions xmlns="http://schemas.xmlsoap.org/wsdl/"</pre>
 xmlns:tns="http://www.iona.com/bus/tests"
 xmlns:xsd="http://www.w3.org/2001/XMLSchema"
 xmlns:http="http://schemas.iona.com/transports/http"
 xmlns:passthru="http://schemas.iona.com/bindings/passthru"
 targetNamespace="http://www.iona.com/bus/tests"
 name="PassthruService">
 <message name="returnString" />
 <message name="returnStringResponse">
   <part name="return" type="xsd:string"/>
 </message>
 <portType name="PassthruPortType">
   <operation name="returnString">
     <input name="returnString" message="tns:returnString"/>
     <output name="returnStringResponse" message="tns:returnStringResponse"/>
   </operation>
 </portType>
 <binding name="PassthruPortBinding" type="tns:PassthruPortType">
   <passthru:binding combineParts="true" />
 </binding>
</definitions>
```

Part II. Transports

Understanding How Endpoints are Defined in WSDL	147
Using HTTP	149
Adding an HTTP Endpoint to a Contract	150
Configuring an HTTP Endpoint	156
Introduction	157
Specifying Send and Receive Timeout Limits	158
Specifying a Username and a Password	160
Configuring Keep-Alive Behavior	162
Specifying Cache Control Directives	164
Managing Cookies in Artix Clients	167
Using the Java Messaging System	169
Defining a JMS Endpoint	170
Introduction	171
Basic Endpoint Configuration	172
Client Endpoint Configuration	176
Server Endpoint Configuration	177
Using the Command Line Tool	179
Migrating to the 4.x JMS WSDL Extensions	181
Using ActiveMQ as Your JMS Provider	182
Using IIOP	183
Using FTP	187
Adding an FTP Endpoint	188
Coordinating Requests and Responses	190
Introduction	191
Implementing the Client's Coordination Logic	192
Implementing the Server's Coordination Logic	196
Using Properties to Control Coordination Behavior	201
Using WebSphere MQ	205
Adding a WebSphere MQ Endpoint	206
Websphere MQ Connection Settings	
Specifying the WebSphere Library to Load	213
Using Queues on Remote Hosts	
Setting a Value of the Message Descriptor's Format Field	217
Using TIBCO Rendezvous	219
Using Tuxedo	225

Understanding How Endpoints are Defined in WSDL

Endpoints represent an instantiated service. They are defined by combining a binding and the networking details used to expose the endpoint.

Overview

An endpoint can be thought of as a physical manifestation of a service. It combines a binding, which specifies the physical representation of the logical data used by a service, and a set of networking details that define the physical connection details used to make the service contactable by other endpoints.

Endpoints and services

In the same way a binding can only map a single interface, an endpoint can only map to a single service. However, a service can be manifested by any number of endpoints. For example, you could define a ticket selling service that was manifested by four different endpoints. However, you could not have a single endpoint that manifested both a ticket selling service and a widget selling service.

The WSDL elements

Endpoints are defined in a contract using a combination of the WSDL service element and the WSDL port element. The service element is a collection of related port elements. The port elements define the actual endpoints.

The WSDL service element has a single attribute, name, that specifies a unique name. The service element is used as the parent element of a collection of related port elements. WSDL makes no specification about how the port elements are related. You can associate the port elements in any manner you see fit.

The WSDL port element has a single attribute, binding, that specifies the binding used by the endpoint. The port element is the parent element of the elements that specify the actual transport details used by the endpoint. The elements used to specify the transport details are discussed in the following sections.

Adding endpoints to a contract

Artix provides a number of tools for adding endpoints to your contracts. These include:

- Artix Designer has wizards that lead you through the process of adding endpoints to your contract.
- A number of the endpoint types can be generated using command line tools.

The tools will add the proper elements to your contract for you. However, it is recommended that you have some knowledge of how the different transports used in defining an endpoint work.

You can also add an endpoint to a contract using any text editor. When you hand edit a contract, you are responsible for ensuring that the contract is valid.

Supported transports

Artix ESB endpoint definitions are built using extensions defined for each of the transports Artix ESB C++ Runtime supports. Artix ESB C++ Runtime supports the following transports:

- HTTP
- BEA Tuxedo
- IBM WebSphere MQ
- TIBCO Rendezvous™
- IIOP
- CORBA
- Java Messaging Service
- File Transfer Protocol

Using HTTP

HTTP is the standard TCP/IP-based protocol used for client-server communications on the World Wide Web. The main function of HTTP is to establish a connection between a web browser (client) and a web server for the purposes of exchanging files and possibly other information on the Web.

Adding an HTTP Endpoint to a Contract	. 150
Configuring an HTTP Endpoint	
Introduction	
Specifying Send and Receive Timeout Limits	. 158
Specifying a Username and a Password	. 160
Configuring Keep-Alive Behavior	. 162
Specifying Cache Control Directives	
Managing Cookies in Artix Clients	. 167
Specifying a Username and a Password Configuring Keep-Alive Behavior Specifying Cache Control Directives	. 160 . 162 . 164

Adding an HTTP Endpoint to a Contract

Overview

Artix provides three ways of specifying an HTTP endpoint's address depending on the payload format you are using. SOAP 1.1 has a standardized soap:address element. SOAP 1.2 uses the wsoap12:address element. All other payload formats use Artix's http:address element.

As well as the standard soap:address element or http:address element, Artix provides a number of HTTP extensions. The Artix extensions allow you to specify a number of the HTTP port's configuration values in the contract.

SOAP 1.1

When you are sending SOAP 1.1 messages over HTTP you must use the soap:address element to specify the endpoint's address. It has one attribute, location, that specifies the endpoint's address as a URL.

Example 67 on page 150 shows a port element used to send SOAP 1.1 messages over HTTP.

Example 67. SOAP 1.1 Port Element

SOAP 1.2

When you are sending SOAP 1.2 messages over HTTP you must use the wsoap12:address element to specify the endpoint's address. It has one attribute, location, that specifies the endpoint's address as a URL.

Example 67 on page 150 shows a port element used to send SOAP 1.2 messages over HTTP.

Example 68. SOAP 1.2 Port Element

```
<service name="artieSOAP12Service">
  <port binding="artieSOAPBinding" name="artieSOAPPort">
        <wsoap12:address location="http://artie.com/index.xml">
```

</port>
</service>

Other payloads

When your messages are mapped to any payload format other than SOAP, such as fixed, you must use Artix's http:address element to specify the endpoint's address. Like the soap:address element, it has one attribute, location, that specifies the endpoint's address as a URL.

Using the command line tool

To use wsdltoservice to add an HTTP endpoint use the following options.

wsdltoservice {-transport soap/http} [-e service] [-t port] [-b binding] [-a address] [-hssdt serverSendTimeout] [-hscvt serverReceiveTimeout] [-hstrc trustedRootCertificates] [-hsuss useSecureSockets] [-hsct contentType] [-hscc serverCacheControl] [-hsscse supressClientSendErrors] [-hsscre supressClientReceiveErrors] [-hshka honorKeepAlive] [-hsmps serverMultiplexPoolSize] [-hsrurl redirectURL] [-hscl contentLocation] [-hsce contentEncoding] [-hsst serverType] [-hssc serverCertificate] [-hsscc serverCertificateChain] [-hsspk serverPrivateKey] [-hsspkp serverPrivateKeyPassword] [-hcst clientSendTimeout] [-hccvt clientReceiveTimeout] [-hctrc trustedRootCertificates] [-hcuss useSecureSockets] [-hcct contentType] [-hccc clientCacheControl] [-hcar autoRedirect] [-hcun userName] [-hcp password] [-hcat clientAuthorizationType][-hca clientAuthorization][-hca accept] [-hcal acceptLanguage] [-hcae acceptEncoding] [-hch host] [-hccn clientConnection] [-hcck cookie] [-hcbt browserType] [-hcr referer] [-hcps proxyServer] [-hcpun proxyUserName] [-hcpp proxyPassword] [-hcpat proxyAuthorizationType] [-hcpa proxyAuthorization] [-hccce clientCertificate] [-hcccc clientCertificateChain] [-hcpk clientPrivateKey] [-hcpkp clientPrivateKeyPassword] [-0 file] [-d dir] [-L file] [[-quiet] | [-verbose]] [-h] [-v] wsdlurl

The -transport soap/http flag specifies that the tool is to generate an HTTP service. The other options are as follows.

Table 22. Options for Adding an HTTP Endpoint

Option	Description
-transport soap/http	If the payload being sent over the wire is SOAP, use -transport soap. For
	all other payloads use -transport http.
-e service	Specifies the name of the generated service element.
-t port	Specifies the value of the name attribute of the generated port element.
-b binding	Specifies the name of the binding for which the service is generated.
-a address	Specifies the value used in the address element of the port.
-hssdt serverSendTimeout	Specifies the number of milliseconds that the server can continue to try to send a response to the client before the connection is timed-out.
-hscvt serverReceiveTimeout	Specifies the number of milliseconds that the server can continue to try to receive a request from the client before the connection is timed-out.
-hstrc trustedRootCertificates	Specifies the full path to the X509 certificate for the certificate authority.
-hsuss useSecureSockets	Specifies if the server uses secure sockets. Valid values are true or false.
-hsct contentType	Specifies the media type of the information being sent in a server response.
-hscc serverCacheControl	Specifies directives about the behavior that must be adhered to by caches involved in the chain comprising a request from a client to a server.
-hsscse supressClientSendErrors	Specifies whether exceptions are thrown when an error is encountered on receiving a client request. Valid values are true or false.
-hsscre supressClientReceiveErrors	Specifies whether exceptions are thrown when an error is encountered on
	sending a response to a client. Valid values are true or false.
-hshka honorKeepAlive	Specifies if the server honors client keep-alive requests. Valid values are true
	Or false.
-hsrurl redirectURL	Specifies the URL to which the client request should be redirected if the URL specified in the client request is no longer appropriate for the requested resource.
-hscl contentLocation	Specifies the URL where the resource being sent in a server response is located.
-hsce contentEncoding	Specifies what additional content codings have been applied to the information being sent by the server, and what decoding mechanisms the client therefore needs to retrieve the information.

Option	Description
-hsst serverType	Specifies what type of server is sending the response to the client.
-hssc serverCertificate	Specifies the full path to the X509 certificate issued by the certificate authority for the server.
-hsscc serverCertificateChain	Specifies the full path to the file that contains all the certificates in the chain.
-hsspk serverPrivateKey	Specifies the full path to the private key that corresponds to the X509 certificate specified by <code>serverCertificate</code> .
-hsspkp	Specifies a password that is used to decrypt the private key.
serverPrivateKeyPassword	
-hcst clientSendTimeout	Specifies the number of milliseconds that the client can continue to try to send a request to the server before the connection is timed-out.
-hccvt clientReceiveTimeout	Specifies the number of milliseconds that the client can continue to try to receive a response from the server before the connection is timed-out.
-hctrc trustedRootCertificates	Specifies the full path to the X509 certificate for the certificate authority.
-hcuss ueSecureSockets	Specifies if the client uses secure sockets. Valid values are true or false.
-hcct contentType	Specifies the media type of the data being sent in the body of the client request.
-hccc clientCacheControl	Specifies directives about the behavior that must be adhered to by caches involved in the chain comprising a request from a client to a server.
-hcar autoRedirect	Specifies if the server should automatically redirect client requests.
-hcun userName	Specifies the username the client uses to register with servers.
-hcp password	Specifies the password the client uses to register with servers.
-hcat clientAuthorizationType	Specifies the authorization mechanisms the client uses when contacting servers.
-hca clientAuthorization	Specifies the authorization credentials used to perform the authorization.
-hca accept	Specifies what media types the client is prepared to handle.
-hcal acceptLanguage	Specifies what language the client prefers for the purposes of receiving a response
-hcae acceptEncoding	Specifies what content codings the client is prepared to handle.
-hch host	Specifies the internet host and port number of the resource on which the client request is being invoked.

Option	Description
-hccn clientConnection	Specifies if the client will open a new connection for each request or if it will keep the original one open. Valid values are close and Keep-Alive.
-hcck cookie	Specifies a static cookie to be sent to the server.
-hcbt browserType	Specifies information about the browser from which the client request originates.
-hcr referer	Specifies the value for the client's referring entity.
-hcps proxyServer	Specifies the URL of the proxy server, if one exists along the message path.
-hcpun proxyUserName	Specifies the username that the client uses to be authorized by proxy servers.
-hcpp proxyPassword	Specifies the password that the client uses to be authorized by proxy servers.
-hcpat proxyAuthorizationType	Specifies the authorization mechanism the client uses with proxy servers.
-hcpa proxyAuthorization	Specifies the actual data that the proxy server should use to authenticate the client.
-hccce clientCertificate	Specifies the full path to the X509 certificate issued by the certificate authority for the client.
-hcccc clientCertificateChain	Specifies the full path to the file that contains all the certificates in the chain.
-hcpk clientPrivateKey	Specifies the full path to the private key that corresponds to the X509 certificate specified by clientCertificate.
-hcpkp clientPrivateKeyPassword	Specifies a password that is used to decrypt the private key.
-o file	Specifies the filename for the generated contract. The default is to append -service to the name of the imported contract.
-d dir	Specifies the output directory for the generated contract.
-L file	Specifies the location of your Artix license file. The default behavior is to check IT_PRODUCT_DIR\etc\license.txt.
-quiet	Specifies that the tool runs in quiet mode.
-verbose	Specifies that the tool runs in verbose mode.
-h	Displays the tool's usage statement.
-v	Displays the tool's version.

Artix WSDL Extension Reference [../wsdl_ref/index.htm].

Example

Example 69 on page 155 shows the namespace entries you need to add to the definitions element of your contract to use the HTTP extensions.

For more information about the specific attributes and their values see the

Example 69. Artix HTTP Extension Namespaces

```
<definitions
...
xmlns:http="http://schemas.iona.com/transports/http"
... >
```

Example 70 on page 155 shows a port element for an endpoint that sends fixed data over HTTP.

Example 70. Generic HTTP Port

```
<service name="artieFixedService">
  <port binding="artieFixedBinding" name="artieFixedPort">
        <htp:address location="http://artie.com/index.xml">
        </port>
  </service>
```

Configuring an HTTP Endpoint

ntroduction	157
Specifying Send and Receive Timeout Limits	158
Specifying a Username and a Password	
Configuring Keep-Alive Behavior	
Specifying Cache Control Directives	

Introduction

In addition to the http:address element or soap:address element used to specify the URL of an HTTP endpoint, Artix uses two other elements to define a number of other properties for HTTP endpoints: http-conf:client and http-conf:server.

The http-conf:client element specifies properties used to configure an HTTP client-side endpoint. The http-conf:server element specifies properties used to configure an HTTP server-side endpoint. The properties are specified as attributes to the elements. While the elements share many attributes there are differences.

To use the HTTP configuration elements, you need to include the following entry in your contract's definition element:

xmlns:http-conf="http://schemas.iona.com/transports/http/con figuration"

For a complete discussion of the specific attributes and their values see the Artix WSDL Extension Reference [../wsdl ref/index.htm].

Specifying Send and Receive Timeout Limits

Overview

The most common values that needs to be configured for an HTTP endpoint are the ones controlling how long the endpoint will spend sending a receiving messages before issuing a timeout exception. Both client endpoints and server endpoints have two attributes that control their timeout behaviors:

SendTimeout and RecieveTimeout.

Send timeout

The timeout limit for attempting to send a message is specified, for both the client-side and server-side, using the <code>SendTimeout</code> attribute. The timeout limit specifies the number of milliseconds an endpoint will spend attempting to transmit a message. It has a default setting of 30000 milliseconds.

This value may need to be adjusted if you are transmitting large messages as they take longer to send. Other factors that may effect the amount if time needed to transmit messages over HTTP are the speed of the network, distance between the endpoints, and the amount of traffic on the network. For example, if you were transmitting high-resolution photographs across the Atlantic, you may need to adjust the value of the <code>SendTimeout</code> attribute to 1200000 as shown in Example 71 on page 158.

Example 71. Setting the SendTimeout Attribute

```
<port ...>
    <soap:address ... />
    <http-conf:client SendTimeout="120000" />
</port>
```

Recieve timeout

The RecieveTimeout attribute specifies the amount of time an endpoint spends between when it initially receives the beginning of a message and the when it receives the last piece of data in the message. For example, if a client using the default settings sends a response to a service that takes 90 seconds to process the response, the client will not timeout. However, if it takes the client 45 seconds to read the response from the network, it will timeout.

The causes for long read times are similar to the reasons for long send times. Large messages, heavy network traffic, and large physical distances can all have an impact on the amount if time it takes an HTTP endpoint to receive a message. For example, if you are transmitting map data to a remote research facility, you may want to specify a value of 600000 for the ReceiveTimeout attribute of the remote endpoint as shown in Example 72 on page 159.

Example 72. Setting the ReceiveTimeout Attribute

```
<port ...>
  <soap:address ... />
  <http-conf:server ReceiveTimeout="600000" />
</port>
```

Specifying a Username and a Password

Overview

Username/password authentication is a common way of requiring clients to identify themselves. By requiring a client to provide a username and a password, a server can keep a record of who is accessing it and determine if they are authorized to access the functionality requested. For example, many Wiki applications and blogging applications require a username and password before allowing content to be edited.

In Artix, the username and password presented by an HTTP endpoint are specified using the following attributes of the http-conf:client element:

- UserName
- Password

Be aware that these values will be visible to anyone that has access to the endpoint's contract. Using this style of authentication does not provide a high level of security. For information on using stronger security measures with Artix see the Artix Security Guide [../security guide/index.htm].

Setting a username

You set a username using the http-conf:client element's UserName attribute. The value you specify is used to populate the username field in the HTTP header of all messages sent from the endpoint. Setting this attribute is optional. If no value is specified, Artix does not populate the username field of the HTTP header with a default value.

Setting a password

You set a password using the http-conf:client element's Password attribute. The value you specify is used to populate the password field in the HTTP header of all messages sent from the endpoint. It is an entirely optional attribute. If no value is specified, Artix does not populate the password field of the HTTP header with a default value.

Relationship between the attributes

The UserName attribute and the Password attribute are independent of each other. Although most applications that require a username also require a password, it is not mandatory that this pattern is followed. An application may just require a username for identification, or it may just use a password to provide a level of exclusivity.

Similarly, Artix does not require that the two attributes be used together. If an endpoint only needs to provide a password, you can provide a value for the Password attribute without providing a value for the UserName attribute. Example 73 on page 161 shows an HTTP endpoint definition that specifies just a username.

Example 73. Specifying Just a Usernamre

```
<port ...>
  <http:address ... />
  <http-conf:client UserName="Joe" />
</port>
```

The attributes and other security features

Specifying a username and password in an endpoint's contract does not effect the use of other Artix security features. You are not forced to use HTTPS when using a username or password. Similarly, you are not stopped from implementing your endpoint using WS-Security headers. For more details on using Artix's security features see the Artix Security Guide [../../security_guide/index.htm].

Configuring Keep-Alive Behavior

Overview

The default behavior of Artix endpoints is to open a connection and keep it open for as long as the client requires. However, it is not always desirable to keep a connection open over multiple requests. This can present a security problem. Artix endpoints can, therefore, be configured to close connections after each request/response cycle.

Making keep-alive requests

HTTP client endpoints are configured to make keep-alive requests using the http-conf:client element's Conneciton attribute. This attribute has two values: close and Keep-Alive.

Keep-Alive is the default. It specifies that the client endpoint wishes to keep its connections open for future requests. The client will request that the server keep the connection open. If the server does honor the request, the connection remains open until one of the endpoints dies. If the server does not honor the request, the client must open a new connection for each request.

close specifies that the client endpoint does not wish to keep its connecitons open for future requests. The client will always open a new connection for each request.

Example 74 on page 162 shows a port element that defines an HTTP client endpoint that does not want to reuse connections.

Example 74. Specifying that the HTTP Connection is Closed

```
<port ...>
   <soap:address location="http://localhost:8080" />
   <http-conf:client Conneciton="close" />
</port>
```

Honoring keep-alive requests

HTTP server endpoints are not required to honor keep-alive requests. The default behavior of Artix HTTP server endpoints is the accept keep-alive requests. You can change this behavior using the http-conf:server element's HonorKeepAlive attribute. It has two values: false and true.

true is the default. It specifies that the server endpoint will honor all keep-alive requests. If a client connects to the server endpoint using at least HTTP 1.1 and requests that the connection is kept alive, the server endpoint

is left open. The client can continue to make requests over the original connection.

false specifies that the server endpoint rejects all keep-alive requests. Once the endpoint responds to a request it closes the connection used for the request/response sequence.

Example 75 on page 163 shows a port element that defines an HTTP server endpoint that rejects keep-alive requests.

Example 75. Rejecting Keep-Alive Requests

```
<port ...>
  <soap:address location="http://localhost:8080" />
  <http-conf:server HonorKeepAlive="false" />
</port>
```

Specifying Cache Control Directives

Overview

A common method to reduce latency and control network traffic on the Web is to use caches that sit between server endpoints and client endpoints. These caches monitor the interactions between the endpoints. They store responses to requests as they are passed from a server endpoint to a client endpoint.

When a cache sees a request that it recognizes, it will check its stored responses. If a match is found, the cache will respond to the request on behalf of the server endpoint. The server endpoint will never know the request was made and the client endpoint will never know that it is getting a cached response.

While this optimizes the transaction time, it does pose a few possible problems:

- If a server endpoint collects usage statistics, it will not have accurate data.
- If the server endpoint frequently updates its data, the client endpoint may get a response that is out of date.

HTTP provides a mechanism for specifying cache behavior using the HTTP message header. You can configure these settings for your endpoints using the CacheControl attribute of both the http-conf:server element and the http-conf:client element.

Server endpoint settings

Server endpoints can tell caches how to handle the responses they issue. For example, a server endpoint can direct caches that its responses are stale after 10 seconds. These directives are only valid for the responses issued from a particular server endpoint.

Table 23 on page 164 shows the valid values for CacheControl in http-conf:server.

Table 23. Settings for CacheControl on an HTTP Server Endpoint

Directive	Behavior
no-cache	Caches cannot use a particular response to satisfy subsequent client requests without first revalidating that response with the server. If specific response header fields are specified with this value, the restriction applies only to those header fields within the response. If no response header fields are specified, the restriction applies to the entire response.

Directive	Behavior
public	Any cache can store the response.
private	Public (<i>shared</i>) caches cannot store the response because the response is intended for a single user. If specific response header fields are specified with this value, the restriction applies only to those header fields within the response. If no response header fields are specified, the restriction applies to the entire response.
no-store	Caches must not store any part of response or any part of the request that invoked it.
no-transform	Caches must not modify the media type or location of the content in a response between a server and a client.
must-revalidate	Caches must revaildate expired entries that relate to a response before that entry can be used in a subsequent response.
proxy-revelidate	Means the same as must-revalidate, except that it can only be enforced on shared caches and is ignored by private unshared caches. If using this directive, the public cache directive must also be used.
max-age	Specifies the maximum age, in seconds, of a cached response before it is stale.
s-maxage	Means the same as max-age, except that it can only be enforced on shared caches and is ignored by private unshared caches. The age specified by s-maxage overrides the age specified by max-age. If using this directive, the proxy-revalidate directive must also be used.
cache-extension	Specifies additional extensions to the other cache directives. Extensions might be informational or behavioral. An extended directive is specified in the context of a standard directive, so that applications not understanding the extended directive can at least adhere to the behavior mandated by the standard directive.

Client endpoint settings

Client endpoints can tell caches what kinds of responses they will accept and how to handle the response they receive. For example, a client endpoint can direct caches not to store any responses that it receives. A client endpoint can also direct caches that it will only accept a cached response that is less than 5 seconds old.

Table 24 on page 166 shows the valid settings for CacheControl in http-conf:client.

Table 24. Settings for CacheControl on HTTP Client Endpoint

Directive	Behavior
no-cache	Caches cannot use a particular response to satisfy subsequent client requests without first revalidating that response with the server. If specific response header fields are specified with this value, the restriction applies only to those header fields within the response. If no response header fields are specified, the restriction applies to the entire response.
no-store	Caches must not store any part of a response or any part of the request that invoked it.
max-age	The client can accept a response whose age is no greater than the specified time in seconds.
max-stale	The client can accept a response that has exceeded its expiration time. If a value is assigned to max-stale, it represents the number of seconds beyond the expiration time of a response
	up to which the client can still accept that response. If no value is assigned, it means the client can accept a stale response of any age.
min-fresh	The client wants a response that will be still be fresh for at least the specified number of seconds indicated.
no-transform	Caches must not modify media type or location of the content in a response between a server and a client.
only-if-cached	Caches should return only responses that are currently stored in the cache, and not responses that need to be reloaded or revalidated.
cache-extension	Specifies additional extensions to the other cache directives. Extensions might be informational or behavioral. An extended directive is specified in the context of a standard directive, so that applications not understanding the extended directive can at least adhere to the behavior mandated by the standard directive.

Managing Cookies in Artix Clients

Overview

Artix can send and receive cookies. It can also be configured to pass along a static cookie with all outgoing requests. While Artix can send and receive cookies, it is up to the application to set dynamic cookies and ensure they are properly managed.


Sending static cookies

If you want your client to always attach a static cookie to its requests, you can specify this in the client's contract. The cookie is specified using the <code>cookie</code> attribute of the <code>http-conf:client</code> element.

How Artix processes cookies

Artix handles cookies using its context mechanism. For an HTTP application there are two contexts. One context is for incoming messages and the other is for outgoing messages. Figure 1 on page 167 shows how an Artix client manages cookies.

Figure 1. Artix Cookie Processing



When a client makes a request it can save a cookie into its outbound context and it will be sent with all future requests. If a client receives a cookie from a service, that cookie is stored in the client's inbound context.

The received cookie does not have to be inspected. In order to inspect the contents of a received cookie, you will need to add the proper logic to your client using the Artix context APIs.

The received cookie is not automatically transferred to the out bound context. If you client needs to pass a received cookie along with future requests, you will need to add logic to your client so that it will transfer the received cookie from the client's inbound context to the outbound context.

More information

For information about setting cookies and using Artix contexts see the relevant programming guide:

- Developing Artix Applications in C++ [../../prog_guide/index.htm]
- Developing Artix Applications in JAX-RPC [../../jaxrpc pguide/index.htm]

Using the Java Messaging System

JMS is a standards based messaging system that is widely used in enterprise Java applications.

Defining a JMS Endpoint	. 170
Introduction	. 17
Basic Endpoint Configuration	. 172
Client Endpoint Configuration	. 176
Server Endpoint Configuration	. 177
Using the Command Line Tool	. 179
Migrating to the 4.x JMS WSDL Extensions	. 183
Using ActiveMQ as Your JMS Provider	. 182

Defining a JMS Endpoint

ntroduction	171
Basic Endpoint Configuration	172
Client Endpoint Configuration	
Server Endpoint Configuration	
Jsing the Command Line Tool	

Introduction

Overview

Artix provides a transport plug-in that enables endpoints to use Java Messaging System (JMS) queues and topics. One large advantage of this is that Artix allows C++ applications to interact directly with Java applications over JMS.

Artix's JMS transport plug-in uses the Java Naming and Directory Interface (JNDI) to locate and obtain references to the JMS provider. Once Artix has established a connection to a JMS provider, Artix supports the passing of messages packaged as either a JMS ObjectMessage or a JMS TextMessage.

Message formatting

The JMS transport takes messages and packages them into either a JMS ObjectMessage or a TextMessage. When a message is packaged as an ObjectMessage the message's data, including any format-specific information, is serialized into a byte[] and placed into the JMS message body. When a message is packaged as a TextMessage, the message's data, including any format-specific information, is converted into a string and placed into the JMS message body.

When a message sent by Artix is received by a JMS application, the JMS application is responsible for understanding how to interpret the message and the formatting information. For example, if the Artix contract specifies that the binding used for a JMS endpoint is SOAP, and the messages are packaged as a TextMessage, the JMS application will receive a string containing all of the SOAP envelope information. For a message encoded using the fixed binding, the message will contain no formatting information, simply a string of characters, numbers, and spaces.

Namespace

The WSDL extensions used to define a JMS endpoint are specified in the namespace http://celtix.objectweb.org/transports/jms. To use the JMS extensions you will need to add the line shown Example 76 on page 171 to the definitions element of your contract.

Example 76. JMS Extension's Namespace

xmlns:jms="http://celtix.objectweb.org/transports/jms"

Basic Endpoint Configuration

Overview

JMS endpoints need to know certain basic information about how to establish a connection to the proper destination. This information is provided using the <code>jms:address</code> element and its child the <code>jms:JMSNamingProperty</code> element. The <code>jms:address</code> element's attributes specify the information needed to identify the JMS broker and the destination. The <code>jms:JMSNamingProperty</code> element specifies the Java properties used to connect to the JNDI service.

address element

The basic configuration for a JMS endpoint is done by using a jms:address element in your service's port element. The jms:address element uses the attributes described in Table 25 on page 172 to configure the connection to the JMS broker.

Table 25. JMS Port Attributes

Attribute	Description
destinationStyle	Specifies if the JMS destination is a JMS queue or a JMS topic.
jndiConnectionFactoryName	Specifies the JNDI name of the JMS connection factory to use when connecting to the JMS destination.
jmsDestinationName	Specifies the JMS name of the destination to which requests are sent.
jmsReplyDestinationName	Specifies the JMS name of the destination where replies are sent. This attribute allows you to use a user defined destination for replies. For more details see Using a named reply destination on page 173.
jndiDestinationName	Specifies the JNDI name of the destination to which requests are sent.
jndiReplyDestinationName	Specifies the JNDI name of the destination where replies are sent. This attribute allows you to use a user defined destination for replies. For more details see Using a named reply destination on page 173.
connectionUserName	Specifies the username to use when connecting to a JMS broker.
connectionPassword	Specifies the password to use when connecting to a JMS broker.

JMSNamingProperties element

To increase interoperability with JMS and JNDI providers, the <code>jms:address</code> element has a child element, <code>jms:JMSNamingProperty</code>, that allows you to specify the values used to populate the properties used when connecting to

the JNDI provider. The jms: JMSNamingProperty element has two attributes: name and value. The name attribute specifies the name of the property to set. The value attribute specifies the value for the specified property.

The following is a list of common JNDI properties that can be set:

- java.naming.factory.initial
- · java.naming.provider.url
- java.naming.factory.object
- java.naming.factory.state
- · java.naming.factory.url.pkgs
- java.naming.dns.url
- · java.naming.authoritative
- java.naming.batchsize
- · java.naming.referral
- java.naming.security.protocol
- · java.naming.security.authentication
- · java.naming.security.principal
- · java.naming.security.credentials
- · java.naming.language
- java.naming.applet

For more details on what information to use in these attributes, check your JNDI provider's documentation and consult the Java API reference material.

Using a named reply destination

By default Artix ESB C++ Runtime endpoints using JMS create a temporary queue for the response queue. You can change this behavior by setting either the jmsReplyDestinationName attribute or the

jndiReplyDestinationName attribute in the endpoint's contract. A client
endpoint will listen for replies on the specified destination and it will specify

the value of the attribute in the ReplyTo field of all outgoing requests. An service endpoint will use the value of the jndiReplyDestinationName attribute as the location for placing replies if there is no destination specified in the request's ReplyTo field.

Examples

Example 77 on page 174 shows an example of a JMS port specification that uses dynamic queues.

Example 77. Artix JMS Port with DynamicQueues

Example 78 on page 174 shows an example of a JMS port specification that does not use dynamic queues.

Example 78. Artix JMS Port with Non-dynamic Queues

Alternate InitialContextFactory settings for using SonicMQ

If you are using Sonic MQ, you will need to use an alternative method of specifying the InitialContextFactory value. You specify a colon-separated list of package prefixes to force the JNDI service to instantiate a context factory

with the class name

com.iona.jbus.jms.naming.sonic.sonicURLContextFactory to perform lookups. This is shown in Example 79 on page 175.

Example 79. JMS Port with Alternate InitialContextFactory Specification

Using the contract in Example 79 on page 175, Artix would use the URL sonic:jms/queue/helloWorldQueue to get a reference to the desired queue. Artix would be handed a reference to a queue named helloWorldQueue if the JMS broker has such a queue.

Client Endpoint Configuration

The client endpoint's behaviors are configured using the jms:client element. The jms:client element is a child of the WSDL port element and has one attribute:

Table 26. Attributes for Configuring a JMS Client Endpoint

Attribute	Description
messageType	Specifies how the message data will be packaged as a JMS message. text specifies that the
	data will be packaged as a TextMessage. binary specifies that the data will be packaged as
	an ObjectMessage.

This element is optional. The default behavior of a JMS client endpoint is to send text messages.

Server Endpoint Configuration

Overview

JMS server endpoints have a number of behaviors that are configurable in the contract. These include if the server uses durable subscriptions, if the server uses local JMS transactions, and the message selectors used by the endpoint.

server element

Server endpoint behaviors are configured using the jms:server element. The jms:server element is a child of the WSDL port element and has the following attributes:

Table 27. Attributes for COnfiguring a JMS Server Endpoint

Attribute	Description
useMessageIDAsCorrealationID	Specifies whether JMS will use the message ID to correlate messages. The default is false.
durableSubscriberName	Specifies the name used to register a durable subscription. See Setting up durable subscriptions on page 177.
messageSelector	Specifies the string value of a message selector to use. See Using message selectors on page 177.
transactional	Specifies whether the local JMS broker will create transactions around message processing. The default is false. See Using reliable
	messaging on page 177.

The jms:server element and all of its attributes are optional.

Setting up durable subscriptions

If you want to configure your server to use durable subscriptions, you can set the optional durableSubscriberName attribute. The value of the attribute is the name used to register the durable subscription.

Using message selectors

If you want to configure your server to use a JMS message selector, you can set the optional messageSelector attribute. The value of the attribute is the string value of the selector. For more information on the syntax used to specify message selectors, see the JMS 1.1 specification.

Using reliable messaging

If you want your server to use the local JMS broker's transaction capabilities, you can set the optional transactional attribute to true.

When the transactional attribute is set, an Artix server's JMS transport layer will begin a transaction when it pulls a request from the queue. The server will then process the request and send the response back to the JMS transport layer. Once the JMS transport layer has successfully placed the response on the response queue, the transport layer will commit the transaction. So, if the Artix server crashes while processing a request or the transport layer is unable to send the response, the JMS broker will hold the request in the queue until it is successfully processed.

In cases where Artix is acting as a router between JMS and another transport, setting the transactional attribute will ensure that the message is delivered to the second server. The JMS portion of the router will not commit the message until the message has been successfully consumed by the outbound transport layer. If an exception is thrown during the consumption of the message, the JMS transport will rollback the message, pull it from the queue again, and attempt to resend it.

Using the Command Line Tool

To use **wsdltoservice** to add a JMS endpoint use the tool with the following options:

wsdltoservice {-transport jms} [-e service] [-t port] [-b binding] [-0
file] [-d dir] [-jnp propName:propVal...] [-jds [queuetopic]] [-jnf
connectionFactoryName] [-jdn destinationName] [-jrdn
replyDesinationName] [-jcun username] [-jcp password] [-jmt
[textbinar]] [-jms messageSelector] [-jumi [truefalse]] [-jtr
[truefalse]] [-jdsn durableSubscriber] [-L file] [[-quiet] | [-verbose]]
[-h] [-v] wsdlurl

The -transport jms flag specifies that the tool is to generate a JMS endpoint. The other options are as follows:

Table 28. Command Line Options for Creating a JMS Endpoint

Option	Description
-e service	Specifies the name of the generated service element.
-t port	Specifies the value of the name attribute of the generated port element.
-b binding	Specifies the name of the binding for which the service is generated.
-o file	Specifies the filename for the generated contract. The default is to append -service to the name of the imported contract.
-d dir	Specifies the output directory for the generated contract.
-jnp propName:propVal	Specifies any optional Java properties to use in connecting to the JNDI provider. This information is used to populate a <code>JMSNamingProperty</code> element. You can use this flag multiple times.
-jds (queue/topic)	Specifies if the JMS destination is a JMS queue or a JMS topic.
-jfn connectionFactoryName	Specifies the JNDI name bound to the JMS connection factory to use when connecting to the JMS destination.
-jdn destinationName	Specifies the JNDI name of the JMS destination to which Artix connects.
-jrdn replyDestinationName	Specifies the JNDI name of the JMS destination used for replies.

Option	Description
-jcun username	Specifies the username used to connect to the JMS broker.
-jcp password	Specifies the password used to connect to the JMS broker.
-jmt (text/binary)	Specifies how the message data will be packaged as a JMS message.
-jms messageSelector	Specifies a message selector to use when pulling messages from the JMS destination.
-jumi (true/false)	Specifies if the JMS message id should be used as the correlation id.
-jtr (true/false)	Specifies if the services uses local JMS transactions when processing requests.
-jdsn durableSubscriber	Specifies the name of the durable subscription to use.
-L file	Specifies the location of your Artix license file. The default behavior is to check <pre>IT_PRODUCT_DIR\etc\license.txt.</pre>
-quiet	Specifies that the tool runs in quiet mode.
-verbose	Specifies that the tool runs in verbose mode.
-h	Displays the tool's usage statement.
-v	Displays the tool's version.

For more information about the specific attributes and their values see the Artix WSDL Extension Reference [../../wsdl_ref/index.htm].

Migrating to the 4.x JMS WSDL Extensions

Overview

The WSDL extensions used to configure a JMS endpoint were modified in the 4.0 release of Artix. This update makes Artix JMS endpoint definitions compatible with Celtix JMS endpoints. To make the transition as smooth as possible, Artix includes an XSLT script that can be used to automatically migrate an old JMS endpoint definition to a new JMS endpoint definition.

XSLT script

The XSLT script used to migrate old JMS endpoint definitions to 4.x JMS endpoints is called oldjmswsdl_to_newjmswsdl.xsl and it is located in <code>IntallDir/Artix/Version/etc/xslt/utilities/jms</code>. It will take any Artix contract containing a pre-4.x Artix JMS endpoint definition as input and output an equivalent Artix contract containing a 4.x Artix JMS endpoint.

Using the script with Artix

You can use Artix's XSLT processor to convert your JMS endpoints. To do so you run the Artix **xslttransform** command line tool using the options shown in Example 80 on page 181.

Example 80. Running the Transformer with the JMS Migration Script

xslttransform -XSL oldjmswsdl_to_newjmswsdl.xsl -IN oldWsdl.wsdl -OUT
newWsdl.wsdl

The XSLT processor will read the contract in oldWsdl.wsdl, transform the old JMS endpoint to a new JMS endpoint, and save the resulting contract in newWsdl.wsdl.

Using ActiveMQ as Your JMS Provider

Overview

Artix installs ActiveMQ, an open source JMS implementation, for you to use as a possible messaging system. All of the Artix JMS demos are configured to use ActiveMQ, so to run the demos you must start the ActiveMQ broker.

Setting the CLASSPATH

When you set your Artix environment using the **artix_env** script, the ActiveMQ jars are automatically added to your CLASSPATH.

If you don not want to set the Artix environment before starting ActiveMQ you need to add

InstallDir/lib/activemq/activemq/3.2.1/activemq-rt.jar to your
CLASSPATH.

Staring the broker

To start the ActiveMQ JMS broker run the following command:

InstallDir/Artix/Version/bin/start_jms_broker

Stopping the broker

To shutdown the ActiveMQ JMS broker run the following command:

InstallDir/Artix/Version/bin/jmsbrokerinteract -sd

Security

By default, ActiveMQ's security features are turned off. To turn on ActiveMQ's security features see the ActiveMQ documentation.

More information

For more information on using ActiveMQ see the project's homepage at http://activemq.org [http://activemq.org/].

Using IIOP

Using IIOP to send non-CORBA formats allows you to take advantages of CORBA services and QoS without using CORBA applications.

Overview

Artix allows you to use IIOP as a generic transport for sending data using any of the payload formats. When using IIOP as a generic transport, you define your endpoint's address using aniiop:address element. The benefit of using the generic IIOP transport is that it allows you to use CORBA services without requiring your applications to be CORBA applications. For example, you could use an IIOP tunnel to send fixed format messages to an endpoint whose address is published in a CORBA naming service.

Namespace

The namespace under which the IIOP extensions are defined is http://schemas.iona.com/bindings/iiop_tunnel. If you are going to add an IIOP port by hand you will need to add this to your contract's definition element.

IIOP address specification

The IOR, or address, of the IIOP port is specified using the iiop:address element. You have four options for specifying IORs in Artix contracts:

 Specify the object's IOR directly in the contract, using the stringified IOR format:

IOR:22342....

• Specify a file location for the IOR, using the following syntax:

file:///file name



Note

The file specification requires three backslashes (///).

 Specify that the IOR is published to a CORBA name service, by entering the object's name using the corbaname format:

corbaname:rir/NameService#object_name

For more information on using the name service with Artix see Artix for CORBA [../../corba ws/index.htm].

• Specify the IOR using corbaloc, by specifying the port at which the service exposes itself, using the corbaloc syntax.

```
corbaloc:iiop:host:port/service name
```

When using corbaloc, you must be sure to configure your service to start up on the specified host and port.

Specifying type of payload encoding

The IIOP transport can perform codeset negotiation on the encoded messages passed through it if your CORBA system supports it. By default, this feature is disabled so that the agents sending the message maintain complete control over codeset conversion. If you wish to enable automatic codeset negotiation use the following element:

<iiop:payload type="string"/>

Specifying POA policies

Using the optional <code>iiop:policy</code> element, you can describe the POA polices Artix will use when creating the IIOP endpoint. These policies include:

- The POA name
- Persistence
- · The system ID assigned to the POA

Setting these policies lets you exploit some of the enterprise features of Progress' Orbix 6.x, such as load balancing and fault tolerance, when deploying an Artix endpoints using the IIOP transport. For information on using these advanced CORBA features, see the Orbix documentation.

POA name

Artix POAs are created with the default name of ws_orb. To specify a name for the POA that Artix creates for an IIOP endpoint, you use the following:

<iiop:policy poaname="poa name"/>

The POA name is used for setting certain policies, such as direct persistence and well-known port numbers in the CORBA configuration.

Persistence

By default Artix POAs have a persistence policy of false. To set the POA's persistence policy to true, use the following:

<iiop:policy persistent="true"/>

ID Assignment

By default Artix POAs are created with a SYSTEM_ID policy, meaning that their ID is assigned by Artix. To specify that the IIOP endpoint's POA should use a user-assigned ID, use the following:

<corba:policy serviceid="POAid"/>

This creates a POA with a USER ID policy and an object id of POAid.

Using the command line tool

To use **wsdltoservice** to add an IIOP endpoint use the tool with the following options.

wsdltoservice {-transport iiop} [-e service] [-t port] [-b binding] [-a
address] [-poa poaName] [-sid serviceId] [-pst persists] [-paytype
payload] [-0 file] [-d dir] [-L file] [[-quiet] | [-verbose]] [-h] [-v] wsdlurl

The -transport iiop flag specifies that the tool is to generate an IIOP endpoint. The other options are as follows.

-e service	Specifies the name of the generated service element.
-t port	Specifies the value of the name attribute of the generated port element.
-b binding	Specifies the name of the binding for which the endpoint is generated.
-a address	Specifies the value used in the generated iiop:address elements.
-poa <i>poaName</i>	Specifies the value of the POA name policy.
-sid serviceId	Specifies the value of the ID assignment policy.

-pst persists	Specifies the value of the persistence policy. Valid values are true and false.
-paytype payload	Specifies the type of data being sent in the message payloads. Valid values are string, octets, imsraw,
	imsraw_binary, cicsraw, and cicsraw_binary.
-o file	Specifies the filename for the generated contract. The default is to append -service to the name of the
	imported contract.
-d dir	Specifies the output directory for the generated contract.
-L file	Specifies the location of your Artix license file. The default behavior is to check IT_PRODUCT_DIR\etc\license.txt.
-quiet	Specifies that the tool runs in quiet mode.
-verbose	Specifies that the tool runs in verbose mode.
-h	Displays the tool's usage statement.
-v	Displays the tool's version.

For more information about the specific attributes and their values see the Artix WSDL Extension Reference [../../wsdl ref/index.htm].

For example, an IIOP endpoint definition for the personalInfoLookup binding would look similar to Example 81 on page 186:

Example 81. CORBA personalInfoLookup Port

Artix expects the IOR for the IIOP endpoint to be located in a file called objref.ior, and creates a persistent POA with an object id of personalInfo to configure the IIOP endpoint.

Example

Using FTP

Artix ESB allows endpoints to communicate using a remote FTP server as an intermediary persistent datastore. When using the FTP transport, client endpoints will put request messages into a folder on the FTP server and then begin scanning the folder for a response. Server endpoints will scan the request folder on the FTP server for requests. When a request is found, the service endpoint will get it and process the request. When the service endpoint finishes processing the request, it will post the response back to the FTP server. When the client sees the response, it will get the response from the FTP server.

Because of the file-based nature of the FTP transport and the fact that endpoints do not have a direct connection to each other, the FTP transport places the burden of implementing a request/response coordination scheme on the developer. The FTP transport also requires that you implement the logic determining how the request and response messages are cleaned-up.

Adding an FTP Endpoint	188
Coordinating Requests and Responses	
Introduction	
Implementing the Client's Coordination Logic	192
Implementing the Server's Coordination Logic	196
Using Properties to Control Coordination Behavior	201

Adding an FTP Endpoint

Overview

You define an FTP endpoint using WSDL extensions that are placed within a the port element of a contract. The WSDL extensions provided by Artix allow you to specify a number of properties for establishing the FTP connection. In addition, they allow you to specify some of the properties used to define the naming properties for the files used by the transport.

Namespace

To use the FTP transport, you need to describe the endpoint using the FTP WSDL extensions in the physical part of a WSDL contract. The extensions used to describe a FTP port are defined in the following namespace:xmlns:ftp="http://schemas.iona.com/transports/ftp"

This namespace will need to be included in your ontract's definitions element.

Defining the connection details

The connection details for the endpoint are defined in an ftp:port element.

The ftp:port element has two attributes: host and port.

- The host attribute is required. It specifies the name of the machine hosting the FTP server to which the endpoint connects.
- The port attribute is optional. It specifies the port number on which the FTP server is listening. The default value is 21.

Example 82 on page 188 shows an example of a port element defining an FTP endpoint.

Example 82. Defining an FTP Endpoint

```
<port name="FTPendpoint">
  <ftp:port host="Dauphin" port="8080" />
</port>
```

In addition to the two required attributes, the ftp:port element has the following optional attributes:

Attribute	Description
requestLocation	Specifies the location on the FTP server where requests are stored. The default is /.
replyLocation	Specifies the location on the FTP server where replies are stored. The default is /.
connectMode	Specifies the connection mode used to connect to the FTP daemon. Valid values are passive and active. The default is passive.
scanInterval	Specifies the interval, in seconds, at which the request and reply locations are scanned for updates. The default is 5.

Specifying optional namimg properties

You can specify optional naming policies using an ftp:properties element. The ftp:properties element is a container for a number ftp:property elements. The ftp:property elements specify the individual naming properties. Each ftp:property element has two attributes, name and value, that make up a name-value pair that are used to provide information to the naming implementation used by the endpoint.

The default naming implementation provided with Artix has two properties:

staticFilemanes	Determines if the endpoint uses a static, non-unique, naming scheme for its files. Valid values are true and false. The default is true.
requestFilenamePrefix	Specifies the prefix to use for file names when staticFilenames is set to false.

For information on defining optional properties see Using Properties to Control Coordination Behavior on page 201.

Coordinating Requests and Responses

Introduction	191
Implementing the Client's Coordination Logic	192
Implementing the Server's Coordination Logic	196
Using Properties to Control Coordination Behavior	201

Introduction

Overview

FTP requires that messages are written out to a file system for retrieval. This poses a few problems. The first is determining a naming scheme that is agreed upon by all endpoints that use a common location on an FTP server. Client endpoints and the server endpoints they are making requests on need a method to coordinate requests and responses. This includes knowing which messages are intended for which endpoint.

The other problem posed by using a file system as a transport is knowing when a message can be cleaned-up. If a message is cleaned-up too soon, there is no way to re-read the message if something goes wrong while it is being processed. If a message is not cleaned-up soon enough, it is possible that the message will be processed more than once.

Artix requires that you implement the logic used to determine the file naming and clean-up logic used by your FTP endpoints. This is done by implementing four Java interfaces: two for the client-side and two for the server-side.

Default implementation

Artix provides a default implementation for coordinating requests and responses. The default implementation enables clients and servers to interact as if they are using a standard RPC mechanism. Message names are generated at runtime following a pattern based on the server endpoint's service name. Request messages are cleaned-up by the server endpoint when the corresponding response is written to the file system. Responses are cleaned-up by the client endpoint when they are read from the file system.

Implementing the Client's Coordination Logic

Overview

The client-side of the coordination implementation is made up of two parts:

- The filename factory is responsible for generating the filenames used for storing request messages on the FTP server and determining the name of the associated replies.
- The reply lifecycle policy is responsible for cleaning-up reply files.

The filename factory

The client-side filename factory is created by implementing the interface com.iona.jbus.transports.ftp.policy.client.FilenameFactory. Example 83 on page 192 shows the interface.

Example 83. Client-Side Filename Factory Interface

The interface has four methods to implement:

```
initialize()
```

initialize() is called by the transport when it is loaded by the bus.
It receives the following:

- the QName of the service the client on which the client wants to make requests.
- the value of the name attribute for the port element defining the endpoint implementing the service.
- an array containing any properties you specified as ftp:property elements in your client's contract.

This method is used to set up any resources you need to implement naming scheme used by the client-side endpoints. For example, the default implementation uses initialize() to do the following:

- 1. Determine if the user wants to use static filenames based on an ftp:property element in the contract. For more information see Using Properties to Control Coordination Behavior on page 201.
- 2. If so, it generates a static filename prefix for the requests.
- 3. If not, it uses the user supplied filename prefix for the requests.

```
getNextRequestFilename()
```

getNextRequestFilename() is called by the transport each time a request is sent out. It returns a string that the transport will use as the filename for the completed request message. For example, the default implementation creates a filename by appending a string representing the server endpoint's system address and the system time, in hexcode, to the prefix generated in initialize().

```
getRequestIncompleteFilename()
```

getRequestIncompleteFilename() is called by the transport each time a request is sent out. It returns a string that the transport will use as the filename for the request message as it is being transmitted. For example, the default implementation creates a filename by appending a the request filename with incomplete.

```
getReplyFilename()
```

getReplyFilename() is called by the transport when it starts listening for a response to a two-way request. It recieves a string representing the name of the request's filename. It returns the name of the file that will contain the response to the specified request. For example, the default

implementation generates the reply filename by appending $_\texttt{reply}$ to the request filename.

The reply lifecycle policy

The reply lifecycle policy is created by implementing the com.iona.jbus.transports.ftp.policy.client.ReplyFileLifecycle interface. Example 84 on page 194 shows the interface.

Example 84. Reply Lifecycle Interface

```
package com.iona.jbus.transports.ftp.policy.client;

public interface ReplyFileLifecycle
{
  boolean shouldDeleteReplyFile(String fileName)
  throws Exception;

String renameReplyFile(String fileName) throws Exception;
}
```

The interface has two methods to implement:

```
shouldDeleteReplyFile()
```

shouldDeleteReplyFile() is called by the transport after it completes reading in a reply. It recieves the filename of the reply and returns a boolean stating if the file should be deleted. If shouldDeleteReplyFile() returns true, the transport deletes the reply file. If it returns false, the transport renames reply file based on the logic implemented in renameReplyFile().

```
renameReplyFile()
```

renameReplyFile() is called by the transport if shouldDeleteReplyFile() returns false. It receives the original name of the reply file. It returns a string the contains the filename the transport uses to rename the reply file.

Configuring the client's coordination logic

If you choose to implement your own coordination logic for an FTP client endpoint, you need to configure the endpoint to load the your implementation classes. This is done by adding two configuration values to the endpoint's Artix configuration scope:

- plugins:ftp:policy:client:filenameFactory specifies the name of the class implementing the client's filename factory.
- plugins:ftp:policy:client:replyFileLifecycle specifies the name of the class implementing the client's reply lifecycle policy.

Both classes need to be on the endpoint's classpath.

Example 85 on page 195 shows an example of an Artix ESB configuration scope that specifies an FTP client endpoint's coordination policies.

Example 85. Configuring an FTP Client Endpoint

```
ftp_client
{
   plugins:ftp:policy:client:filenameFactory="demo.ftp.policy.client.myFilenameFactory";
   plugins:ftp:policy:client:replyFileLifecycle="demo.ftp.policy.client.myReplyFileLifecycle";
};
```

For more information on configuring Artix ESB see Configuring and Deploying Artix Solutions, C++ Runtime [../../deploy/cpp/index.htm].

Implementing the Server's Coordination Logic

Overview

The server-side of the coordination implementation is made up of two parts:

- The filename factory is responsible for identifying which requests to dispatch and how to name reply messages.
- The request lifecycle policy is responsible for cleaning-up request files.

The filename factory

The server-side filename factory is created by implementing the interface com.iona.jbus.transports.ftp.policy.server.FilenameFactory. Example 86 on page 196 shows the interface.

Example 86. Server-Side Filename Factory Interface

```
package com.iona.jbus.transports.ftp.policy.server;
import javax.xml.namespace.QName;
import com.iona.jbus.Bus;
import com.iona.transports.ftp.Element;
import com.iona.webservices.wsdl.ext.ftp.FTPProperties;
public interface FilenameFactory
 void initialize (Bus bus, QName service, String port,
                 FTPProperties properties) throws Exception;
  String getRequestFilenamesRegEx() throws Exception;
  Element[] updateRequestFiles(Element[] inElements)
  throws Exception;
  String getReplyIncompleteFilename(String requestFilename)
  throws Exception;
  String getReplyFilename(String requestFilename)
  throws Exception;
  FilenameFactoryPropertyMetaData[] getPropertiesMetaData();
```

The interface has six methods to implement:

initialize()

initialize() is called by the transport when it is activiated by the bus. It recieves the following:

- the bus that has activated the transport.
- the QName of the service to which the endpoint is implementing.
- the value of the name attribute for the port element defining the endpoint's connection details.
- an array containing any properties you specified as ftp:property elements in your server endpoint's contract.

This method is used to set up any resources you need to implement naming scheme used by the server-side endpoints. For example, the default implementation uses initialize() to do the following:

- Determine if the user wants to use static filenames based on an ftp:property element in the contract. For more information see Using Properties to Control Coordination Behavior on page 201.
- 2. If so, it generates a static filename prefix for the requests.
- 3. If not, it uses the user supplied filename prefix for the requests.

```
getRequestFileReqEx()
```

getRequestFileRegEx() is called by the transport when it initializes the server-side FTP listener. It returns a regular expression that is used to match request filenames intended for a specific server instance. For example, the default implementation returns a regular expression of the form

```
{wsdl:tns} {wsdl:service(@name)} {wsdl:port(@name)} {reqUuid}.
```

```
updateRequestFiles()
```

updateRequestFiles() is called by the transport after it determines the list of possible requests and before it dispatches the requests to the service implementation for processing. It recieves an array of com.iona.transports.ftp.Element objects. This array is a list of all the request messages selected by the request filename regular expression. updateRequestFiles() returns an array of Element objects containing

only the messages that are to be dispatched to the service implementation.

```
getReplyIncompleteFilename()
```

getReplyInclompleteFilename() is called by the transport when it is ready to post a response. It recieves the filename of the request that generated the response. It returns a string that is used as the filename for the response as it is being written to the FTP server. For example, the default implementation returns _incomplete appended to request filename.

```
getReplyFilename()
```

getReplyFilename() is called by the transport after it finishes writting a response to the FTP server. It recieves the filename of the request that generated the response. It returns a string that is used as the filename for the completed response. For example, the default implementation returns reply appended to request filename.

```
getPropertiesMetaData()
```

<code>getPropertiesMetaData()</code> is a convience function that returns an array of all the possbile properties you can use to effect the behavior of the FTP naming scheme. The properties returned correspond to the values defined in the <code>ftp:properties</code> element. For more information see Using

Properties to Control Coordination Behavior on page 201.

The request lifecycle policy

The request lifecycle policy is created by implementing the com.iona.jbus.transports.ftp.policy.server.RequestFileLifecycle interface. Example 87 on page 198 shows the interface.

Example 87. Request Lifecycle Interface

```
package com.iona.jbus.transports.ftp.policy.server;
public interface RequestFileLifecycle
{
  boolean shouldDeleteRequestFile(String fileName)
  throws Exception;
  String renameRequestFile(String fileName) throws Exception;
}
```

The interface has two methods to implement:

```
shouldDeleteRequestFile()
```

shouldDeleteRequestFile() is called by the transport after it completes writing in a response. It recieves the filename of the request that generated the response and returns a boolean stating if the file should be deleted. If <code>shouldDeleteRequestFile()</code> returns <code>true</code>, the transport deletes the request file. If it returns <code>false</code>, the transport renames reply file based on the logic implemented in <code>renameRequestFile()</code>.

renameRequestFile()

renameRequestFile() is called by the transport if shouldDeleteRequestFile() returns false. It receives the original name of the request file. It returns a string the contains the filename the transport uses to rename the request file.

Configuring the server's coordination logic

If you choose to use your own coordination logic for an FTP server endpoint, you need to configure the endpoint to load the proper implementation classes. This is done by adding two configuration values to the endpoint's Artix configuration scope:

- plugins:ftp:policy:server:filenameFactory specifies the name of the class implementing the server's filename factory.
- plugins:ftp:policy:server:requestFileLifecycle specifies the name of the class implementing the server's request lifecycle policy.

Both classes need to be on the endpoint's classpath.

Example 88 on page 199 shows an example of an Artix configuration scope that specifies an FTP server endpoint's coordination policies.

Example 88. Configuring an FTP Server Endpoint

```
ftp_client
{
  plugins:ftp:policy:server:filenameFactory="demo.ftp.policy.server.myFilenameFactory";
  plugins:ftp:policy:server:requestFileLifecycle="demo.ftp.policy.client.myReqFileLifecycle";
};
```

For more information on configuring Artix see Configuring and Deploying Artix Solutions, C++ Runtime [../../deploy/cpp/index.htm].

Using Properties to Control Coordination Behavior

Overview

In order to ensure that your FTP client endpoints and FTP server endpoints are using the same coordination behavior, you may need to pass some information to the transports as they initialize. To make this information available to both sides of the application and still be settable at run time, the Artix FTP transport allows you to provide custom properties that are settable in an endpoint's contract. These properties are set using the ftp:properties element.

Properties in the contract

You can place any number of custom properties into port element defining an FTP endpoint. As described in Specifying optional naming properties on page 189, the ftp:properties element is a container for one or more ftp:property elements. The ftp:property element has two attributes: name and value. Both attributes can have any string as a value. Together they form a name/value pair that your coordination logic is responsible for processing.

For example, imagine an FTP endpoint defined by the port element in Example 89 on page 201.

Example 89. FTP Endpoint with Custom Properties

```
<port ...>
  <ftp:port ... />
  <ftp:properties>
    <ftp:property name="UseHumanNames" value="true" />
    <ftp:property name="LastName" value="Doe" />
  </ftp:properties>
</port>
```

The endpoint is configured using two custom FTP properties:

- UseHumanNames with a value of true.
- LastName with a value of Doe.

These properties are only meaningful if the coordination logic used by the endpoint supports them. If they are not supported, they are ignored.

Supporting the properties

The initialize() method of both the client-side filename factory and the server-side filename factory take a

com.iona.webservices.wsdl.ext.ftp.FTPProperties object. The FTPProperties object is populated by the contents of the endpoints ftp:properties element when the transport is initialized.

The FTPProperties object can be used to access all of the properties defined by ftp:property elements. To access the properties you do the following:

- 1. Use the getExtensors() method to get an Iterator object.
- 2. Using the Iterator objects next() method, get the elements in the list.
- 3. Cast the return value of the <code>next()</code> method to an <code>FTPProperty</code> object.

Each com.iona.webservices.wsdl.ext.ftp.FTPProperty object contains one name/value pair from one ftp:property element. You can extract the value of the name attribute using the FTPProperty object's getProperty() with the constant

com.iona.webservices.wsdl.ext.ftp.FTPProperty.NAME. You can extract the value of the value attribute using the FTPProperty object's getProperty() with the constant

com.iona.webservices.wsdl.ext.ftp.FTPProperty.VALUE. Once you have the values of the properties, it is up to you to determine how they impact the coordination scheme.

Example 90 on page 202 shows code for supporting the properties shown in Example 89 on page 201.

Example 90. Using Custom FTP Properties

```
import com.iona.webservices.wsdl.ext.FTPProperties;
import com.iona.webservices.wsdl.ext.FTPProperty;

String nameTypeProp = "UseHumanNames";
String lastNameProp = "LastName";
for (Iterator it = properties.getExtensors(); it.hasNext();)
```

```
{
  FTPProperty property = (FTPProperty)it.next();
  String n = property.getProperty(FTPProperty.NAME);

if (nameTypeProp.equals(n))
  {
   Boolean useHuman = new Boolean(property.getProperty(FTPProperty.VALUE));
  }

if (lastNameProp.equals(n))
  {
   String lastName = property.getProperty(FTPProperty.VALUE);
  }
}
```

Filling in the filename factory property metadata

The server-side filename factory's <code>getPropertiesMetaData()</code> method is a convenience function that can be used to publish the supported custom properties. It returns the details of the supported properties in an array of <code>com.iona.jbus.transports.ftp.policy.server.FilenameFactoryPropertyMetaData</code> objects.

FilenameFactoryPropertyMetaData objects have three fields:

- name is a string that specifies the value of the ftp:property element's name attribute.
- readonly is a boolean that specifies if you can set this property in a contract.
- valueSet is an array of strings that specify the possible values for the property.

FilenameFactoryPropertyMetaData objects do not have any methods for populating its fields once the object is instantiated. You must set all of the values using the constructor that is shown in Example 91 on page 203.

Example 91. Constructor for FilenameFactoryPropertyMetaData

```
valueSet = vs;
}
```

Example 92 on page 204 shows code for creating an array to be returned from getPropertiesMetaData().

Example 92. Populating the Filename Properties Metadata

The list of possible values specified for the property LastName is set to \mathtt{null} because the property can have any string value.

Using WebSphere MQ

Artix can use WebSphere MQ to transport messages and leverage much of WebSphere's infrastructure to provide QoS.

Adding a WebSphere MQ Endpoint	. 206
Websphere MQ Connection Settings	
Specifying the WebSphere Library to Load	
Using Queues on Remote Hosts	
Setting a Value of the Message Descriptor's Format Field	

Adding a WebSphere MQ Endpoint

Overview

The description for an Artix WebSphere MQ endpoint is entered in a port element of the Artix contract containing the interface to be exposed over WebSphere MQ. Artix defines two elements to describe WebSphere MQ endpoints and their attributes:

- mg:client defines an endpoint for a WebSphere MQ client application.
- mq:server defines an endpoint for a WebSphere MQ server application.

You can use one or both of the WebSphere MQ elements to describe a WebSphere MQ endpoint. Each can have different configurations depending on the attributes you choose to set.

WebSphere MQ namespace

The WSDL extensions used to describe WebSphere MQ transport details are defined in the WSDL namespace

 $\label{lem:http://schemas.iona.com/transports/mq. If you are going to add a WebSphere MQ port by hand you will need to include the following in the definitions tag of your contract:$

xmlns:mq="http://schemas.iona.com/transports/mq"

Required Attributes

When you define a WebSphere MQ endpoint you need to provide at least enough information for the endpoint to connect to its message queues. For any WebSphere application that means setting the <code>QueueManager</code> and <code>QueueName</code> attributes in the <code>port</code> element. In addition, if you are configuring a client that expects to receive replies from the server, you need to set the

a client that expects to receive replies from the server, you need to set the ReplyQueueManager and ReplyQueueName attributes of the mq:client element defining the client endpoint.

In addition, if you are deploying applications on a machine with a full MQ installation, you need to set the Server_Client attribute to client if the endpoint is going to use remote queues. This setting instructs Artix to load libmqic instead of libmqm.

Using the command line tool

To use **wsdltoservice** to add a WebSphere MQ endpoint use the tool with the following options.

wsdltoservice {-transport mq} [-e service] [-t port] [-b binding] [-sqm queueManager] [-sqn queue] [-srqm queueManager] [-srqn queue] [-smqn modelQueue] [-sus usageStyle] [-scs correlationStyle] [-sam accessMode] [-sto timeout] [-sme expiry] [-smp priority] [-smi messageId] [-sci correlationId] [-sd delivery] [-st transactional] [-sro reportOption] [-sf format] [-sad applicationData] [-sat accountingToken] [-SCn connectionName] [-SC convert] [-SCr reusable] [-scfp fastPath] [-said idData] [-saod originData] [-cqm queueManager] [-cqn queue] [-crqm queueManager] [-crqn queue] [-cmqn modelQueue] [-cus usageStyle] [-ccs correlationStyle] [-cam accessMode] [-cto timeout] [-cme expiry] [-cmp priority] [-cmi messageId] [-cci correlationId][-cd delivery][-ct transactional][-cro reportOption] [-cf format] [-cad applicationData] [-cat accountingToken] [-ccn connectionName] [-cc convert] [-ccr reusable] [-ccfp fastPath] [-caid idData] [-caod originData] [-caon queue] [-cui userId] [-o file] [-d dir] [-L file] [[-quiet] | [-verbose]] [-h] [-v] wsdlurl

The $-transport\ mq$ flag specifies that the tool is to generate a WebSphere MQ service. The other options are as follows.

Table 29. Options for Adding a WebSphere MQ Endpoint

Option	Description	
-e service	Specifies the name of the generated service element.	
-t port	Specifies the value of the name attribute of the generated port element.	
-b binding	Specifies the name of the binding for which the endpoint is generated.	
-sqm queueManager	Specifies the name of the server's queue manager.	
-sqn queue	Specifies the name of the server's request queue.	
-srqm queueManager	Specifies the name of the server's reply queue manager.	
-srqn queue	Specifies the name of the server's reply queue.	
-smqn modelQueue	Specifies the name of the server's model queue.	

Option	Description	
-sus usageStyle	Specifies the value of the server's UsageStyle attribute. Valid values are Peer,	
	Requester, Or Responder.	
-scs correlationStyle	Specifies the value of the server's <code>CorrelationStyle</code> attribute. Valid values are	
	messageId, correlationId, Of messageId copy.	
-sam accessMode	Specifies the value of the server's AccessMode attribute. Valid values are peek, send,	
	receive, receive exclusive, Or receive shared.	
-sto timeout	Specifies the value of the server's Timeout attribute.	
-sme expiry	Specifies the value of the server's MessageExpiry attribute.	
-smp priority	Specifies the value of the server's MessagePriority attribute.	
-smi messageId	Specifies the value of the server's MessageId attribute.	
-SCi correlationId	Specifies the value of the server's CorrelationID attribute.	
-sd delivery	Specifies the value of the server's Delivery attribute.	
-st transactional	Specifies the value of the server's Transactional attribute. Valid values are none,	
	internal, Or xa.	
-sro reportOption	Specifies the value of the server's ReportOption attribute. Valid values are none,	
	coa, cod, exception, expiration, Of discard.	
-sf format	Specifies the value of the server's Format attribute.	
-sad applicationData	Specifies the value of the server's ApplicationData attribute.	
-sat accountingToken	Specifies the value of the server's AccountingToken attribute.	
-scn connectionName	Specifies the name of the connection by which the adapter connects to the queue.	
-sc convert	Specifies if the messages in the queue need to be converted to the system's native encoding. Valid values are true or false.	
-scr reusable	Specifies the value of the server's ConnectionReusable attribute. Valid values a	
	true Or false.	
-scfp fastPath	Specifies the value of the server's ConnectionFastPath attribute. Valid values are	
	true Or false.	

Option	Description	
-said idData	Specifies the value of the server's ApplicationIdData attribute.	
-saod <i>originData</i>	Specifies the value of the server's ApplicationOriginData attribute.	
-cqm queueManager	Specifies the name of the client's queue manager.	
-cqn queue	Specifies the name of the client's request queue.	
-crqm queueManager	Specifies the name of the client's reply queue manager.	
-crqn queue	Specifies the name of the client's reply queue.	
-cmqn modelQueue	Specifies the name of the client's model queue.	
-cus usageStyle	Specifies the value of the client's <code>UsageStyle</code> attribute. Valid values are <code>Peer</code> , <code>Requester</code> , or <code>Responder</code> The default value is <code>Requester</code> .	
-ccs correlationStyle	Specifies the value of the client's CorrelationStyle attribute. Valid values are messageId, correlationId, Or messageId copy.	
-cam accessMode	Specifies the value of the client's AccessMode attribute. Valid values are peek, send, receive, receive exclusive, Or receive shared.	
-cto timeout	Specifies the value of the client's Timeout attribute.	
-cme expiry	Specifies the value of the client's MessageExpiry attribute.	
-cmp priority	Specifies the value of the client's MessagePriority attribute.	
-cmi messageId	Specifies the value of the client's MessageId attribute.	
-cci correlationId	Specifies the value of the client's CorrelationId attribute.	
-cd delivery	Specifies the value of the client's Delivery attribute.	
-ct transactional	Specifies the value of the client's Transactional attribute. Valid values are none, internal, Or xa.	
-cro reportOption	Specifies the value of the client's ReportOption attribute. Valid values are none, coa, cod, exception, expiration, Or discard.	
-cf format	Specifies the value of the client's Format attribute.	
-cad applicationData	Specifies the value of the client's ApplicationData attribute.	

Option	Description	
-cat accountingToken	Specifies the value of the client's AccountingToken attribute.	
-ccn connectionName	Specifies the name of the connection by which the adapter connects to the queue.	
-cc convert	Specifies if the messages in the queue need to be converted to the system's native encoding. Valid values are true or false.	
-ccr reusable	Specifies the value of the client's ConnectionReusable attribute. Valid values are true Or false.	
-ccfp fastPath	Specifies the value of the client's ConnectionFastPath attribute. Valid values are true Or false.	
-caid idData	Specifies the value of the client's ApplicationIdData attribute.	
-caod originData	Specifies the value of the client's ApplicationOriginData attribute.	
-caqn queue	Specifies the remote queue to which a server will put replies if its queue manager is not on the same host as the client's local queue manager.	
-cui userId	Specifies the value of the client's UserIdentification attribute.	
-o file	Specifies the filename for the generated contract. The default is to append -service to the name of the imported contract.	
-d dir	Specifies the output directory for the generated contract.	
-L file	Specifies the location of your Artix license file. The default behavior is to check <pre>IT_PRODUCT_DIR\etc\license.txt.</pre>	
-quiet	Specifies that the tool runs in quiet mode.	
-verbose	Specifies that the tool runs in verbose mode.	
-h	Displays the tool's usage statement.	
-v	Displays the tool's version.	

For more information about the specific attributes and their values see the Artix WSDL Extension Reference

[http://www.iona.com/support/docs/artix/5.5/wsdl ref/index.htm].

Example

An Artix contract exposing an interface, monsterBash, bound to a SOAP payload format, Raydon, on an WebSphere MQ queue, UltraMan would contain a service element similar to Example 93 on page 211.

Example 93. Sample WebSphere MQ Port

Websphere MQ Connection Settings

Overview

Granting authority for setting context information

The Artix ESB MQ transport makes some basic connection decisions. These have an impact on the privileges required when Artix ESB connects to a queue manager, and how context information is handled.

You can control access privileges using the WebSphere MQ **setmqaut** command.

Example 94 on page 212 shows the commands required to provide the proper authorization for the Artix ESB transport. For example, these commands apply when the Artix AccessMode WSDL extension is set to send+setid.

Example 94. Granting the MQ Transport Authorization

```
setmqaut -m MY_QMNGR -t queue -n MY_Q -g grp +all
setmqaut -m MY_QMNGR -t queue -n MY_Q -g grp -setall -passid
-passall
```

For more details on setting authorizations, see the entry for MQ AccessModes in the Artix WSDL Extension Reference

[http://www.iona.com/support/docs/artix/5.5/wsdl ref/index.htm].

Further information

For more information on the implications of using MQOO_SET_ALL_CONTEXT, the **setmqaut** command, and so on, see:

http://publibboulderiom.com/infocenter/wmqv6/v6r0/index.jsp?topic=/com/ibm.mq.csqzaw.doc/uj.19910_.htm. http://publibboulderiom.com/infocenter/wmqv6/v6r0/index.jsp?topic=/com/ibm.mq.amgzag.doc/fa15980_.htm.

Specifying the WebSphere Library to Load

Overview

The version of the WebSphere MQ shared library loaded by an Artix MQ endpoint alters the types of queues that an endpoint can access. For example, if an Artix endpoint loads the MQ client shared library, it will only be able to use queues hosted on a remote machine. Artix provides an attribute in the MQ WSDL extensions that allows you to control which library is loaded.

The attribute

Both the mq:server element and the mq:client element support the attribute that is used to specify which MQ libraries to load. The server_Client attribute specifies which shared libraries to load on systems with a full WebSphere MQ installation. Table 30 on page 213 describes the settings for this attribute for each type of WebSphere MQ installation.

Table 30. WebSphere MQ Server Client Attribute Settings

MQ Installation	Server_Client	Behavior
	Value	
Full		The server shared library(libmqm) is loaded and the application will use
		queues hosted on the local machine.
Full	server	The server shared library(libmqm) is loaded and the application will use
		queues hosted on the local machine.
Full	client	The client shared library(libmqic) is loaded and the application will use
		queues hosted on a remote machine.
Client		The application will attempt to load the server shared library(libmqm) before
		loading the client shared library(libmqic). The application accesses queues
		hosted on a remote machine.
Client	server	The application will fail because it cannot load the server shared libraries.
Client	client	The client shared library(libmqic) is loaded and the application accesses
		queues hosted on a remote machine.

Example

Example 95 on page 214 shows an a service element for an MQ endpoint that uses the MQ client shared library.

Example 95. ARTIX MQ Endpoint Using MQ Client Library

Using Queues on Remote Hosts

Overview

When interoperating between WebSphere MQ endpoints whose queue managers are on different hosts, Artix requires that you specify the name of the remote queue to which the server will post reply messages. This ensures that the server will put the replies on the proper queue. Otherwise, the server will receive a request message with the ReplyToQ field set to a queue that is managed by a queue manager on a remote host and will be unable to send the reply.

You specify this server's local reply queue name in the mq:client element's AliasQueueName attribute when you define it in the client endpoint's contract.

Effect of AliasQueueName

When you specify a value for the AliasQueueName attribute in an mq:client element, you alter how Artix populates the request message's ReplyToQ field and ReplyToQMgr field. Typically, Artix populates the reply queue information in the request message's message descriptor with the values specified in the ReplyQueueManager attribute and the ReplyQueueName attribute. Setting the AliasQueueName attribute causes Artix to leave ReplytoQMgr empty, and to set ReplyToQ to the value of the AliasQueueName attribute. When the ReplyToQMgr field of the message descriptor is left empty, the sending queue manager inspects the queue named in the ReplyToQ field to determine who its queue manager is and uses that value for ReplyToQMgr. The server puts the message on the remote queue that is configured as a proxy for the client's local reply queue.

Example

If you had a system defined similar to that shown in Figure 2 on page 216, you would need to use the AliasQueueName attribute setting when configuring your WebSphere MQ client. In this set up the client is running on a host with a local queue manager QMgrA. QMgrA has two queues configured. RqA is a remote queue that is a proxy for RqB and RplyA is a local queue. The server is running on a different machine whose local queue manager is QMgrB. QMgrB also has two queues. RqB is a local queue and RplyB is a remote queue that is a proxy for RplyA. The client places its request on RqA and expects replies to arrive on RplyA.




Figure 2. MQ Remote Queues

The port elements for the client and server for this deployment are shown in Example 96 on page 216. The AliasQueueName attribute is set to RplyB because that is the remote queue proxying for the reply queue in server's local queue manager. The ReplyQueueManager attribute and the ReplyQueueName attribute are set to the client's local queue manager so that it knows where to listen for responses. In this example, the server's ReplyQueueManager attribute and ReplyQueueName attribute do not need to be set because you are assured that the client is populating the request's message descriptor with the needed information for the server to determine where replies are sent.

Example 96. Setting Up WebSphere MQ Ports for Intercommunication

Setting a Value of the Message Descriptor's Format Field

Overview

WebSphere MQ messages have a Format field in their message descriptors. Message receivers use this field to determine the nature of the data in the nature. What the message receiver does with this information is the responsibility of the application developer. Artix, however, uses the Format field to determine if the contents of a message are to undergo codeset conversion.

You can specify the value placed in the message descriptor's Format field using the Format attribute. This attribute is supported by both the mq:client element and the mq:server element and its value is a string specifying the name of the message's format.

Special values

The Format attribute can take the special values described in Table 31 on page 217.

Table 31. WebSphere MQ Format Attribute Settings

Attribute Setting	Description
none (Default)	Corresponds to MQFMT_NONE. No format name is specified.
string	Corresponds to MQFMT_STRING. string specifies that the message consists entirely of character data. The message data may be either single-byte characters or double-byte characters.
unicode	Corresponds to MQFMT_STRING. unicode specifies that the message consists entirely of Unicode characters. (Unicode is not supported in Artix at this time.)
event	Corresponds to MQFMT_EVENT. event specifies that the message reports the occurrence of an WebSphere MQ event. Event messages have the same structure as programmable commands.
programmable command	Corresponds to MQFMT_PCF. programmable command specifies that the messages are user-defined messages that conform to the structure of a programmable command format (PCF) message.

Attribute Setting	Description
	For more information, consult the IBM Programmable Command Formats and Administration Interfaces documentation at http://publibfp.boulder.ibm.com/epubs/html/csqzac03/csqzac030d.htm#Header_12 .

Using codeset conversion

Artix uses the value of the Format field in an MQ message header to determine if the message data should be converted into a host systems native codeset. If the Format field is set to MQFMT_STRING, Artix will attempt to convert the data into the host's native codeset. If the Format field has any other value, Artix will not attempt to perform codeset conversion.

If you are interoperating with systems that use a different codeset than the system your endpoint is hosted on, you need to set the Format attribute of the Artix endpoint to string. This is particularly important when you are interoperating with WebSphere MQ applications hosted on a mainframe because the data needs to be converted into the systems native data format. Not doing so will result in the mainframe receiving corrupted data.

Example

Example 97 on page 218 shows an mq:client element that defines an endpoint used for making requests against a server on a mainframe system. In this particular example, we are talking directly to the mainframe queue manager.

Example 97. WebSphere MQ Client Talking to the Mainframe

In this example, you will also need to set the MQSERVER environment variable.

The section *Using a Remote MQ Server* in Artix Technical Use Cases [http://www.iona.com/support/docs/artix/5.0/cookbook/index.htm] explains this in detail.

Using TIBCO Rendezvous

The TIBCO Rendezvous transport lets you use Artix to integrate systems based on TIBCO Rendezvous (TIB/RV) software.

Supported features

Table 32 on page 219 shows the matrix of TIBCO Rendezvous features Artix supports.

Table 32. Supported TIBCO Rendezvous Features

Feature	Supported	Not Supported
Server-Side Advisory Callbacks	х	
Certified Message Delivery	х	
Fault Tolerance (TibrvFtMember/Monitor)		х
Virtual Connections (TibrvVcTransport)		х
Secure Daemon (rvsd/TibrvSDContext)		х
TIBRVMSG_IPADDR32		х
TIBRVMSG_IPPORT16		х

Namespace

To use the TIB/RV transport, you need to define the endpoint using TIB/RV in the physical part of an Artix contract. The extensions used to describe a TIB/RV endpoint are defined in the namespace:

xmlns:tibrv="http://schemas.iona.com/transports/tibrv"

This namespace will need to be included in your Artix contract's definition element.

Describing the port

As with other transports, the TIB/RV transport specifications are contained within a port element. Artix uses tibrv:port to describe the attributes of a TIB/RV endpoint. The only required attribute for a tibrv:port element is serverSubject which specifies the subject to which the server listens.

Using the command line tools

To use wsdltoservice to add a TIB/RV endpoint use the following options.

wsdltoservice {-transport tibrv} [-e service] [-t port] [-b binding] [-tss subject] [-tcst subject] [-tbt bindingType] [-tcl callbackLevel] [-trdt timeout] [-tts transportService] [-ttn transportNetwork] [-ttbm batchMode] [-tqp priority] [-tqlp queueLimitPolicy] [-tqme queueMaxEvents] [-tqda queueDiscardAmount] [-tcs cmSupport] [-tctsn cmTransportServerName] [-tctcn cmTransportClientName] [-tctro cmTransportRequestOld] [-tctln cmTransportLedgerName] [-tctsl cmTransportSyncLedger] [-tctra cmTransportRelayAgent] [-tctdtl cmTransportDefaultTimeLimit][-tclca cmListenerCancelAgreements] [-tcqtsn cmQueueTransportServerName] [-tcqtcn cmQueueTransportClientName] [-tcqtww cmQueueTransportWorkerWeight] [-tcqtws cmQueueTransportWorkerTasks] [-tcqtsw cmQueueTransportSchedulerWeight] [-tcqtsh cmQueueTransportSchedulerHeartbeat][-tcqtsa cmQueueTransportSchedulerActivation] [-tcqtct cmQueueTransportCompleteTime] [-tmnfv messageNameFieldValue] [-tmnfp messageNameFieldPath] [-tbfi bindingFieldId] [-tbfn bindingFieldName] [-0 file] [-d dir] [-L file] [[-quiet] | [-verbose]] [-h] [-v] wsdlurl

The -transport tibry flag specifies that the tool is to generate a TIB/RV service. The other options are as follows.

Table 33. Options for Adding a TIB/RV Endpoint

-e service	Specifies the name of the generated service element.
-t port	Specifies the value of the name attribute of the generated port element.
-b binding	Specifies the name of the binding for which the endpoint is generated.
-tss subject	Specifies the subject to which the server listens.
-tcst subject	Specifies the prefix to the subject on which the client listens for replies.

-tbt bindingType	Specifies the message binding type. Valid values are msg, xml, opaque,
	Of string.
-tcl callbackLevel	Specifies the server-side callback level when TIB/RV system advisory messages are received. Valid values are INFO, WARN, or ERROR.
-trdt timeout	Specifies the client-side response receive dispatch timeout.
-tts transportService	Specifies the UDP service name or port for TibrvNetTransport.
-ttn transportNetwork	Specifies the binding network addresses for TibrvNetTransport.
-ttbm batchMode	Specifies if the TIB/RV transport uses batch mode to send messages. Valid values are DEFAULT_BATCH and TIMER_BATCH.
-tqp priority	Specifies the queue priority.
-tqlp queueLimitPolicy	Valid values are discard_none, discard_new, discard_first, or discard_last.
-tqme queueMaxEvents	Specifies the queue max events.
-tqda queueDiscardAmount	Specifies the queue discard amount.
-tcs cmSupport	Specifies if Certified Message Delivery support is enabled. Valid values are true or false.
-tctsn cmTransportServerName	Specifies the server's TibrvCmTransport correspondent name.
-tctcn cmTransportClientName	Specifies the client TibrvCmTransport correspondent name.
-tctro cmTransportRequestOld	Specifies if the endpoint can request old messages on start-up. Valid values are true or false.
-tctln cmTransportLedgerName	Specifies the TibrvCmTransport ledger file.
-tctsl cmTransportSyncLedger	Specifies if the endpoint uses a synchronous ledger. Valid values are true or false.
-tctra cmTransportRelayAgent	Specifies the endpoint's TibrvCmTransport relay agent.
-tctdtl cmTransportDefaultTimeLimit	Specifies the default time limit for a Certified Message to be delivered.
-tclca cmListenerCancelAgreements	Specifies if Certified Message agreements are canceled when the endpoint disconnects. Valid values are true or false.
-tcqtsn cmQueueTransportServerName	Specifies the server's TibrvCmQueueTransport correspondent name.
	•

-tcqtcn cmQueueTransportClientName	Specifies the client's TibrvCmQueueTransport correspondent name.
-tcqtww	Specifies the endpoint's TibrvCmQueueTransport worker weight.
cmQueueTransportWorkerWeight	
-tcqtws cmQueueTransportWorkerTasks	Specifies the endpoint's TibrvCmQueueTransport worker tasks
	parameter.
-tcqtsw	Specifies the TibrvCmQueueTransport scheduler weight parameter.
cmQueueTransportSchedulerWeight	
-tcqtsh	Specifies the endpoint's TibrvCmQueueTransport scheduler heartbeat
cmQueueTransportSchedulerHeartbeat	parameter.
-tcqtsa	Specifies the TibrvCmQueueTransport scheduler activation
cmQueueTransportSchedulerActivation	parameter.
-tcqtct	Specifies the TibrvCmQueueTransport complete time parameter.
cmQueueTransportCompleteTime	
-tmnfv messageNameFieldValue	Specifies the message name field value.
-tmnfp messageNameFieldPath	Specifies the message name field path.
-tbfi bindingFieldId	Specifies the binding field id.
-tbfn bindingFieldName	Specifies the binding field name.
-o file	Specifies the filename for the generated contract. The default is to append -service to the name of the imported contract.
-d dir	Specifies the output directory for the generated contract.
-L file	Specifies the location of your Artix license file. The default behavior is to check IT_PRODUCT_DIR\etc\license.txt.
-quiet	Specifies that the tool runs in quiet mode.
-verbose	Specifies that the tool runs in verbose mode.
-h	Displays the tool's usage statement.
-v	Displays the tool's version.

For more information about the specific attributes and their values see the Artix WSDL Extension Reference [../../wsdl ref/index.htm].

Example

Example 98 on page 223 shows an Artix description for a TIB/RV endpoint.

Example 98. TIB/RV Port Description

```
<service name="BaseService">
  <port binding="tns:BasePortBinding" name="BasePort">
        <tibrv:port serverSubject="Artix.BaseService.BasePort"/>
        </port>
    </service>
```

Using Tuxedo

Artix allows services to connect using Tuxedo's transport mechanism. This provides them with all of the qualities of service associated with Tuxedo.

Tuxedo namespaces

To use the Tuxedo transport, you need to describe the endpoint using Tuxedo in the physical part of an Artix contract. The extensions used to describe a Tuxedo endpoint are defined in the following namespace:

xmlns:tuxedo="http://schemas.iona.com/transports/tuxedo"

This namespace will need to be included in your Artix contract's definition element.

Defining the Tuxedo services

As with other transports, the Tuxedo transport description is contained within a port element. Artix uses a tuxedo:server element to describe the attributes of a Tuxedo endpoint. The tuxedo:server element has a child element, tuxedo:service, that gives the bulletin board name of a Tuxedo endpoint. The bulletin board name for the endpoint is specified in the element's name attribute. You can define more than one Tuxedo service to act as an endpoint.

Mapping operations to a Tuxedo service

For each of the Tuxedo services that are endpoints, you must specify which of the operations bound to the endpoint being defined are handled by the Tuxedo service. This is done using one or more tuxedo:input child elements.

The tuxedo:input element takes one required attribute, operation, that specifies the WSDL operation that is handled by this Tuxedo service endpoint.

Using the command line tools

To use **wsdltoservice** to add a Tuxedo endpoint use the tool with the following options.

wsdltoservice {-transport tuxedo} [-e service] [-t port] [-b binding]
[-tsn tuxService] [-tfn tuxService:tuxFunction] [-ton
tuxService:operation] [-0 file] [-d dir] [-L file] [[-quiet] | [-verbose]]
[-h] [-v] wsdlurl

The -transport tuxedo flag specifies that the tool is to generate a Tuxedo service. The other options are as follows.

Table 34. Options for Adding a Tuxedo Service

Option	Description
-e service	Specifies the name of the generated service
	element.
-t port	Specifies the value of the name attribute of the
	generated port element.
-b binding	Specifies the name of the binding for which the endpoint is generated.
-tsn tuxService	Specifies the name the service uses when registering with the Tuxedo bulletin board.
-tfn	Specifies the name of the function to be used on
tuxService:tuxFunction	the specified Tuxedo bulletin board.
-ton	Specifies the WSDL operation that is handled by
tuxService:operation	the specified Tuxedo endpoint.
-o file	Specifies the filename for the generated contract. The default is to append -service to the name
	of the imported contract.
-d dir	Specifies the output directory for the generated contract.
-L file	Specifies the location of your Artix license file.
	The default behavior is to check IT PRODUCT DIR\etc\license.txt.
-quiet	Specifies that the tool runs in quiet mode.
-verbose	Specifies that the tool runs in verbose mode.
-h	Displays the tool's usage statement.
-v	Displays the tool's version.

For more information about the specific attributes and their values see the Artix WSDL Extension Reference [../../wsdl_ref/index.htm].

Example

An Artix contract exposing the personalInfoService as a Tuxedo endpoint would contain a service element similar to Example 99 on page 227.

Example 99. Tuxedo Port Description

Part III. Other Artix ESB Features

Working with CORBA	233
Adding a CORBA Binding	
Creating a CORBA Endpoint	240
Procedure	241
Configuring an Artix CORBA Endpoint	242
Generating CORBA IDL	246
Using the Artix Transformer	249
Using the Artix Transformer as a Service	250
Using Artix to Facilitate Interface Versioning	252
WSDL Messages and the Transformer	257
Writing XSLT Scripts	260
Elements of an XSLT Script	261
XSLT Templates	263
Common XSLT Functions	269
Using Codeset Conversion	271

Working with CORBA

CORBA, unlike the other platforms supported by Artix ESB, specifies both a mapping between the logical messages and a network protocol. Because these two cannot be decoupled, Artix provides extensions for both and requires that they be used together. To further enforce the coupling of the CORBA payload format and the CORBA network protocol all Artix tools that generate CORBA extensions generate them in sets.

Adding a CORBA Binding	. 234
Creating a CORBA Endpoint	
Procedure	
Configuring an Artix CORBA Endpoint	
Generating CORBA IDL	

Adding a CORBA Binding

Overview

CORBA applications use a specific payload format when making and responding to requests. The CORBA binding, described using a WSDL extension, specifies the repository ID of the IDL interface represented by the port type, resolves parameter order and mode ambiguity in the operations' messages, and maps the XML Schema data types to CORBA data types.

In addition to the binding information, Artix also uses a <code>corba:typemap</code> element to unambiguously describe how data is mapped to CORBA data types. For primitive types, the mapping is straightforward. However, complex types such as structures, arrays, and exceptions require more detailed descriptions. For a detailed description of the CORBA type mappings see Artix for CORBA [../../corba ws/index.htm].

Options

To add a CORBA binding to an Artix contract you can choose one of the following methods:

- Use Artix Designer. Artix Designer provides a wizard that automatically generates the binding and type map information for a specified port type.
- Use the wsdltocorba command line tool. The command line tool automatically generates the binding and type map information for a specified port type. See Using wsdltocorba on page 234.
- Enter the binding and typemap information by hand using a text editor or XML editor. This option provides you the flexibility to customize the binding. However, hand editing Artix contracts can be a time consuming process and provides no error checking mechanisms. For information on the WSDL extensions used to specify a CORBA binding see Mapping to the binding on page 236.

Using wsdltocorba

The **wsdltocorba** tool adds CORBA binding information to an existing Artix contract. To generate a CORBA binding use the following command:

wsdltocorba {-corba} {-i portType} [-d dir] [-b binding] [-o file] [-props
namespace] [-wrapped] [-L file] [[-quiet] | [-verbose]] [-h] [-v] wsdl_file

The command has the following options:

Table 35. Options for Adding a CORBA Binding

-corba	Instructs the tool to generate a CORBA binding for the specified port type.
-i portType	Specifies the name of the port type being mapped to a CORBA binding.
-d dir	Specifies the directory into which the new WSDL file is written.
-b binding	Specifies the name for the generated CORBA binding. Defaults to portTypeBinding.
-o file	Specifies the name of the generated WSDL file. Defaults to wsdl_file-corba.wsdl.
-props namespace	Specifies the namespace to use for the generated CORBA typemap
-wrapped	Specifies that the generated CORBA binding uses wrapper types.
-L file	Specifies the location of your Artix license file. The default behavior is to check IT_PRODUCT_DIR\etc\license.txt.
-quiet	Specifies that the tool runs in quiet mode. No output will be shown on the console. This includes error messages.
-verbose	Specifies that the tool runs in verbose mode.
-h	Specifies that the tool will display a usage message.
-A	Displays the tool's version.

The generated WSDL file will also contain a CORBA endpoint with no address specified. To complete the endpoint specification you can do so manually or use Artix Designer.

WSDL namespace

The WSDL extensions used to describe CORBA data mappings and CORBA transport details are defined in the WSDL namespace

http://schemas.iona.com/bindings/corba. To use the CORBA extensions you will need to include the following in the definitions tag of your contract:

xmlns:corba="http://schemas.iona.com/bindings/corba"

Mapping to the binding

The extensions used to map a logical operation to a CORBA binding are described in detail below:

• corba:binding

corba:binding indicates that the binding is a CORBA binding. This element has one required attribute: repositoryID. The repositoryID attribute specifies the full type ID of the interface. The type ID is embedded in the object's IOR and therefore must conform to the IDs that are generated from an IDL compiler. These are of the form:

```
IDL:module/interface:1.0
```

The corba:binding element also has an optional attribute, bases, that specifies that the interface being bound inherits from another interface. The value for bases is the type ID of the interface from which the bound interface inherits. For example, the following IDL:

```
//IDL
interface clash{};
interface bad : clash{};
```

would produce the following corba: binding:

```
<corba:binding repositoryID="IDL:bad:1.0"
bases="IDL:clash:1.0"/>
```

• corba:operation

corba:operation is an Artix-specific element of the operation element and describes the parts of the operation's messages. corba:operation takes a single attribute, name, which duplicates the name given in operation.

• corba:param

corba:param is a child of corba:operation. Each part element of the input and output messages specified in the logical operation, except for the

part representing the return value of the operation, must have a corresponding <code>corba:param</code> element. The parameter order defined in the binding must match the order specified in the IDL definition of the operation. The <code>corba:param</code> element has the following required attributes:

Table 36. Attributes of corba:param

Attribute	Description
mode	Specifies the direction of the parameter. The values directly correspond to the IDL directions: in, inout, out. Parameters
	set to in must be included in the input message of the logical
	operation. Parameters set to out must be included in the
	output message of the logical operation. Parameters set to inout must appear in both the input and output messages
	of the logical operation.
idltype	Specifies the IDL type of the parameter. The type names are prefaced with corba: for primitive IDL types, and corbatm: for complex data types, which are mapped out in the corba:typeMapping portion of the contract.
name	Specifies the name of the parameter as given in the logical portion of the contract.

• corba:return

corba:return is a child of corba:operation and specifies the return type, if any, of the operation. It has two attributes:

Attribute	Description
name	Specifies the name of the parameter as given in the logical portion of the contract.
idltype	Specifies the IDL type of the parameter. The type names are prefaced with corba: for primitive IDL types and corbatm: for complex data types which are mapped out in the corba:typeMapping portion of the contract.

• corba:raises

corba:raises is a child of corba:operation and describes any exceptions the operation can raise. The exceptions are defined as fault messages in the logical definition of the operation. Each fault message must have a corresponding corba:raises element. corba:raises has one required attribute, exception, which specifies the type of data returned in the exception.

In addition to operations specified in corba:operation tags, within the WSDL operation element, each operation element in the binding must also specify empty input and output elements as required by the WSDL specification. The CORBA binding specification, however, does not use them.

For each fault message defined in the logical description of the operation, a corresponding <code>fault</code> element must be provided in the <code>operation</code> element, as required by the WSDL specification. The <code>name</code> attribute of the <code>fault</code> element specifies the name of the schema type representing the data passed in the fault message.

For example, a logical interface for a system to retrieve employee information might look similar to personalInfoLookup, shown in

Example 100 on page 238.

Example 100. personalInfo lookup port type

```
<message name="personalLookupRequest">
 <part name="empId" type="xsd:int"/>
</message>
<message name="personalLookupResponse">
 <part name="return" element="xsd1:personalInfo"/>
<message name="idNotFoundException">
 <part name="exception" element="xsd1:idNotFound"/>
</message>
<portType name="personalInfoLookup">
 <operation name="lookup">
   <input name="empID" message="personalLookupRequest"/>
   <output name="return"</pre>
           message="personalLookupResponse"/>
   <fault name="exception" message="idNotFoundException"/>
 </operation>
</portType>
```

Example

The CORBA binding for personalInfoLookup is shown in Example 101 on page 239.

Example 101. personalInfoLookup CORBA Binding

```
<binding name="personalInfoLookupBinding"</pre>
         type="tns:personalInfoLookup">
 <corba:binding repositoryID="IDL:personalInfoLookup:1.0"/>
 <operation name="lookup">
    <corba:operation name="lookup">
      <corba:param name="empId" mode="in"</pre>
                  idltype="corba:long"/>
      <corba:return name="return"</pre>
                    idltype="corbatm:personalInfo"/>
      <corba:raises exception="corbatm:idNotFound"/>
   </corba:operation>
   <input/>
   <output/>
   <fault name="personalInfoLookup.idNotFound"/>
 </operation>
</binding>
```

Creating a CORBA Endpoint

Procedure	241
Configuring an Artix CORBA Endpoint	242
Generating CORBA IDL	246

Procedure

Generally, when you are creating a CORBA endpoint with Artix, you need to do two things:

- 1. Specify the port information in the Artix contract so that Artix can instantiate the appropriate port.
- 2. Generate the IDL describing your service so that a native CORBA application can understand the interfaces of the new service.

Configuring an Artix CORBA Endpoint

Overview

CORBA endpoints are described using the Artix-specific WSDL elements corba:address and corba:policy within the WSDL port element, to specify how a CORBA object is exposed.

Namespace

The namespace under which the CORBA extensions are defined is http://schemas.iona.com/bindings/corba. If you are going to add a CORBA endpoint by hand you will need to add this to your contract's definition element.

CORBA address specification

The IOR of the CORBA object is specified using the corba: address element. You have four options for specifying IORs in Artix contracts:

 Specify the object's IOR directly in the contract, using the stringified IOR format:

IOR:22342...

• Specify a file location for the IOR, using the following syntax:

file:///file name



Note

The file specification requires three backslashes (///).

 Specify that the IOR is published to a CORBA name service, by entering the object's name using the corbaname format:

corbaname:rir/NameService#object name

For more information on using the name service with Artix see Artix for CORBA [../../corba_ws/index.htm].

• Specify the IOR using corbaloc, by specifying the port at which the endpoint exposes itself, using the corbaloc syntax.

corbaloc:iiop:host:port/service name

When using corbaloc, you must be sure to configure your endpoint to start up on the specified host and port.

Specifying POA policies

Using the optional <code>corba:policy</code> element, you can describe a number of POA polices the endpoint will use when creating the POA for connecting to a CORBA application. These policies include:

- the name of the generated POA
- · if persistence is used
- the ID of the generated POA

Setting these policies lets you exploit some of the enterprise features of Progress' Orbix 6.x, such as load balancing and fault tolerance, when deploying an Artix integration project. For information on using these advanced CORBA features, see the Orbix documentation.

POA name

Artix POAs are created with the default name of ws_{or} . To specify the name of the POA Artix creates to connect with a CORBA object, you use the following:

<corba:policy poaname="poa_name"/>

Persistence

By default Artix POAs have a persistence policy of false. To set the POA's persistence policy to true, use the following:

<corba:policy persistent="true"/>

ID assignment

By default Artix POAs are created with a SYSTEM_ID policy, meaning that their ID is assigned by the ORB. To specify that the POA connecting a specific object should use a user-assigned ID, use the following:

<corba:policy serviceid="POAid"/>

This creates a POA with a USER ID policy and an object id of POAid.

Using the command line tool

You can use the **wsdltoservice** command line tool to add a CORBA endpoint definition to an Artix contract. To use **wsdltoservice** to add a CORBA endpoint use the tool with the following options.

wsdltoservice {-transport corba} [-e service] [-t port] [-b binding] [-a
address] [-poa poaName] [-sid serviceId] [-pst persists] [-o file] [-d
dir] [-L file] [[-q] | [-V]] [-h] wsdlurl

The $-transport\ corba$ flag specifies that the tool is to generate a CORBA endpoint. The other options are as follows.

Table 37. Options for Adding a CORBA Endpoint

Argument	Descriptions
-e service	Specifies the name of the generated service element.
-t port	Specifies the value of the name attribute of the generated port element.
-b binding	Specifies the name of the binding for which the service is generated.
-a address	Specifies the value used in the corba: address element of the port.
-poa poaName	Specifies the value of the POA name policy.
-sid serviceId	Specifies the value of the ID assignment policy.
-pst persists	Specifies the value of the persistence policy. Valid values are true and false.
-o file	Specifies the filename for the generated contract. The default is to append -service to the name of the imported contract.
-d dir	Specifies the output directory for the generated contract.
-L file	Specifies the location of your Artix license file. The default behavior is to check IT_PRODUCT_DIR\etc\license.txt.
-q	Specifies that the tool runs in quiet mode. No output will be shown on the console. This includes error messages.
-h	Specifies that the tool will display a usage message.

Argument	Descriptions
-V	Specifies that the tool runs in verbose mode.

Example

For example, a CORBA port for the personalInfoLookup binding would look similar to Example 102 on page 245:

Example 102. CORBA personalInfoLookup Port

```
<service name="personalInfoLookupService">
  <port name="personalInfoLookupPort"
        binding="tns:personalInfoLookupBinding">
        <corba:address location="file:///objref.ior"/>
        <corba:policy persistent="true"/>
        <corba:policy serviceid="personalInfoLookup"/>
        </port>
</service>
```

Artix expects the IOR for the CORBA object to be located in a file called objref.ior, and creates a persistent POA with an object id of personalInfo to connect the CORBA application.

Generating CORBA IDL

Overview

Artix clients that use a CORBA transport require that the IDL defining the interface exists and be accessible. Artix provides tools to generate the required IDL from an existing WSDL contract. The generated IDL captures the information in the logical portion of the contract and uses that to generate the IDL interface. Each portType element in the contract generates an IDL module.

From the command line

The **wsdltocorba** tool compiles Artix contracts and generates IDL for the specified CORBA endpoint. To generate IDL use the following command:

 $wsdltocorba { -idl } {-b \ binding} [-corba] [-i \ portType] [-d \ dir] [-0 \ file] \\ [-L \ file] [[-q] | [-V]] [-h] \ wsdl \ file$

The command has the following options:

Table 38. Options for Generating IDL

Option	Description
-idl	Instructs the tool to generate an IDL file from the specified binding.
-b binding	Specifies the CORBA binding from which IDL is to be generated.
-corba	Instructs the tool to generate a CORBA binding for the specified port type.
-i portType	Specifies the name of the port type being mapped to a CORBA binding.
-d dir	Specifies the directory into which the new WSDL file is written.
-o file	Specifies the name of the generated WSDL file. Defaults to wsdl_file.idl.
-L file	Specifies the location of your Artix license file. The default behavior is to check IT_PRODUCT_DIR\etc\license.txt.
-q	Specifies that the tool runs in quiet mode. No output will be shown on the console. This includes error messages.
-V	Specifies that the tool runs in verbose mode.

Option	Description
-h	Specifies that the tool will display a usage message.

By combining the -idl and -corba flags with **wsdltocorba**, you can generate a CORBA binding for a logical operation and then generate the IDL for the generated CORBA binding. When doing so, you must also use the -i portType flag to specify the port type from which to generate the binding and the -b binding flag to specify the name of the binding from which to generate the IDL.

Using the Artix Transformer

The Artix transformer allows you to perform message transformations, data validation, and interface versioning without having to write additional code.

Using the Artix Transformer as a Service	250
Using Artix to Facilitate Interface Versioning	252
WSDL Messages and the Transformer	257
Writing XSLT Scripts	
Elements of an XSLT Script	
KSLT Templates	263
Common XSLT Functions	

Using the Artix Transformer as a Service

Overview

Using the Artix transformer, you can create a Web service that does simple tasks such as converting dates into the proper format or generating HTML output without writing any code. You can also develop services to validate the format of requests before they are sent to a busy server for processing.

The data processing is performed by the Artix transformer which uses an XSLT script to determine how to process the data.

Procedure

To use the Artix transformer as a service you:

- Define the data, interface, binding, and transport details for the server in an Artix contract.
- Write the XSLT script that defines the data processing you want the transformer to perform.
- 3. Configure the service with the transformer's configuration details.

Defining the server

The contract for a service that is implemented by the Artix transformer is the same as the Artix contract for any other service in Artix. You need to define the complex types, if any, that the service uses. Then you need to define the messages used by the service to receive and respond to requests.

Once the data types and messages are defined, you then define the service's interface. The only limitation for a service that is implemented by the Artix Transformer is that it cannot have any fault messages. The interface can define multiple operations. Each operation will be processed using different XSLT scripts.

After defining the logical details of the service, you need to define the binding and network details for the service. The transformer can use any of the bindings and transports supported by Artix.

Writing the scripts

The XSLT scripts tell the transformer what it needs to do to process the data it receives. The scripts can be as simple or complex as they need to be to perform the task. The only requirement is that they are valid XSLT documents.

For more information about writing XSLT scripts read Writing XSLT Scripts on page 260.

Configure the transformer

The Artix transformer is an Artix plug-in and can be loaded by an Artix process. This provides a great deal of flexibility in how you configure and deploy the process. There are two common deployment patterns for deploying the Artix transformer as a service. The first is to configure the transformer to load into the Artix container. The second is to configure the transformer to load directly into the client process which is making requests against it.

For a detailed discussion of how to configure and deploy the Artix Transformer see Configuring and Deploying Artix Solutions, C++ Runtime [../../deploy/cpp/index.htm].

Using Artix to Facilitate Interface Versioning

Overview

One of the most common and difficult problems faced in large scale client server deployments is upgrading systems. For example, if you change the interface for your server to add new functionality or streamline communications, you then need to change all of the clients that access the server. This can mean upgrading thousands of clients that may be scattered across the globe.

The Artix transformer provides a solution to this problem that allows you to slowly upgrade the clients without disrupting their ability to function. Using the transformer you can develop an XSLT script that converts messages between the different interfaces. Then you can place the transformer between the old clients and the new server. This solution eliminates the need for operating two versions of the same server, or trying to do a massive client and server upgrade. It also does this without requiring you to do any custom programing.

Procedure

To use the Artix transformer for interface versioning do the following:

- 1. Create a composite Artix contract defining both versions of the interfaces that need to be supported.
- 2. Define an interface for the transformer that defines operations for mapping the interfaces.
- 3. Add a SOAP binding to the contract for the transformer's interface.
- Add an HTTP port to the contract to define how the transformer can be contacted.
- 5. Write the XSLT scripts that define the message transformations.
- 6. Configure the transformer.
- Configure the Artix chain builder to create a chain containing the transformer and the server on which clients will make requests.

Creating a composite contract

While the server and the client applications can be run without knowledge of the other's interface, the transformer responsible for translating the messages between to the two interface versions must know about all of the

interface versions used. This includes all data type definitions and message definitions used by both versions of the interface.

You can create this composite contract in several ways. The most straightforward way is to create a new contract which imports both the new interface's contract and the old interface's contract. To import the contracts you place an import element for each contract just after the definitions element in the new contract and before any other elements in the new contract. The import element has two attributes. location specifies the pathname of the file containing the contract that is being imported. namespace defines the XML namespace under which the imported contract can be referenced.

For example, if you were creating a composite contract for interface versioning you would have two contracts; one for the server with the updated interface and one for the client using the legacy interface. The file name for the server's contract is r2e2.wsdl and the contract for the client is r2e1.wsdl. For simplicity, they are located in the same directory as the composite contract. The composite contract importing both versions of the interface is shown in Example 103 on page 253.

Example 103. Composite WSDL

Note that in the definitions element of the contract, XML namespace shortcuts are defined for the imported contracts namespace. This makes using items defined in the imported contracts much easier.

Define the transformer's interface

Once you have imported all versions of the interface that you need to support into the transformer's composite contract, you need to define the transformer's interface. The transformer must have one operation defined for each transformation that is required to support all of the interface versions. For example, if you only changed the structure of the request message in when upgrading the server's interface, the transformer only needs one operation because the transformation is only one way. If you changed both the request and response messages, the transformer's interface will need two operations; one for the request message and one for the response.

The operation to transform a request from the client to the proper format for the server takes the client's message as its input element and the server's message as its output message. The operation to transform a response from the server to the proper format for a client takes the server's outgoing message as its input element and the client's incoming message as its output element.



Note

Fault messages are not supported.

When adding the operations, be sure to use the proper namespaces when referencing the messages for the different versions of the interface. Using the wrong namespaces could result in an invalid contract at the very least. If the contract is valid, and the namespaces are incorrect, your system will behave erratically.

For example, if the interface in Example 103 on page 253 was updated so that both the client's request and the server's response need to be transformed the transformer's interface would need two operations. In this example the name of the request message is widgetRequest and the name of the response

message is widgetResponse. The interface for the transformer,

versionTransform, is shown in Example 104 on page 254.

Example 104. Versioning Interface

<portType name="versionTransform">
 <operation name="requestTransform">

In the operation transforming the request, requestTransform, the input message is taken from the namespace r1 which is the namespace under which the client's contract is imported. The output message is taken from r2 which is the namespace under which the server's contract is imported. For the response message transformation, responseTransform, the order is reversed. The input message is from r2 and the output message is from r1.

Defining the physical details for the transformer

After defining the operations used in transforming between the different version of the interface, you need to define the binding and network details for the transformer. The transformer can use any of the bindings and transports supported by Artix. For information on adding a binding for the transformer read Chapter: "Understanding Bindings in WSDL" on page 23. For information on adding network details for the transformer read Chapter: "Understanding How Endpoints are Defined in WSDL" on page 147.

Writing the XSLT scripts

The XSLT scripts tell the transformer what it needs to do to process the data it receives. The scripts can be as simple or complex as they need to be to perform the task. The only requirement is that they are valid XSLT documents. For more information about writing XSLT scripts read Writing XSLT Scripts on page 260.

Configuring the transformer

The Artix transformer is an Artix plug-in and can be loaded by an Artix process. This provides a great deal of flexibility in how you configure and deploy the process. For a detailed discussion of how to configure and deploy the Artix transformer see Configuring and Deploying Artix Solutions, C++ Runtime [../../deploy/cpp/index.htm].

When using the transformer to do interface versioning, you need to deploy it as part of a service chain. To build a service chain in Artix you deploy the Artix chain builder. Like the transformer, the chain builder is an Artix plug-in and provides a number of deployment options. One way of deploying the chain builder along with the transformer is to deploy it alongside the transformer in an Artix container.

For a detailed discussion of how to configure and deploy the Artix chain builder see Configuring and Deploying Artix Solutions, C++ Runtime [../../deploy/cpp/index.htm].

WSDL Messages and the Transformer

Overview

Incoming messages

Conceptually, the Artix transformer works on XML representations of the data passed along the wire. Your XSLT scripts are written based on the WSDL descriptions of the message's being processed. This relieves you of the burden of understanding how the data on the wire is represented.

The virtual XML document the transformer uses as input is created by using the Artix contract to map the raw data from the input port into a DOM facade. The mapping is done as follows:

- If the message is defined using the doc-literal styles, the transformer uses the message part's schema definition to create a representation of the message.
- If the message is not defined using the doc-literal style, the transformer does the following to build an XML representation of the message:
 - 1. the name of the message's root element is the QName of the message element referred to by the operation's input element.
 - 2. Each part element in the input message is placed in an element derived from the name attribute of the part element.
 - 3. If the part is of a complex type, or an element of a complex type, the type's elements appear inside of the element containing the part.

For example, if you had a service defined by the WSDL fragment in Example 105 on page 257 and the transformer implemented the operation configure the XML document would be constructed using the message oldClientInput, which is the input message.

Example 105. WSDL Fragment for Transformer

```
</complexType>
</types>
. . .
<message name="original">
 <part name="vehicle" type="xsd1:vehicleType"/>
 <part name="name" type="xsd:string"/>
</message>
<message name="transformed">
 <part name="vehicle" type="xsd:string"/>
 <part name="firstName" type="xsd:string"/>
 <part name="lastName" type="xsd:string"/>
</message>
<portType name="parkingLotMeter">
 <operation name="configure">
   <input name="oldClientInput" message="tns:original"/>
   <output name="updatedInput" message="tns:transformed"/>
 </operation>
</portType>
```

When the message is reconstructed, the transformer uses the input message's name, given in the input element, as the name of the root element of the XML document. It then uses the message parts and the schema types to recreate the data as an XML message. So if the transformer was using the contract defined in Example 105 on page 257 an input message processed by the transformer could look like Example 106 on page 258.

Example 106. Transformer Input Message

Outbound message

The results from the transformer goes through the reverse of the process that turns the input message into a virtual XML document. The transformer uses the output message definition from the Artix contract to place the result message back onto the wire in the proper payload format. If the result message is not properly formed this attempt will fail, so you must be careful when writing your XSLT script to ensure that the results match the expected format.

When the result message is deconstructed, the transformer expects the following:

- If the output message is defined using the doc-literal style, the message must match the schema defining the message's part.
- If the output message is not defined using the doc-literal style, then the following must be true:
 - The name of the message's root element is the QName of the message element referred to by the output element in the contract.
 - There are the same number of elements in the result as there are part elements in the output message definition.
 - The elements in the result are based on the name attributes of the part elements in the output message definition.
 - The data contained in the element representing the output message's
 part elements matched the XML Schema definitions in the contract.

For example, a result message for the configure operation defined in Example 105 on page 257 would look like Example 107 on page 259.

Example 107. Transformer Output Message

Using element names

You can configure the transformer to use the element name of the message parts instead of the value of the part element's name attribute. For more information see Configuring and Deploying Artix Solutions, C++ Runtime [../../deploy/cpp/index.htm].

Writing XSLT Scripts

Overview

XML Stylesheet Language Transformations(XSLT) is a language used to describe the transformation of XML documents. The current W3C standard for XSLT is 1.0 and can be read at the W3C web site (http://www.w3.org/TR/xslt). XSLT documents, called scripts, are well-formed XML documents that describe how a source XML document is transformed into a resulting XML document. It can be used to perform tasks as simple as splitting a name entry into first and last name entries and as complex as validating that a complex XML document matches the expectations of an interface described in a WSDL document.

Procedure

Writing an XSLT script can be done in a number of ways and using a number of tools. The steps given here assume that you are writing fairly simple scripts using a text editor.

To write a XSLT script do the following:

- 1. Create an XML stylesheet with the required xsl:transform element.
- Determine which elements in your source message need to be processed and create xsd:template elements for each of them.
- 3. For each element that has a matching template element, define how you want the element processed to produce a new output document.
- 4. If child elements need to be processed as part of processing a parent element, define a template for the child element and apply it as part of the parent element's template using xsd:apply-templates.

Elements of an XSLT Script

Overview

An XSLT script is essentially an XML stylesheet containing a special set of elements that instruct an XSLT engine in the processing of other XML documents. An XSLT script must be defined in an xsl:transform element or an xsl:stylesheet element. In addition, it needs at least one valid top-level element to define the transformation.

The transform element

The xsl:transform element denotes that the document is an XML stylesheet. The xsl:stylesheet element can be used in place of the xsl:transform element. They are equivalent.

When creating an XSLT script you must set the version attribute to 1.0 to inform the transformer what version of XSLT you are using. In addition, you must provide an XML namespace shortcut for the XSLT namespace in the xsl:transform element. Example 108 on page 261 shows a valid xsl:transform element for an XSLT script.

Example 108. XSLT Script Stylesheet Element

Top-level elements

While all that is needed to make an XML document a valid XSLT script is the xsl:transform element, the xsl:transform element does not provide any instructions for processing data. The data processing instructions in an XSLT script are provided by a number of top-level XSLT elements. These element's include:

- xsl:import
- xsl:include
- xsl:strip-space
- xsl:preserve-space

- xsl:output
- xsl:key
- xsl:decimal-format
- xsl:namespace-alias
- xsl:attribute-set
- xsl:variable
- xsl:param
- xsl:template

An XSLT script can have any number and combination of top-level elements. Other than xsl:import, which must occur before any other elements, the top-level elements can be used in any order. However, be aware that the order determines the order in which processing steps happen.

Example 109 on page 262 shows a simple XSLT script that transforms SSN elements into acctnum elements.

Example 109. Simple XSLT Script

Using this XSLT script the transformer would change a message that contained <SSN>012457890</SSN> into a message that contained <acctNum>012457890</acctNum>.

Example

XSLT Templates

Overview

XSLT processors use templates to determine the elements on which to apply a set of transformations. Documents are processed from the top element through their structure to determine if elements match a defined template. If a match is found, the rules specified by the template are applied.

To write a template in XSLT you need to do the following:

- 1. Create an xsl:template element.
- 2. Provide the path to the source element it processes.
- 3. Write the processing rules.

xsl:template elements

Templates are defined using xsl:template elements. These elements take one required attribute, match, which specifies the source element that triggers the rules. In addition, you can use the name attribute to give the template a unique identifier for referencing it elsewhere in the contract.

Specifying the source elements

You specify the elements of the source document to which template rules are matched using the match attribute of the xsl:template element. The source elements are specified using the syntax specified by the XPath specification (http://www.w3.org/TR/xpath). The source element address looks very similar to a file path where slash(/) specifies the root element and child elements are listed in top down order separated by a slash(/). For example to specify the surname element of the XML document shown in

Example 110 on page 263, you would specify it as /name/surname.

Example 110. Sample XML Document

```
<name>
  <firstname>
   Joe
  </firstname>
  <surname>
  Friday
```

```
</surname>
<name>
```

Template matching order

XSLT processors start processing with the <xsl:template match="/"> element if it is present. All of the processing directives for this template act on the top-level elements of the source document. For example, given the XML document shown in Example 110 on page 263 any processing rules specified in <xsl:template match="/"> would apply to the name element. In addition, specifying a template for the root element(/) forces you to make all your source element paths explicit from the root element. The XSLT script shown in Example 111 on page 264 generates the string Friday when run on Example 110 on page 263.

Example 111. XSLT Script with Root Element Template

```
<xsl:transform version = '1.0'
    xmlns:xsl='http://www.w3.org/1999/XSL/Transform'>
    <xsl:template match="/">
        <xsl:value-of select="/name/surname"/>
        </xsl:template>
    </xsl:transform>
```

You do not need to specify a template for the root element of the source document in an XSLT script. When you omit the root element's template the processor treats all template paths as though they originated from the source documents top level element. The XSLT script in Example 112 on page 264 generates the same output as the script in Example 111 on page 264.

Example 112. XSLT Script without Root Element Template

```
<xsl:transform version = '1.0'
    xmlns:xsl='http://www.w3.org/1999/XSL/Transform'>
    <xsl:template match="surname">
        <xsl:value-of select="."/>
        </xsl:template>
</xsl:transform>
```

Template rules

The contents of an xsl:template element define how the source document is processed to produce an output document. You can use a combination of XSLT elements, HTML, and text to define the processing rules. Any plain text and HTML that are used in the processing rules are placed directly into the output document. For example, if you wanted to generate an HTML document

from an XML document you would use an XSLT script that included HTML tags as part of its processing rules. The script in Example 113 on page 265 takes an XML document with a title element and a subTitle element and produces an HTML document where the contents of title are displayed using the <h1> style and the contents of subTitle are displayed using the <h2> style.

Example 113. XSLT Template with HTML

Applying templates to child elements

You can instruct the XSLT processor to apply any templates defined in the script to the children of the element being processed using an xsl:apply-templates element as one of the rules in a template. xsl:apply-templates instructs the XSLT processor to treat the current element as a root element and run the templates in the script against it.

For example you could rewrite Example 113 on page 265 as shown in Example 114 on page 265 using xsl:apply-templates and defining a template for the title and subTitle elements.

Example 114. XSLT Template Using apply-templates

```
<h2>
     <xsl:value-of select="."/>
     </h2>
     </xsl:template>
</xsl:transform>
```

You can use the optional select attribute to limit the child elements to which the templates are applied. select takes an XPath value and operates in the same manner as the match attribute of xsl:template.

Example

For example, if your ordering system produced bills that looked similar to the XML document in Example 115 on page 266, you could use an XSLT script to reformat the bill for a system that required the customer's name in a single element, name, and the city and state to be in a comma-separated field, city.

Example 115. Bill XML Document

```
<widgetBill>
 <customer>
   <firstName>
     Joe
   </firstName>
   <lastName>
     Cool
   </lastName>
 </customer>
 <address>
   <street>
     123 Main Street
   </street>
   <city>
     Hot Coffee
   </city>
   <state>
     MS
   </state>
   <zipCode>
      3942
   </zipCode>
 </address>
 <amtDue>
   123.50
 </amtDue>
</widgetBill>
```

The XSLT script shown in Example 116 on page 267 would result in the desired transformation.

Example 116. XSLT Script for widgetBill

```
<xsl:transform version = '1.0'</pre>
    xmlns:xsl='http://www.w3.org/1999/XSL/Transform'>
0 <xsl:template match="widgetBill">
   <xsl:element name="widgetBill">
     <xsl:apply-templates/>
   </xsl:element>
 </xsl:template>
 <xsl:template match="customer">
   <xsl:element name="name">
     <xsl:value-of select="concat(//firstName,' ',//lastName)"/>
   </xsl:element>
 </xsl:template>
 <xsl:template match="address">
     <xsl:element name="address">
     <xsl:copy-of select="//street"/>
     <xsl:element name="city">
       <xsl:value-of select="concat(//city,', ',//state)"/>
     </xsl:element>
     <xsl:copy-of select="//zipCode"/>
   </xsl:element>
 </xsl:template>
4 <xsl:template match="amtDue">
   <xsl:copy-of select="."/>
 </xsl:template>
</xsl:transform>
```

The script does the following:

- Creates an element, widgetBill, in the output document and places the results of the other templates as its children.
- Creates an element, name, and sets its value to the result of the concatenation.
- Creates an element, address, and sets its value to the results of the rules. address will contain a copy of the street element from the source document, a new element, city, that is a concatenation, and a copy of the zipcode element from the source document.
- Copy the amtDue element from the source document into the output document.

Processing the document in Example 115 on page 266 with this XSLT script would result in the XML document shown in Example 117 on page 268.

Example 117. Processed Bill XML Document

```
<widgetBill>
 <customer>
   Joe Cool
 </customer>
  <address>
   <street>
     123 Main Street
   </street>
   <city>
    Hot Coffee, MS
   </city>
   <zipCode>
     3942
   </zipCode>
  </address>
 <amtDue>
   123.50
 </amtDue>
</widgetBill>
```

Common XSLT Functions

Overview

XSLT provides a range of capabilities in processing XML documents. These include conditional statements, looping, creating variables, and sorting. However, there are a few common functions that are used to generate output documents. These include:

- xsl:value-of
- xsl:copy-of
- xsl:element

xsl:value-of

xsl:value-of creates a text node in the ouput document. It has a required select attribute that specifies the text to be inserted into the output document.

The value of select is evaluated as an expression describing the data to insert. It can contain any of the XSLT string functions, such as <code>concat()</code>, or an XSLT axis describing an element in the source document.

Once the select expression is evaluated the result is placed in the output document.

xsl:copy-of

xsl:copy-of copies data from the source document into the output document. It has a required select. The value of select is an expression describing the elements to be copied.

When the result of evaluating the expression is a tree fragment, the complete fragment is copied into the output document. When the result is an element, the element, its attributes, its namespaces, and its children are copied into the output document. When the result is neither an element nor a result tree fragment, the result is converted to a string and then inserted into the output document.

xsl:element

xsl:element creates an element in the output document. It takes a required name attribute that specifies the name of the element that is created. In

addtion, you can specify a namespace for the element using the optional namespace attribute.

Using Codeset Conversion

Some bindings do not natively support codeset conversion. Artix provides WSDL extensions and a plug-in that add codeset conversion to these bindings.

Overview

While many of the bindings supported by Artix provide a means for handling codeset conversion, some do not. It is also possible that any custom bindings you developed do not support codeset conversion. To allow bindings that do not natively support codeset conversion to participate in environments where more than one codeset is used, Artix provides an i18n message-level interceptor that will perform codeset conversion on the message buffer before it is placed on the wire.

The i18n interceptor can be configured by defining the codeset conversion in your endpoint's Artix contract using an Artix port extensor. You can also configure the i18n interceptor programmatically using the context mechanism. The programmatic settings will override any settings described in the contract. For more information on using the context mechanism see the appropriate development guide for your development environment.

Configuring Artix to use the i18n interceptor

Before your application can use the generic i18n interceptor for code conversion you must configure the Artix bus to load the required plug-ins and add the interceptor to the appropriate message interceptor lists. To configure your application to use the i18n interceptor do the following:

- If your application includes a client that needs to use codeset conversion, add i18n-context:I18nInterceptorFactory to the binding:artix:client_message_interceptor_list variable for your application.
- If your application includes a service that needs to use codeset conversion, add i18n-context:I18nInterceptorFactory to the binding:artix:server_message_interceptor_list variable for your application.

For more information on configuring Artix see Configuring and Deploying Artix Solutions, C++ Runtime [../../deploy/cpp/index.htm].

Describing the codeset conversions in the contract

You define the codeset conversions performed by the i18n interceptor in the port element defining an endpoint. There are two extensors used to define

the codeset conversions. One, i18n-context:server, is for service providers and the other, i18n-context:client, is for clients. They both provide settings for how both incoming messages and outgoing messages are to be encoded. These extensions are defined in the namespace http://schemas.iona.com/bus/i18n/context.

To define the codeset conversions performed by the i18n interceptor do the following:

1. Add the following line to the definitions element of your contract.

```
xmlns:i18n-context="http://schemas.iona.com/bus/i18n/con
text"
```

2. If your application provides a service that requires codeset conversion add a i18n-context:server element to the port definition of the service endpoint.

Table 39 on page 272 shows the attributes for the i18n-context:server element. These attributes define how message codesets are converted.

Table 39. Attributes for the i18n-context:server Element

Attribute	Description
LocalCodeSet	Specifies the server's native codeset. The default is the codeset specified by the local system's locale setting.
OutboundCodeSet	Specifies the codeset into which replies are converted. The default is the codeset specified in InboundCodeSet.
InboundCodeSet	Specifies the codeset into which requests are converted. The default is the codeset specified in LocalCodeSet.

3. If your application includes a client that requires codeset conversion add an i18n-context:client element to the port definition of the service endpoint.

Table 40 on page 273 describes the attributes used by the i18n-context:client element for defining how message codesets are converted.

Table 40. Attributes for the i18n-context:client Element

Attribute	Description
LocalCodeSet	Specifies the server's native codeset. Default is the codeset specified by the local system's locale setting.
OutboundCodeSet	Specifies the codeset into which requests are converted. The default is the codeset specified in LocalCodeSet.
InboundCodeSet	Specifies the codeset into which replies are converted. The default is the codeset specified in OutboundCodeSet.

Example

The contract fragment in Example 118 on page 273 shows a port definition for an endpoint that defines a server/client pair. The server uses UTF-8 as its local codeset and the client uses ISO-8859-1 as its local codeset.

Example 118. Specifying Codeset Conversion

Using the endpoint definition above, the client will convert its requests into UTF-8 before sending them to the server. The server will convert its replies into ISO-8859-1 before sending them to the client. The client's inbound

codeset is set to ISO-8859-1 because if left unset the value would have defaulted to UTF-8. The client would then perform an extra conversion.

Index FilenameFactoryPropertyMetaData, 203 name, 203 readOnly, 203 Α valueSet, 203 ActiveMQ, 182 fixed:binding, 70 address specification encoding, 71 CORBA, 242 justification, 71 IIOP, 183 padHexCode, 71 fixed:body, 71 В justification, 72 bindings padHexCode, 72 CORBA, 236 fixed:choice fixedrecord length, 69 discriminatorName, 77 FML field tables, 56 fixed:enumeration, 76 fixedValue, 76 SOAP with Attachments, 46 tagged, 87 value, 76 fixed:field, 73 TibrvMsg, 106 XML, 63 bindingOnly, 73 fixedValue, 75 format, 74 C iustification, 75 configuring IIOP, 184 size, 73 corba:address, 242 fixed:operation, 71 corba:binding, 236 discriminator, 71 bases, 236 fixed:sequence, 80 repositoryID, 236 counterName, 80 corba:operation, 236 occurs, 80 name, 236 FTP Transport corba:para client filename factory, 192 name, 237 reply lifecycle policy, 194 corba:param, 236 request lifecycle policy, 198 idltype, 237 server filename factory, 196 mode, 237 ftp:port corba:policy, 243 connectMode, 189 persistent, 243 host, 188 poaname, 243 port, 188 serviceid, 243 replyLocation, 189 corba:raises, 237 requestLocation, 189 exception, 237 scanInterval, 189 corba:return, 237 ftp:properties, 189, 201 idltype, 237 ftp:property, 189, 201 name, 237 name, 189, 201 corba:typemap, 234

F

value, 189, 201	JMS, 171
FTPProperties, 202	jms:address, 172
getExtensors(), 202	connectionPassword attribute, 172
FTPProperty, 202	connectionUserName attribute, 172
ftrp:port, 188	destinationStyle attribute, 172
	jmsDestinationName attribute, 172
Н	jmsReplyDestinationName attribute, 172
http-conf:client, 157	jndiConnectionFactory attribute, 172
CacheControl, 165	jndiDestinationName attribute, 172
Connection, 162	jndiReplyDestinationName attribute, 172
Password, 160	jms:client, 176
SendTimeout, 158	messageType attribute, 176
http-conf:client:client	jms:JMSNamingProperties
UserName, 160	name attribute, 172
http-conf:server, 157	value attribute, 172
CacheControl, 164	jms:JMSNamingProperty, 172
HonorKeepAlive, 162	jms:server, 177
SendTimeout, 158	durableSubscriberName, 177
http:address, 151	messageSelector, 177
location, 151	transactional, 177
http:conf:client, 160	useMessageIDAsCorrelationID, 177
	JNDI, 171
1	М
i18n-context:client, 271	
InboundCodeSet, 273	mime:content, 46
LocalCodeSet, 273	part, 47
OutboundCodeSet, 273	type, 47
i18n-context:server, 271	mime:multipartRelated, 45
InboundCodeSet, 272	mime:part, 45, 46
LocalCodeSet, 272	name attribute, 46
OutboundCodeSet, 272	mq:client, 206
iiop:address, 183	AliasQueueName, 215
iiop:payload, 184	Format, 217
iiop:policy, 184	Server_Client, 213
persistent, 185	mq:server, 206
poaname, 184	Format, 217
serviceid, 185	Server_Client, 213 MTOM, 49
IOR specification, 183, 242	consumer
	configuration, 54
J	
	comparation, or
Java Messaging System, 171	
Java Messaging System, 171 Java Naming and Directory Interface, 171	P passthru:binding, 142

plugins:ftp:policy:client:filenameFactory, 195	tagged:sequence, 91
plugins:ftp:policy:client:replyFileLifecycle, 195	tibrv:array, 117
plugins:ftp:policy:server:filenameFactory, 199	tibrv:binding, 107
plugins:ftp:policy:server:requestFileLifecycle, 199	stringAsOpaque, 107
	stringEncoding, 107
R	tibrv:context, 138
	tibrv:field, 136
rmi:address, 100	tibrv:input, 108
url, 100	tibrv:msg, 136
rmi:class, 100	tibrv:operation, 108
name, 100	tibrv:output, 109
	messageNameFieldPath, 109
S	messageNameFieldValue, 109
SOAP Message Transmission Optimization Mechanism,	stringAsOpaque, 109
49	stringEncoding, 109
soap12:body	tibrv:port, 219
parts, 40	serverSubject, 219
soap12:header, 39	tuxed:operation, 61
encodingStyle, 40	tuxedo:binding, 60
message, 39	tuxedo:field, 60
namespace, 40	id, 60
part, 39	name, 60
use, 39	tuxedo:fieldTable, 60
soap:address, 150	tuxedo:input, 225
location, 150	operation, 225
soap:body soap:	tuxedo:server, 225
parts, 29	tuxedo:service, 225
soap:header, 29	name, 225
encodingStyle, 29	, 220
message, 29	W
namespace, 29	
part, 29	WebSphere MQ
use, 29	Format
specifying POA policies, 184, 243	working with mainframes, 218
	WSDL
T	port element, 147
	binding attribute, 147
tagged:binding, 88	service element, 147
tagged:body, 90	name attribute, 147
tagged:case, 93	WSDL:binding element, 23
tagged:choice, 93	name attribute, 23
tagged:enumeration, 91	wsdltocorba
tagged:field, 90	adding a CORBA binding, 234
tagged:operation, 89	generating IDL, 246

```
wsdltoservice
  adding a CORBA endpoint, 243
  adding a JMS endpoint, 179
  adding a TIB/RV endpoint, 219
  adding a tuxedo endpoint, 225
  adding a WebSphere MQ endpoint, 206
  adding an HTTP endpoint, 151
  adding an IIOP service, 185
wsdltosoap, 26, 36
wsoap12:address, 150
  location, 150
X
xformat:binding, 63
  rootNode, 63
xformat:body, 64
  rootNode, 64
XML Stylesheet Language Transformations, 260
XPath, 263
xsl:apply-template
  select, 266
xsl:apply-templates, 265
xsl:copy-of, 269
  select, 269
xsl:element, 269
  name, 269
  namespace, 269
xsl:stylesheet, 261
xsl:template, 263
  match, 263
xsl:transform, 261
xsl:value-of, 269
  select, 269
```

XSLT, 260