
Micro Focus Security ArcSight Logger

Software Version: 7.0

Administrator's Guide

Document Release Date: December, 2019

Software Release Date: December, 2019



Legal Notices

Micro Focus
The Lawn
22-30 Old Bath Road
Newbury, Berkshire RG14 1QN
UK

<https://www.microfocus.com>

Copyright Notice

© Copyright 2019 Micro Focus or one of its affiliates

Confidential computer software. Valid license from Micro Focus required for possession, use or copying. The information contained herein is subject to change without notice.

The only warranties for Micro Focus products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. Micro Focus shall not be liable for technical or editorial errors or omissions contained herein.

No portion of this product's documentation may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying, recording, or information storage and retrieval systems, for any purpose other than the purchaser's internal use, without the express written permission of Micro Focus.

Notwithstanding anything to the contrary in your license agreement for Micro Focus ArcSight software, you may reverse engineer and modify certain open source components of the software in accordance with the license terms for those particular components. See below for the applicable terms.

US Governmental Rights. For purposes of your license to Micro Focus ArcSight software, "commercial computer software" is defined at FAR 2.101. If acquired by or on behalf of a civilian agency, the US Government acquires this commercial computer software and/or commercial computer software documentation and other technical data subject to the terms of the Agreement as specified in 48 C.F.R. 12.212 (Computer Software) and 12.211 (Technical Data) of the Federal Acquisition Regulation ("FAR") and its successors. If acquired by or on behalf of any agency within the Department of Defense ("DOD"), the US Government acquires this commercial computer software and/or commercial computer software documentation subject to the terms of the Agreement as specified in 48 C.F.R. 227.7202-3 of the DOD FAR Supplement ("DFARS") and its successors. This US Government Rights Section 18.11 is in lieu of, and supersedes, any other FAR, DFARS, or other clause or provision that addresses government rights in computer software or technical data.

Trademark Notices

Adobe™ is a trademark of Adobe Systems Incorporated.

Microsoft® and Windows® are US registered trademarks of Microsoft Corporation.

UNIX® is a registered trademark of The Open Group.

Documentation Updates

The title page of this document contains the following identifying information:

- Software Version number
- Document Release Date, which changes each time the document is updated
- Software Release Date, which indicates the release date of this version of the software

To check for recent updates or to verify that you are using the most recent edition of a document, go to:

[ArcSight Product Documentation on the Micro Focus Security Community](#)

Support

Contact Information

| | |
|---------------------------------------|---|
| Phone | A list of phone numbers is available on the Technical Support Page: https://softwaresupport.softwaregrp.com/support-contact-information |
| Support Web Site | https://softwaresupport.softwaregrp.com/ |
| ArcSight Product Documentation | https://community.softwaregrp.com/t5/ArcSight-Product-Documentation/ct-p/productdocs |

About this PDF Version of Online Help

This document is a PDF version of the online help. This PDF file is provided so you can easily print multiple topics from the help information or read the online help in PDF format. Because this content was originally created to be viewed as online help in a web browser, some topics may not be formatted properly. Some interactive topics may not be present in this PDF version. Those topics can be successfully printed from within the online help.

Document Revision History

The title page of this document contains the following identifying information:

- Software Version number, which indicates the software version.
- Document Release Date, which changes each time the document is updated.

To check for recent updates or to verify that you are using the most recent edition of a document, go to [ArcSight Product Documentation Community on the Micro Focus Security Community](#).

Document Changes

| Date | Product Version | Description |
|------|-----------------|-------------|
| | | |
| | | |
| | | |
| | | |

Contents

| | |
|--|----|
| Chapter 1: Overview | 24 |
| Introduction to Logger | 24 |
| Logger Events | 25 |
| Logger Features | 25 |
| Storage Configuration | 26 |
| Receiver Configuration | 26 |
| Analyzing Events | 27 |
| Grouping Events | 28 |
| Exporting Events | 28 |
| Forwarder Configuration | 29 |
| User Management | 29 |
| Other Setup and Maintenance | 29 |
| Deployment Scenarios | 30 |
| Setting up Search Heads for Faster Peer Searches | 32 |
| Sending IPv6 Data to Logger | 32 |
| Centralized Management | 32 |
| Running Logger on Encrypted Appliances | 33 |
| Connecting to Logger | 33 |
| Navigating the User Interface | 34 |
| Menus, Take Me To, and Bar Gauges | 35 |
| Take Me To Navigation Box | 35 |
| Bar Gauges | 36 |
| Server Clock, Current User, and Options Dropdown | 36 |
| Logger Options | 36 |
| Customizing the Maximum EPS | 37 |
| Customizing the Logo | 37 |
| Customizing the Start Page | 38 |
| Logger User / Roles Report | 39 |
| Changing the Display Theme | 40 |
| Help, About, and Logout | 40 |
| Summary | 41 |
| Summary Dashboard Panels | 42 |
| The Effect of Search Group Filters on the Summary Page | 43 |

| | |
|--|----|
| Chapter 2: Dashboards | 44 |
| Out-of-Box Dashboards | 44 |
| Managing Out-Of-Box Dashboards | 46 |
| The Monitor Dashboard | 46 |
| Monitor Dashboard Summary Panel | 47 |
| Monitor Dashboard Receivers Panel | 48 |
| Monitor Dashboard Platform Panel | 49 |
| Monitor Dashboard Network Panel | 49 |
| Monitor Dashboard Logger Panel | 50 |
| Monitor Dashboard Forwarders Panel | 51 |
| Monitor Dashboard Storage Panel | 51 |
| The System Overview Dashboard | 52 |
| The Intrusion and Configuration Events Dashboard | 53 |
| The Login and Connection Activity Dashboard | 53 |
| The Event Count Dashboard | 54 |
| Malware Overview Dashboard | 55 |
| The Attacks and Suspicious Activity Dashboard | 56 |
| Operating System Errors and Warnings Dashboard | 57 |
| The Vulnerability Overview Dashboard | 58 |
| The Insecure Services Dashboard | 59 |
| The DGA Overview Dashboard | 60 |
| The MITRE Att&ck Overview Dashboard | 61 |
| The MITRE Att&ck Events Statistics Dashboard | 62 |
| Custom Dashboards | 63 |
| Creating and Managing Custom Dashboards | 64 |
| Adding a Custom Dashboard | 65 |
| Editing a Custom Dashboard | 65 |
| Deleting a Custom Dashboard | 66 |
| Adding and Managing Panels in a Dashboard | 66 |
| Adding a Panel to a Dashboard | 66 |
| Editing a Dashboard Panel | 68 |
| Deleting a Dashboard Panel | 69 |
| Changing the Layout of a Dashboard | 69 |
| Setting a Default Dashboard | 69 |
| Chapter 3: Searching and Analyzing Events | 71 |
| The Process of Searching Events | 71 |
| Understanding Classic Search Field Colors | 73 |
| Search page | 74 |

| | |
|---|-----|
| Custom Fieldsets | 75 |
| Saved Searches/ Filters | 75 |
| Page Views | 76 |
| Charts | 77 |
| Elements of a Search Query | 78 |
| Query Expressions | 78 |
| Indexed Search Portion of a Query | 79 |
| Keyword Search (Full-text Search) | 79 |
| Field-Based Search | 80 |
| Field Based Search Operators | 81 |
| Field-Based Search Expression Guidelines | 83 |
| Limitations on Field-Based Search Operators | 85 |
| Search Operator Portion of a Query | 85 |
| Search based on Event Time | 85 |
| Time Range | 86 |
| Time Stamps in Logger | 88 |
| Fieldsets | 89 |
| Predefined Fieldsets | 89 |
| "User-Defined Fields" Fieldset | 90 |
| "Raw Event" Fieldset | 90 |
| Generating Search Results | 90 |
| Custom Fieldsets | 90 |
| Constraints | 91 |
| Syntax Reference for Query Expressions | 93 |
| Using the Advanced Search Builder | 98 |
| Accessing the Advanced Search Builder | 98 |
| Nested Conditions | 100 |
| Alternate Views for Query Building in Search Builder | 101 |
| Search Analyzer | 102 |
| Performance Optimizations for Indexed Fields in Queries | 102 |
| Regex Helper Tool | 103 |
| Search Helper | 104 |
| Autocomplete Search | 105 |
| Opening Filters and Saved Searches via Autocomplete | 106 |
| Search History and Search Operator History | 107 |
| Examples, Usage, Suggested Next Operators, and Help | 107 |
| Searching for Events | 108 |
| Running a Search | 108 |
| About Building Search Queries | 111 |

| | |
|---|-----|
| Search Hit Limits | 112 |
| Concurrent Searches | 112 |
| Using the Active Search List | 113 |
| Running Concurrent Searches | 114 |
| Searching Peers (Distributed Search) | 115 |
| Tuning Search Performance | 117 |
| Searching for Rare Field Values | 117 |
| Using Super-Indexed Fields to Increase Search Speed | 117 |
| Searching for IPv6 Addresses | 120 |
| Using the INSUBNET Operator to Search for IPv6 Addresses | 122 |
| The Search Results Display | 122 |
| Adjusting the Displayed Search Results | 123 |
| Canceling a Search in Progress | 124 |
| The Histogram | 124 |
| Displaying the Histogram | 125 |
| Mouse-Over | 125 |
| Histogram Drill Down | 126 |
| The Search Results Table | 126 |
| Additional Fields in the Search Results | 126 |
| User-Defined Fields | 126 |
| System-Defined Fields | 127 |
| Refining a Search from the Search Results Table | 127 |
| Changing the Displayed Search Results Using Field Sets | 128 |
| Viewing Raw Events | 128 |
| Multi-line Data Display | 129 |
| Auto Refresh Search Results | 129 |
| Chart Drill Down | 129 |
| The Field Summary Panel | 130 |
| Displaying the Field Summary Panel | 131 |
| Selected Fields List | 131 |
| Field Summary Drill Down | 132 |
| Discovering Fields in Raw Event Data | 132 |
| Refining and Charting a Search from Field Summary | 133 |
| Saving the Search Results | 134 |
| Example of a Quick Report in PDF Format (Search Results Export) | 135 |
| Exporting Search Results | 135 |
| Scheduling an Export Operation | 137 |
| Saving Queries, Creating Saved Searches and Saved Filters. | 138 |
| System Filters/Predefined Filters | 140 |
| Searching with Saved Queries | 144 |

| | |
|---|---------|
| Scheduling Date and Time Options | 145 |
| Enriching Logger Data Through Static Correlation | 146 |
| Indexing | 146 |
| Full-Text Indexing (Keyword Indexing) | 147 |
| Field-Based Indexing | 147 |
| Superindexing | 149 |
| Viewing Alerts | 149 |
| Live Event Viewer | 150 |
| Using Global ID | 154 |
| Chapter 4: Reporting | 156 |
| The Reports User Interface | 156 |
| Multitasking with Tabs | 156 |
| The Reports Menu | 157 |
| The Reports Home Page | 158 |
| Accessing the Reports Home Page | 158 |
| Using the Right Tool for the Job | 159 |
| Design Tools: New Reports and Report Objects | 160 |
| Frequently-Asked Questions | 160 |
| How do Smart Reports differ from Ad hoc and Studio Reports? | 160 |
| Which Reports Open Where? | 161 |
| How Does the Smart Viewer Differ from the Ad hoc Viewer? | 162 |
| How do Smart, Powerview, and Ad hoc Design Tools Differ? | 163 |
| Administrative Prerequisites | 163 |
| Assigning Access Rights | 164 |
| What Access Rights are Necessary? | 164 |
| Adjusting Timeout Values for Long-Running Reports | 164 |
| Finding and Managing Reports | 165 |
| Reports Explorer | 165 |
| What are Report Objects? | 166 |
| Working with Explorer | 166 |
| Explorer Favorites | 168 |
| Explorer Options and Context Menus | 169 |
| Recent Reports | 171 |
| Running a Recent Report | 171 |
| Re-running a Recent Report | 172 |
| Published Reports | 172 |
| Working with Published Reports | 173 |
| Other Reports | 175 |

| | |
|---|-----|
| Filtering the Other Reports List | 176 |
| Scheduled Reports | 177 |
| Scheduling a Report | 178 |
| What is Smart Export? | 179 |
| Working with Scheduled Reports | 180 |
| Scheduling Report Limitations | 181 |
| Running Reports | 183 |
| Understanding Run Report Options | 183 |
| Best Practices for Running Reports | 184 |
| Running a Report | 184 |
| Running, Viewing, and Publishing Reports | 185 |
| Running Background Reports | 185 |
| Restrict Long Reports to Run in the Background | 186 |
| Running Distributed Reports | 187 |
| Run-Time Filters, Criteria, and Parameters | 187 |
| Additional Filters | 188 |
| Data Source Report Settings | 189 |
| Select Filter Criteria | 189 |
| Selecting Groups, Devices, and Peers | 190 |
| Viewing Reports | 190 |
| The Ad hoc Report Viewer | 191 |
| Ad hoc Viewer Menu Options | 191 |
| Displaying a Table of Contents for a Grouped Report | 192 |
| The Smart Report Viewer | 193 |
| Smart Viewer Menu Options | 194 |
| Collaborating on Reports | 194 |
| Adding a Comment to a Report | 194 |
| Searching for IPv6 Addresses in Reports | 195 |
| Report Formats for Viewing and Export | 196 |
| About Report Pagination | 197 |
| View Options | 198 |
| Export Options | 200 |
| Publishing Reports | 202 |
| Publishing a Report | 202 |
| Publish Report Options | 203 |
| Working with Published Reports | 204 |
| Exporting and Uploading Reports | 206 |
| Exporting and Saving a Report | 206 |
| Uploading a Report to a Server or FTP Site | 207 |
| Shared Folder Upload Options | 208 |

| | |
|--|-----|
| FTP Upload Options | 209 |
| Emailing a Report | 209 |
| Email Delivery Settings | 210 |
| Designing Custom Reports | 211 |
| Powerview Designer and Classic Report Designer | 211 |
| Working with Logger Report Designers | 212 |
| Create a New Report from an Existing One | 213 |
| The Smart Report Designer | 215 |
| Smart Reports | 217 |
| Creating a New Smart Report | 218 |
| Annotating Smart Report Charts | 218 |
| The Powerview Designer | 219 |
| The Powerview Heading Context Menu | 220 |
| The Powerview Data Context Menu | 221 |
| The Powerview Chart Menu | 222 |
| Creating a Chart for an Ad hoc Report in Powerview | 223 |
| Classic: The Ad hoc Report Designer | 224 |
| Toolbar Buttons | 225 |
| Report Components | 225 |
| Creating a New Classic Report | 226 |
| Creating an IPv6 Report | 227 |
| Private Reports | 228 |
| Customizing Report Elements | 228 |
| Data Source | 228 |
| Fields | 229 |
| Filter | 230 |
| Group | 232 |
| Totals | 233 |
| Sort | 234 |
| Highlight | 234 |
| Matrix | 236 |
| Chart | 237 |
| Assigning Fields | 238 |
| Map | 239 |
| Map Parameters | 240 |
| Geolocation Lookup | 240 |
| Building Dashboards | 244 |
| How do Smart Dashboards differ from Ad hoc Dashboards? | 245 |
| Viewing Dashboards in the Dashboard Viewer | 245 |
| Dashboard Prerequisites | 246 |

| | |
|--|-----|
| What Items Can a Dashboard Include? | 247 |
| Creating a New Smart Dashboard | 248 |
| Dashboard Migration Tool | 249 |
| Designing Queries, Parameters, and Templates | 250 |
| Queries | 250 |
| How Search and Report Queries Differ | 251 |
| Overview of Query Design Elements | 251 |
| Working with Queries | 251 |
| Creating a Copy of an Existing Query | 251 |
| Creating an IPv6 Search Query for Reports | 252 |
| Modifying a Query Object | 253 |
| Deleting a Query Object | 253 |
| Creating Reports from Filters and Saved Searches. | 253 |
| Create a New Query from Smart Designer | 255 |
| Designing a New Query | 256 |
| Working with Steps | 256 |
| The Query Design Process | 257 |
| Steps | 258 |
| Data Source Step | 259 |
| Join Step | 261 |
| Union Step | 261 |
| Filter Step | 262 |
| Sort Step | 262 |
| Formula Fields Step | 262 |
| Dynamic Fields Step | 263 |
| External Task Step | 263 |
| Format Step | 264 |
| Query Object Advanced Properties | 265 |
| Defining Queries on the Designer | 267 |
| SQL Designer | 267 |
| List of Database Objects | 267 |
| Design Tab | 267 |
| Select | 268 |
| Where | 268 |
| Group By | 268 |
| Having | 268 |
| Order By | 269 |
| Edit Tab | 269 |
| Relationship of Edit and Design Tabs | 269 |
| Result Tab | 270 |

| | |
|---|-----|
| Logger Search Reports Designer | 270 |
| Data Science Engine Step at Query Object Level | 271 |
| Predictive Analysis | 272 |
| What if Analysis | 272 |
| Parameters | 273 |
| Parameter Properties | 273 |
| Parameter Object Editor | 274 |
| Creating New Parameters | 275 |
| Setting Parameter Name, Data Type, and Default Values | 275 |
| Default Value for Date Type Parameter | 276 |
| Defining Input Type | 277 |
| Setting Multiple Default Values | 277 |
| Setting up Boolean Parameters | 278 |
| Setting Various Run Time Behaviors | 278 |
| Setting the Data Source List | 279 |
| Setting Multiple Default Values | 279 |
| Modifying a Parameter | 280 |
| Deleting a Parameter | 280 |
| Parameter Value Groups | 281 |
| Configuring Parameter Value Groups | 281 |
| Template Styles | 284 |
| Working with Logger Report Templates | 284 |
| Defining a New Template | 285 |
| Reports Administration | 285 |
| Creating a Reports User Group | 285 |
| Managing Reports of Deleted Users | 286 |
| Report Server Configuration | 286 |
| Report Configuration | 287 |
| Investigate Connection | 288 |
| Report Categories | 289 |
| System-defined Categories | 290 |
| Placing a System-defined Query or Parameter into a Category | 293 |
| Adding a New Category | 294 |
| Deleting a Category | 296 |
| Job Execution Status | 296 |
| Chart | 297 |
| List of Jobs | 297 |
| The Filters area | 298 |
| Filtering the list | 298 |
| Backup and Restore Report Content | 299 |

| | |
|---|-----|
| iPackager Utility | 299 |
| How iPackager Works | 299 |
| iPackager Actions | 300 |
| Selecting Entities | 300 |
| Opening a Configuration File | 300 |
| Selecting Entity Objects | 301 |
| Adding Entity Objects to a Configuration File | 301 |
| Report Category Filters | 301 |
| Deleting Entity Objects from a Configuration File | 302 |
| Modifying Entity Object Properties | 302 |
| Category Properties | 303 |
| Report Properties | 304 |
| Query Properties | 305 |
| Parameter Properties | 306 |
| Template Properties | 306 |
| Building the CAB File | 307 |
| Deploying a Report Bundle | 307 |
| Deleting an iPackager Configuration File | 309 |
| Chapter 5: Configuration | 310 |
| Search | 310 |
| Filters | 311 |
| Search Group Filters | 314 |
| Saved Searches | 315 |
| Scheduled Searches/Alerts | 317 |
| Adding a Scheduled Search or Scheduled Alert | 318 |
| Saved Search Alerts | 323 |
| Creating Saved Search Alerts (Scheduled Alerts) | 323 |
| Saved Search Files | 326 |
| Search Indexes | 326 |
| Guidelines for Field-Based Indexing | 327 |
| Global Search Options | 328 |
| Setting Global Search Options | 328 |
| Search Option Parameters | 329 |
| Managing Fieldsets | 333 |
| Default Fields | 333 |
| Custom Fields | 335 |
| Running Searches | 335 |
| Running Searches List | 336 |
| Lookup Files | 336 |

| | |
|---|-----|
| Creating Lookup Files | 337 |
| Naming Lookup Files | 337 |
| Naming Fields in the Lookup File | 337 |
| Duplicate Values in the Lookup File | 337 |
| Lookup Capacity | 338 |
| Uploading Lookup Files | 338 |
| Managing Uploaded Lookup Files | 340 |
| Import Geolocation Files | 342 |
| Data | 342 |
| Devices | 343 |
| Device Groups | 345 |
| Receivers | 346 |
| Transformation Hub Receivers | 347 |
| Transformation Hub Authentication | 348 |
| Step 1: Generate a CSR on the Logger Side | 348 |
| Step 2: Locate Transformation Hubs Intermediate Certificate and Key | 349 |
| Step 3: Sign the Logger CSR on the Transformation Hub | 349 |
| Step 4: Move the Signed Certificate File to Logger | 349 |
| Step 5: Import the Certificate Chain to the Logger Keystore | 349 |
| Import Transformation Hub RE Certificate | 350 |
| Step 1: Obtain Transformation Hub RE Certificate | 350 |
| Step 2: Set the environment | 350 |
| Step 3: Import the RE Certificate | 351 |
| File Based Receivers | 351 |
| Multi-line Receivers | 352 |
| Folder Follower Receivers | 352 |
| Using Source Types with File Follower Receivers | 353 |
| Working with Receivers | 353 |
| UDP, TCP, CEF UDP, and CEF TCP Receiver Parameters | 356 |
| Transformation Hub Receiver Parameters | 358 |
| File Receiver Parameters | 359 |
| Folder Follower Receiver Parameters | 361 |
| File Transfer Receiver Parameters | 363 |
| SmartMessage Receiver Parameters | 365 |
| Date and Time Specification | 365 |
| Source Types | 367 |
| Working with Source Types | 368 |
| Parsers | 371 |
| Using Parsers with Source Types | 372 |
| Using the Parse Command | 372 |

| | |
|---|-----|
| Working with Parsers | 373 |
| Example: Creating an Extract Parser | 375 |
| Forwarders | 376 |
| Real Time Alerts | 383 |
| Creating Real Time Alerts | 386 |
| Logger Alert Types | 388 |
| Alert Triggers and Notifications | 389 |
| When are Alert events triggered? | 390 |
| Receiving Alert Notifications | 390 |
| Sending Notifications to E-mail Destinations | 391 |
| Setting Up Alert Notifications | 391 |
| Sending Notifications to Syslog and SNMP Destinations | 392 |
| SNMP Destinations | 392 |
| Syslog Destinations | 393 |
| Sending Notifications to ESM Destinations | 394 |
| ESM Destinations | 395 |
| Certificates | 398 |
| Forwarding Log File Events to ESM | 399 |
| Data Validation | 400 |
| SecureData Decryption | 402 |
| Storage | 404 |
| Storage Groups | 405 |
| Storage Rules | 407 |
| Storage Volume | 408 |
| Java Memory Allocation | 410 |
| Event Archives | 410 |
| Archiving Events | 412 |
| Guidelines for Archiving Events | 412 |
| Loading and Unloading Archives | 414 |
| Indexing Archived Events | 415 |
| Daily Archive Settings | 416 |
| Archive Storage Settings | 416 |
| Scheduled Tasks | 417 |
| Scheduled Tasks | 417 |
| Currently Running Tasks | 418 |
| Finished Tasks | 418 |
| Filtering the Task List | 419 |
| Advanced Configuration | 420 |
| Retrieve Logs | 420 |
| Maintenance Operations | 422 |

| | |
|--|-----|
| Required Permissions for Maintenance Mode | 422 |
| Entering and Exiting Maintenance Mode | 423 |
| Defragmenting the Logger Database | 424 |
| Defragmenting a Logger | 425 |
| Freeing Defragmentation Storage Space | 426 |
| Defragmenting Global Summary Persistence | 427 |
| Storage Volume Size Increase | 428 |
| About Increasing Storage Volume Size on a SAN Logger | 429 |
| Adding Storage Groups | 430 |
| Adding Fields to the Schema | 431 |
| Importing Schema Fields from Peers | 433 |
| Maintenance Results | 436 |
| Configuration Backup and Restore | 436 |
| Running a Configuration Backup | 438 |
| Scheduling Reoccurring Backups | 439 |
| Restoring from a Configuration Backup | 440 |
| Content Management | 441 |
| User Rights for Importing Content | 441 |
| Importing Content | 442 |
| User Rights for Exporting Content | 442 |
| Exporting Content | 443 |
| How does EPS license differ from GB per day license? | 444 |
| Standalone License Information | 445 |
| Logger Standalone EPS License | 445 |
| Logger Standalone GB per day License | 447 |
| Managed by ArcMC License Information | 448 |
| GB managed by ArcMC License Usage | 448 |
| EPS managed by ArcMC License Usage | 448 |
| Trial Licenses | 449 |
| Logger Software Installations and Licenses | 449 |
| Peer Nodes | 450 |
| Overview Steps for Configuring Peers | 450 |
| Guidelines for Configuring Peers | 451 |
| Authenticating Peers | 451 |
| Selecting a Peer Authentication Method | 452 |
| Authorizing a Peer | 452 |
| Adding and Deleting Peer Relationships | 452 |
| Adding a Peer | 453 |
| Deleting a Peer | 455 |
| Chapter 6: System Admin | 456 |

| | |
|---|-----|
| System | 457 |
| System Locale | 457 |
| System Reboot | 458 |
| Network | 458 |
| System DNS | 459 |
| Hosts | 459 |
| NICs | 460 |
| Static Routes | 461 |
| Time/NTP | 462 |
| Impact of Daylight Savings Time Change on Logger Operations | 464 |
| SMTP | 465 |
| License & Update | 466 |
| Updating Your Logger License | 466 |
| Upgrading a Logger Appliance | 467 |
| Standalone Logger with an SODP License | 467 |
| Process Status | 469 |
| System Settings | 469 |
| SNMP | 470 |
| SNMP Metrics Supported | 470 |
| Configuration on the Logger Appliance | 471 |
| Configuration on the NMS | 472 |
| SSH Access to the Appliance | 473 |
| Logs | 474 |
| Audit Logs | 474 |
| Audit Forwarding | 475 |
| Storage | 475 |
| Remote File Systems | 475 |
| Managing a Remote File System | 476 |
| SAN | 478 |
| Managing a LUN | 478 |
| Restoring a SAN | 480 |
| Creating Multiple Paths to a LUN | 481 |
| RAID Controller | 483 |
| Security | 483 |
| SSL Server Certificate | 484 |
| Generating a Self-Signed Certificate | 484 |
| Generating a Certificate Signing Request (CSR) | 486 |
| Importing a Certificate | 487 |
| Enabling HTTP Strict Transport Security | 487 |
| SSL Client Authentication | 488 |

| | |
|--|-----|
| Configuring Logger to Support SSL Client Authentication | 489 |
| Uploading Trusted Certificates | 490 |
| Uploading a Certificate Revocation List | 490 |
| FIPS 140-2 | 491 |
| FIPS Compliance | 491 |
| Enabling and Disabling FIPS Mode on Logger | 492 |
| Installing or Updating a SmartConnector to be FIPS-Compliant | 493 |
| Users/Groups | 495 |
| Authentication | 495 |
| Sessions | 495 |
| Local Password | 496 |
| Users Exempted From Password Expiration | 498 |
| Enabling Forgot Password | 498 |
| External Authentication | 500 |
| Local Password Authentication | 501 |
| Client Certificate Authentication | 501 |
| Client Certificate and Local Password Authentication | 502 |
| RADIUS Authentication | 503 |
| LDAP/AD and LDAPS Authentication | 504 |
| Local Password Fallback | 505 |
| Login Banner | 506 |
| User Management | 506 |
| Creating and Activating Users | 507 |
| Adding a User | 507 |
| Editing and Deleting Users | 509 |
| Activating Users | 509 |
| Setting Logger User Permissions | 510 |
| Reset a User's Password | 510 |
| User Groups | 511 |
| Managing User Groups | 512 |
| Creating a New User Group | 512 |
| Editing and Deleting User Groups | 512 |
| Change My Password | 513 |
| Other System Administration Information | 514 |
| Monitoring System Health | 514 |
| System Health Events | 515 |
| Using the Appliance Command Line Interface | 517 |
| Software Logger Command Line Options | 520 |
| Firewall Rules | 522 |
| Configuring the Firewall on Logger Appliance | 522 |

| | |
|---|-----|
| Appendix A: Search Operators | 524 |
| CEF (Deprecated) | 524 |
| chart | 525 |
| dedup | 529 |
| eval | 530 |
| extract | 535 |
| fields | 537 |
| head | 538 |
| keys | 538 |
| lookup | 539 |
| parse | 544 |
| rare | 545 |
| regex | 546 |
| rename | 546 |
| replace | 547 |
| rex | 549 |
| sort | 551 |
| tail | 552 |
| top | 553 |
| transaction | 554 |
| where | 556 |
| Appendix B: Reporting Cheatsheet | 557 |
| Appendix C: Using SmartConnectors to Collect Events | 559 |
| SmartMessage | 559 |
| Configuring a SmartConnector to Send Events to Logger | 560 |
| Configuring SmartConnectors to Send Events to Both Logger and an ArcSight Manager | 560 |
| Configuring SmartConnectors for Failover Destinations | 561 |
| Sending Events from ArcSight ESM to Logger | 561 |
| Appendix D: Using the Rex Operator | 563 |
| Syntax of the rex Operator | 563 |

| | |
|---|-----|
| Understanding the rex Operator Syntax | 563 |
| Ways to Create a rex Expression | 565 |
| Creating a rex Expression Manually | 565 |
| Example rex Expressions | 566 |
| Appendix E: Logger Audit Events | 569 |
| Types of Audit Events | 569 |
| Information in an Audit Event | 569 |
| Platform Events | 570 |
| Application Events | 579 |
| Appendix F: System Health Events | 598 |
| Appendix G: Event Field Name Mappings | 603 |
| Appendix H: Logger Content | 608 |
| Reports | 608 |
| Device Monitoring | 609 |
| Anti-Virus | 609 |
| CrossDevice | 610 |
| Database | 613 |
| Firewall | 613 |
| IDS-IPS | 614 |
| Identity Management | 615 |
| Network | 615 |
| Operating System | 616 |
| VPN | 617 |
| DNS | 618 |
| Foundation | 618 |
| Configuration Monitoring | 619 |
| MITRE Monitoring | 620 |
| Intrusion Monitoring | 621 |
| Attackers | 624 |
| Resource Access | 626 |
| Targets | 627 |
| User Tracking | 629 |
| NetFlow Monitoring | 630 |
| Network Monitoring | 630 |

| | |
|---|-----|
| Vulnerabilities | 631 |
| Logger Administration | 633 |
| SANS Top 5 | 633 |
| 1 - Attempts to Gain Access through Existing Accounts | 633 |
| 2 - Failed File or Resource Access Attempts | 634 |
| 3 - Unauthorized Changes to Users Groups and Services | 635 |
| 4 - Systems Most Vulnerable to Attack | 635 |
| 5 - Suspicious or Unauthorized Network Traffic Patterns | 636 |
| OWASP | 638 |
| A1 - Injections | 638 |
| A2- Broken Authentication | 638 |
| A3- Sensitive Data Exposure | 639 |
| A4- XML External Entities | 639 |
| A5- Broken Access Control | 639 |
| A6- Security Misconfiguration | 640 |
| A7- Cross-Site Scripting | 640 |
| A8- Insecure Deserialization | 640 |
| A9 - Using Components with Known Vulnerabilities | 641 |
| A10 - Insufficient Logging AND Monitoring | 641 |
| Cloud | 641 |
| CSA | 642 |
| Treacherous 12 | 642 |
| Abuse and Nefarious Use of Cloud Services | 642 |
| Account Hijacking | 643 |
| Advanced Persistent Threats | 643 |
| Data Breaches | 643 |
| Data Loss | 643 |
| Denial of Service | 644 |
| Insecure Interfaces and APIs | 644 |
| Insufficient Due Diligence | 644 |
| Insufficient Identity Credential and Access Management | 645 |
| Malicious Insiders | 645 |
| System Vulnerabilities | 645 |
| Vulnerabilities in Shared Technologies | 646 |
| Parameters | 646 |
| IPAddress | 647 |
| categoryObjectParameter | 647 |
| commonlyBlockedPorts | 647 |
| destinationAddress | 648 |
| destinationPort | 648 |

| | |
|---|-----|
| deviceGroupParameter | 648 |
| deviceProduct | 648 |
| deviceSeverityParameter | 649 |
| deviceVendor | 649 |
| dmBandwidthParameter | 649 |
| dmConfigurationParameter | 649 |
| dmLoginParameter | 650 |
| eventNameParameter | 650 |
| resourceTypeParameter | 650 |
| webPorts | 650 |
| zoneParameter | 651 |
| zones | 651 |
| userName Parameter | 651 |
| hostName Parameter | 652 |
| System Filters | 652 |
| Appendix I: Restoring Factory Settings | 658 |
| Before Restoring Your System | 658 |
| Restoring Your System | 658 |
| Restoring LX400 and Earlier Appliance Models | 659 |
| Restoring LX500 or LX600 Appliance Models | 660 |
| Appendix J: Logger Search From ArcSight ESM | 663 |
| Understanding the Integrated Search Functionality | 663 |
| Setup and Configuration | 664 |
| On ESM | 664 |
| On Logger | 665 |
| Supported Search Options | 665 |
| Guidelines | 665 |
| Searching on Logger From ArcSight Console | 666 |
| Send Documentation Feedback | 668 |

Chapter 1: Overview

This document provides information about the administration, configuration and use of ArcSight Logger 7.0. It includes information on storage, receiver, and forwarder configuration; working with events; user management; and setup and maintenance considerations.

| | |
|---------------------------------------|----|
| • Introduction to Logger | 24 |
| • Logger Events | 25 |
| • Logger Features | 25 |
| • Deployment Scenarios | 30 |
| • Connecting to Logger | 33 |
| • Navigating the User Interface | 34 |
| • Help, About, and Logout | 40 |
| • Summary | 41 |

Introduction to Logger

Logger is a log management solution that is optimized for extremely high event throughput, efficient long-term storage, and rapid data analysis. Logger receives and stores events; supports search, retrieval, and reporting; and can optionally forward selected events. Logger compresses raw data, but can always retrieve unmodified data on demand for forensics-quality litigation data.

Logger is available in appliance and software form factors. The appliance-based solution is a hardened, dedicated, enterprise-class system that is optimized for extremely high event throughput, efficient long-term storage, and rapid data analysis. The software-based solution is similar in feature and functionality to the appliance-based solution, however, the software solution enables you to install ArcSight Logger on a supported platform of your choice. The software version is available as a VMware virtual machine, as well as on Amazon Web Service (AWS), and Microsoft Azure cloud computing platforms.

You can have a single Logger or as many as you need. Multiple Loggers can work together to scale up to support extremely high event volume with search queries distributed across all Loggers. Logger can be managed by ArcSight Management Center and that includes license and configuration management.

Note: Where there are no specific differences, all types of Logger are called **Logger** in this document. Where there are differences, the specific type of Logger is indicated.

Logger Events

An **event** consists of a receipt time, an event time, a source (host name or IP address), and a message portion. Logger displays events in a table, with fields that describe the event. The user can look and view the events using the Classic Search (**Analyze > Classic Search**)

The screenshot shows the 'Classic Search' interface. At the top, there is a toolbar with icons for file operations, a search icon, and a settings icon. Below the toolbar, there are three dropdown menus: 'All Fields', 'Logger Receipt Time', and 'Last 10 minutes'. A search input field contains the text 'deviceProduct = Logger'. To the right of the input field are three buttons: 'Go!', 'Advanced', and 'Go to Search'. Below the search input field, there is a message that says 'There are no Active Searches in Memory.' and a button labeled 'Active Searches' with a dropdown arrow.

and Search page (**Analyze > Search**).

The screenshot shows the 'Search' page. At the top, there is a toolbar with icons for file operations, a search icon, and a settings icon. Below the toolbar, there are three dropdown menus: 'All Fields', 'Logger Receipt Time', and 'Last 10 minutes'. A large search input field contains the placeholder text 'Enter search query...'. To the right of the input field is a button labeled 'GO!'.

Logger receives structured data in the form of normalized Common Event Format (CEF) events and unstructured data, such as syslog events. The file-type receivers configured on Logger only parse event time from an event. Although Logger is message-agnostic, it can do more with messages that adhere to the Common Event Format (CEF), an industry standard for the interoperability of event- or log-generating devices.

For more information about CEF, see ArcSight CEF in [Micro Focus Security Community](#).

Logger Features

The following sections provide an overview of key Logger features with links to relevant sections of this guide.

- [Storage Configuration](#)26
- [Receiver Configuration](#)26
- [Analyzing Events](#)27
- [Grouping Events](#)28
- [Exporting Events](#) 28

| | |
|---|----|
| • Forwarder Configuration | 29 |
| • User Management | 29 |
| • Other Setup and Maintenance | 29 |

Storage Configuration

Logger events can be stored either locally on any Logger or remotely on Logger Appliance models that support Storage Area Network (SAN). You can store events using SAN but only using one Logical Unit (LUN). Using a Network File System (NFS) as primary storage for events is not recommended.

The **Logger Appliance** includes onboard storage for events. Some Logger models include RAID 1 or RAID 5 storage systems. (See Logger appliance specifications at [ArcSight Logger](#).)

An NFS or a CIFS system can be used for archiving Logger event data and configuration information such as Saved Searches.


The storage volume (data storage's identifiable unit), either external or local, can be divided into multiple storage groups, each with a separate retention policy. Two storage groups are created when Logger is first configured. Up to 48 storage groups can be added later. For more information on storage strategy, refer to the Logger Installation Guide. For more information on event storage, see ["Storage" on page 404](#).

Receiver Configuration

Logger receives events as Common Event Format (CEF) messages, syslog messages, encrypted SmartMessages, or by reading log files. Traditionally, syslog messages are sent using User Datagram Protocol (UDP), but Logger can receive syslog and CEF messages using the more reliable Transmission Control Protocol (TCP) as well. You can also configure the Logger to read event data or log files from a CIFS host.

Logger can also read events from text log files on remote hosts. Each event must include a timestamp. Logger can be configured to poll remote folders for new files matching a filename pattern. Once the events in the new file have been read, Logger can delete the file, rename it, or simply remember that it has been read. Logger can read remote files on network drives using SCP, SFTP, or FTP protocol, or using a previously-established NFS or CIFS mount or, on some Logger Appliance models, a SAN.

Logger can receive events from SmartConnector, ESM, Transformation Hub, and files.



Logger may also receive events from an ArcSight Manager as CEF-formatted syslog messages. These events are forwarded to Logger through a special software component called an ArcSight Forwarding SmartConnector that converts the events into CEF-formatted syslog messages before sending them to Logger.

- For more information on setting up receivers, see ["Receivers" on page 346](#).
- For more information on setting up SmartConnectors, refer to the Logger Installation Guide.
- For more information on collecting events from ArcSight ESM, refer to the Logger Installation Guide.

Analyzing Events

Events can be searched, yielding a table of events that match a particular query. Queries can be entered manually or automatically created by clicking on terms in the event table. Queries can be based on plain English keywords (full-text search), predefined fields, or specified as regular expressions. Logger supports a flow-based search language that allows you to specify multiple search commands in a pipeline format.

By default, a Logger queries only its primary data store even if peer Loggers are configured. However, you can configure it to distribute a query across peer Loggers of your choice.

Queries can be saved as a filter or as a saved search. Saved filters can be used to select events for forwarding or to filter for the same things later. A Saved Search is used to export selected events or to save results to a file, typically as a scheduled task.

The following topics provide more information about analyzing events:

- ["Searching for Events" on page 108](#)
- ["Saving Queries, Creating Saved Searches and Saved Filters." on page 138](#)
- ["Filters" on page 311](#)
- ["Saved Searches" on page 315](#)
- ["Parsers" on page 371](#)

Grouping Events

The combination of a source IP address and a Logger receiver is called a device. As events are received, devices are automatically created for each IP/receiver pair. Devices can also be created manually.

Devices can be categorized by membership in one or more device groups. While an incoming event belongs to one and only one device, it can be associated with more than one device group.

Storage rules associate a device group with a storage group. Storage rules are ordered by priority, and the first matching rule determines to which storage group an incoming event will be sent.

Device groups, devices, storage groups, and peer Loggers can each be used to filter events using Search Constraints, which can be specified interactively on the Analyze page as well as when creating filters or Saved Searches.

The following topics provide more information about grouping events:

- ["Event Archives" on page 410](#)
- ["Storage Rules" on page 407](#)
- ["Searching Peers \(Distributed Search\)" on page 115](#)

Exporting Events

A Logger Appliance can export events to various sources. Events that match the current query can be exported locally, to an NFS mount, a CIFS mount, as a file or to a SAN, when the appliance supports SANs.

Events from a Software Logger can be exported locally to the Logger (to the `<install_dir>/data/logger` directory) or to the browser from which you connect to the Logger. The `<install_dir>/data/logger` directory can be mounted to an NFS or CIFS.

Events can be exported in Comma-Separated Values (CSV) format for easy processing by external applications or as a PDF file for generating a quick report. A PDF report includes a table of search results and any charts generated for the results. Both raw (unstructured data) and CEF events (structured data) can be included in the PDF exported report.

Events in Common Event Format (CEF) have more columns defined, making the data more useful, but non-CEF events can be exported as well, if desired. The user can control which fields are exported.

Exports can be scheduled to run regularly by creating a Saved Search Job. First, a Saved Search is created, either manually or by saving a query on the Analyze page. A Saved Search can be based on an existing filter. A Saved Search Job combines one or more Saved Searches and a schedule with export options.

The following topics provide more information about exporting events:

- ["Exporting Search Results" on page 135](#)
- ["Time/NTP" on page 462](#)
- ["Scheduled Searches/Alerts" on page 317](#)

Forwarder Configuration

Logger can send events (as they are received or stored events) to other hosts using UDP or TCP, to a Logger, SmartConnector, or to an ESM. The events sent to a particular host can be filtered by a query. Outgoing syslog messages can be configured to either pass the original source IP and timestamp or to use Logger's "send time" and IP address.

Logger can send CEF events directly to an ArcSight Manager using its built-in SmartConnector. Logger can act as a funnel, receiving events at very high volumes and sending fewer, filtered events on to an ArcSight Manager, as depicted under ["Logger can act as a funnel, forwarding selected events to ESM" on the next page](#).

The following topics provide more information about forwarding events:

- ["Forwarders" on page 376](#)
- ["ESM Destinations" on page 395](#)

User Management

User accounts can be created by the Logger administrator for different users of the system. User accounts inherit privileges from the User Group to which they belong. User Groups can have an enforced event filter called Search Group filters applied to them. This will limit the events that a specific user can see.

The following topics provide more information about user management:

- ["Users/Groups" on page 495](#)
- ["Change My Password" on page 513](#)
- ["Search Group Filters" on page 314](#)

Other Setup and Maintenance

Logger configuration settings, such as receivers, filters, Saved Search jobs, and so on—everything except events—can be backed up as a configuration backup file to any disk and later restored.

Logs detailing Logger activity can be downloaded through the browser on demand, for debugging or other reasons. Other system information is available for viewing. Various system settings can be modified. Some require a system reboot or restart for the changes to take effect.

The Logger Appliance can be rebooted using controls in the user interface. For Software Logger, the Logger service and related processes can be restarted. Follow instructions in ["Software Logger Command Line Options" on page 520](#) to start, stop, or restart Software Logger.

The following topics provide more information about setup and maintenance:


- ["Configuration Backup and Restore" on page 436](#)
- ["Retrieve Logs" on page 420](#)
- ["Storage" on page 475](#)
- ["System" on page 457](#)
- ["License & Update" on page 466](#)
- ["Network" on page 458](#)

Deployment Scenarios


Typically, Logger is deployed inside the perimeter firewall with a high degree of physical security to prevent tampering with the collected event information. Logger does not require other ArcSight products. It receives and forwards syslog and log file events created by a wide variety of hardware and software network products.

Logger also inter-operates with ESM as shown in the following figures. A typical use of Logger is to collect firewall or other data and forward a subset of the data to ArcSight Manager for real-time monitoring and correlation, as shown below. Logger can store the raw firewall data for compliance or service-level agreement purposes.


Logger can act as a funnel, forwarding selected events to ESM



Logger can store events sent by ESM




Logger can store and forward filtered events in a hierarchical ESM deployment



Setting up Search Heads for Faster Peer Searches

If you have several peered Loggers and many users that need to search at the same time, you can set up your Loggers so that some of them are used for receiving, storing, and forwarding events, and others are used only for searching their peers.

A **node** is any peered Logger used for receiving, storing, and forwarding events. A **search head** is a peered Logger that is only used for searching. Search heads do not forward, receive, or store events. To take advantage of search heads, you must set up your architecture so that no data is sent to the Loggers that will be used as the search heads.



Tip: For best search speed, both nodes and search heads require a minimum of 16 GB Ram, with 32 GB recommended.

Once this configuration is in place, ten users can log into the search head and run searches across ten specified nodes at the same time. You can scale this out to enable 100 users to run concurrent searches by setting up ten search heads.

Sending IPv6 Data to Logger

You can send IPv6 data to Logger by using SmartConnectors, version 7.5.0 or higher. For more information, see ["Configuring a SmartConnector to Send Events to Logger" on page 560](#) and refer to the SmartConnector User's Guide for information and instructions.

Once your Logger has IPv6 data, you can filter for IPv6 addresses, just like IPv4 addresses. See ["Searching for IPv6 Addresses" on page 120](#).

Centralized Management

Micro Focus Secure Open Data Platform ArcSight Management Center provides centralized management for Loggers and connectors with a single panel view of all managed ArcSight products.

Using ArcSight Management Center ArcSight Management Center, you can create or import configurations for managed products, and then rapidly push them to products of the same type across your network, ensuring consistent configuration for managed products with one action. You can perform a

variety of remote management tasks, singly and in bulk, on Loggers, and connectors. Logger tasks you can perform using ArcSight Management Center include initial configuration, peer configuration, and user management.

For more information, consult your sales representative or refer to the ArcSight Management Center Administrator's Guide.

Running Logger on Encrypted Appliances

Logger can run on encrypted hardware to help you to meet compliance regulations and privacy challenges by securing your sensitive data at rest.

You can encrypt your Logger Appliance by using Micro Focus Secure Encryption, available from the [Server Management Software > Micro Focus Secure Encryption](#) web page. For instructions, refer to the Micro Focus Secure Encryption Installation and User Guide, available in PDF and CHM formats through the Technical Support / Manuals link on that page.

Logger Appliances are encryption-capable. They come pre- installed with everything necessary for you to encrypt them using Micro Focus Secure Encryption. The length of time encryption takes depends on the amount of data on the server being encrypted. In our testing, an L7600 appliance with 7.5 TB of stored data took about 72 hours to encrypt. You can continue using Logger while the encryption runs. You may notice some performance degradation after encrypting your existing Logger appliance.

Caution: After encryption, you cannot restore your Logger to its previously unencrypted state.


Connecting to Logger

You can connect to Logger and log in with most browsers, including Chrome, Firefox and Internet Explorer. Refer to the Release Notes for a list of browsers supported in this release.

To connect and log into Logger:

1. Use the URL configured during Logger installation to connect to Logger through a supported browser.
 - For the Logger appliance, use **https://<hostname or IP address>**
The End User License Agreement is displayed. Review and accept the EULA.
 - For Software Logger, use **https://<hostname or IP address>:<configured_port>**, where the hostname or IP address is the system on which the Logger software is installed, and configured_port is the port set up during the Logger installation, if applicable.

The Login screen opens.



2. Enter your user name and password, and click **Login**. Use the following default credentials if you are connecting for the first time or have not yet changed the default credentials:

Username: **admin**

Password: **password**

- If login succeeds, the Summary page (Logger's default home page) is displayed. For information on the Summary page see ["Summary" on page 41](#)
- If login fails, the message Authentication Failed is displayed at the top of the login screen. Enter the correct username and password combination to try again.


Note: The first time you log in with the default user name and password, you will be required to change the password.

Depending on your system administration settings, the following options maybe also be available.

- **Forgot Password?** A "Forgot Password?" link is displayed if your Logger is configured to show it. Click this link to change your password. For more information on the Forgot Password link, see ["Enabling Forgot Password" on page 498](#).
- **Use Local Authentication:** The "Use Local Authentication" checkbox is always displayed, but only becomes active when a login attempt fails. By default, this option is available only for the default admin. For more information on the Use Local Authentication option, see ["Local Password" on page 496](#).

Navigating the User Interface

A navigation and information bar (navbar) runs across the top of every page in the user interface.



- [Menus, Take Me To, and Bar Gauges](#) 35

- [Server Clock, Current User, and Options Dropdown](#)36
- [Logger Options](#)36
- [Changing the Display Theme](#)40

Menus, Take Me To, and Bar Gauges

The Summary, Analyze, Dashboards, and Reports menu tabs provide access to various Logger functions and data stored on it.




You can configure system settings and administrative functions in the Configuration and System Admin menus. For more information on each, refer to the sections below.

- The options available in the Summary menu are discussed in ["Summary" on page 41](#).
- The options available in the Dashboards menu are discussed in ["Dashboards" on page 1](#).
- The options available in the Analyze menu are discussed in ["Searching and Analyzing Events" on page 71](#).
- The options available in the Reports menu are discussed in ["Reporting" on page 156](#).
- The options available in the Configuration menu are discussed in ["Configuration" on page 310](#).
- The options available in the System Admin menu are discussed in ["System Admin" on page 456](#).

Take Me To Navigation Box


To the right of the menu tabs, the **Take me to...** navigation box provides a quick and easy way to navigate to any location in the UI. The **Take me to...** feature enables you to navigate to any Logger feature simply by starting to type the feature's name. You can access the Take me to... navigation box by clicking in it or by using the Alt+o, Alt+p, or Ctrl+Shift+o hot keys. As you type, a list of features that match drops down. Click an item in the list or press enter to go to the specified feature. You can open the help for the current page by typing help in the **Take me to...** search box.

Note: **Take me to** functionality has been disabled for overall reports section. Instead, the user can directly be redirected the an specific report by typing: Reports: YourReportSearch. For example: Reports:Most C



Bar Gauges

Bar gauges at the top right of the screen provide an indication of the throughput and CPU usage, which is available in more detail on the Monitor Dashboard discussed in ["Dashboards" on page 1](#).




The range of the bar gauges can be changed on the Options page, as discussed in ["Logger Options" below](#).

Server Clock, Current User, and Options Dropdown

The server clock is shown to the right of the bar gauges, along with the currently logged-in user's name and the Options dropdown arrow.

The server clock displays the Logger server's system time. This may be different from the user's local time.



Below the clock is the login name of the current user. To the right of the user's login name is the dropdown arrow that you can use to open the ["Logger Options" below](#) and the ["Help, About, and Logout" on page 40](#) options.

Logger Options

When you click the Options drop-down arrow, you can access the Options page and the ["Help, About, and Logout" on page 40](#) options as well.

The **Options** page enables you to set the default start page (home page) for all users and specific start pages for individual users and to upload a custom logo to display instead of the default logo.

To access the Options page from any user interface page:

Click the down-arrow by your user name (▼) and then select **Options**.

Options

System

EPS input rate bar gauge max

100K

EPS output rate bar gauge max

100K

Default start page for all users

Summary

Upload a logo (PNG file)

Choose File

No file chosen

Show default logo

☒

Personal

Default start page for admin

Use default for all users

Save

Customizing the Maximum EPS

You can set the maximum rate on the EPS In and EPS Out bar gauges by using the **EPS Input rate bar gauge max** and **EPS output rate bar gauge max** dropdowns in the **Options** menu. If the event rate exceeds the specified maximum, the range is automatically increased.

Customizing the Logo

The **Upload a logo (PNG file)** option in the Options menu enables you to replace the Micro Focus ArcSight Logger logo with your custom logo. The logo must be in .png format. The recommended logo size is 175 X 50 pixels and the maximum file size is 1MB.

175 by 50 pixel logo:



To display a custom logo:

1. From the Options menu, click **Browse**, navigate to the logo you want to use, and click **Open**. The name of your logo is displayed by the browse button.
2. Then uncheck **Show default logo**. The custom logo will be displayed on the login page and on the menu bar.


To display the default Micro Focus ArcSight logo:

Check the **Show default logo** checkbox.

Customizing the Start Page

To set your own personal start page:

From the Personal section of the Options menu, select one of the start page options.



The **Default start page for all users** option indicates which user interface page is displayed after a user logs in. You can set the default start page (home page) for all users and specific start pages individual users. Refer to the following table for information on how to configure a specific start page.

| If you want to set... | Configure the... |
|--|--|
| The same start page for all users | <p>Default start page for all users option to the desired page.</p> <p>This is a global setting for your Logger. To override this setting, configure a different start page for specific users by using the Default start page for <username> option.</p> <p>When you set Default start page for all users option to Dashboards, the Monitor Dashboard is the default dashboard displayed for all users, except users who have configured other dashboards as their defaults, as described in "Setting a Default Dashboard" on page 69.</p> |
| A different start page for specific users | <p>Default start page for <username> option to the desired page.</p> <p>This setting overrides the global Default start page for all users setting.</p> <p>When this option is set to "Use default for all users," the global default page (Default start page for all users) value is used for all users.</p> |
| A specific dashboard for a specific user OR A specific dashboard for all users | <p>Default start page for <username> option to Dashboards.</p> <p>The Monitor Dashboard is the default dashboard displayed for all users. However, if you want to display a different dashboard for one or more users, set the desired dashboard as the default when logged in as those users. For details, see "Setting a Default Dashboard" on page 69.</p> |

Logger User / Roles Report


The user can render a report listing all the users and their respective roles. To access this report, click the **download** button from the export section of the Options menu.

Tip: Make sure to have manage / user group permissions. Otherwise, this functionality will not be displayed. For more information, see ["Setting Logger User Permissions" on page 510](#).

Changing the Display Theme


About


Logger UI displays the dark theme as default.



Procedure

To switch from default to a daylight theme:

1. Before switching from one theme to the other, save any unsaved work.
2. From the header menu, click the  icon so that your display changes from dark to light.




Dark theme (default) is appropriate for a dark room environment to reduce glare. The daylight theme is appropriate for a lighted room.

Tip Reports can be visualized in more detail using the daylight theme.

Help, About, and Logout

When you click the Options drop-down arrow, you can access the following options and the ["Logger Options" on page 36](#) page as well.

To access the online help: From any user-interface page, click the down-arrow by your user name () and then select **Help**.

Tip: The latest Logger documentation is available in Adobe Acrobat PDF format, through the [Micro Focus Security Community](#).

To access version information about your Logger: From any user-interface page, click the down-arrow by your user name and then select **About**.

To log out of Logger: From any user interface page, click the down arrow by your user name and then select **Logout**. You will be returned to the Login screen.




Tip: Logging out is good security practice, to eliminate the chance of unauthorized use of an unattended Logger session. Logger automatically logs you out after a user-configurable length of time (15 minutes by default). To change this length of time, see ["Users/Groups" on page 495](#).

Caution: Simply closing the browser window does not automatically log you out. Click the **Logout** link to prevent the possibility of a malicious user restarting the browser and resuming your Logger session.

Summary

Logger's default home page is the Summary page. (For information on how to use a different page as your home page, see ["Logger Options" on page 36](#).) The Summary page is a dashboard that provides summarized event information about your Logger in one screen. It enables you to gauge incoming events activity and the status of indexing. The events that are in Logger's primary storage (not aged out due to retention or archived data) are used to generate the summary information.


Logger's home page, the Summary page, displays data in four panels. Each panel is displayed in a donut chart by default. You can change the display setting for each panel by clicking the appropriate icon.

- Select  for a list.
- Select  for a column chart.
- Select  for a donut chart.

Note: Donut charts display an event total in the middle of the donut. This is the total number of events displayed in that chart. If the number of events is more than 1000, the event total is displayed using the appropriate standard metric prefix (k, M, G, T).

The panels on the Summary page can display up to 30 items. If there are more than 30, the panels display the top 30, by count.

Logger's Home Page: The Summary Page



Hover your pointer over a column, donut slice, or over the item in the legend to display information about it. For even more details, you can drill down to view the events by a specific resource—receiver, device, agent severity, or agent type. To do so, click the column, donut slice, or list resource to search for those events. The Search page opens and the search box is automatically populated with the search that generated the information you clicked on the Summary page. The Start and End fields are populated with the time of oldest events stored on your system (that have not aged out due to retention) and the current time, respectively.


For example, if you click Logger Internal Event Device under Event Summary by Receiver, the **Analyze > Classic Search** page opens with the following query populated, and the search is run. If desired, you can further refine the search query to filter the search results to suit your needs. Click **Go!** to run the search again. You can also execute a search in **Analyze > Search**. For more information, see "[Search page](#)" on [page 74](#).

You cannot change or add other panels to the Summary page. If you need to display other information, you can create a custom Dashboard as described in "[Dashboards](#)" on [page 1](#).

The information displayed on the Summary page is for your local Logger only, and does not include information about peer Loggers even if peers are configured.

Summary Dashboard Panels

- **Global Summary:** The number of events indexed on your Logger during the time period displayed on the screen. This time period is dependent on the retention policy set on your Logger. The start is the

time of the oldest event stored in the Logger since the Logger was restarted, that has not aged out due to retention; the end time is current time. The **Add Data** () button at the top opens the Receivers page where you can add and manage the receivers that put log data into your Logger. For more information on managing receivers, see ["Receivers" on page 346](#).

Note: Kindly note **Global Summary** and **Search** page might differ significantly in the amount of events displayed as search time granularity used in both pages is different.

- **Event Summary By Receiver:** The list of receivers configured on your Logger, the number of events received on each receiver (that are in Logger's primary storage, not aged out due to retention or archived data), and the timestamp of the last event received on each receiver. If a receiver is deleted, the summary information for it will continue to display until the events received on it age out from Logger's primary storage. However, the receiver name is changed to the receiver ID (a numerical string) associated with the deleted receiver.
- **Event Summary By Device:** A device is a named event source, comprising of an IP address (or hostname) and a receiver name. The Devices panel lists devices configured on your Logger, the number of events received on each device (that are in Logger's primary storage, not aged out due to retention or archived data), and the timestamp of the last event received on each device. If a device is deleted, the summary information for it will continue to display until the events received on it age out from Logger's primary storage. However, you cannot click the device name to view the events associated with the deleted device.
- **Event Summary By Agent Severity:** The list of severity levels of the incoming events from ArcSight SmartConnectors to your Logger, the number of events received of each severity level, and the timestamp of the last event received of each severity level. Only events in Logger's primary storage (not aged out due to retention or archived data) are considered when summarizing this information.
- **Event Summary By Agent Type:** The list of ArcSight SmartConnectors sending events to your Logger, the number of events received from each SmartConnector (for events that are in Logger's primary storage, not aged out due to retention or archived data), and the timestamp of the last event received from each SmartConnector. If a SmartConnector is deleted, the summary information for it will continue to display until the events received from it age out from Logger's primary storage.

The Effect of Search Group Filters on the Summary Page

Search Group filters that enforce privileges on storage groups are applied to the content displayed on the Summary page. However, Search Group filters that enforce privileges on **device groups** are not applied. Therefore, the Summary page includes counts of events in device groups to which a user does not have privileges. However, if the user tries to drill down to view events, search results in accordance with access privileges are returned as the search query is run on the Analyze page, which enforces all types of Search Group filters. Similarly, if a Search Group filter enforces privileges on both, storage groups and device groups, only the storage group enforcement is applied on the Summary page.

Chapter 2: Dashboards

The following topics provide an overview of how to connect to Logger, and explores Logger's dashboards. Logger includes standard dashboards that display the real-time and historical status of receivers and forwarders as well as storage, CPU, and disk usage statistics. You can create your own dashboards for an all-in-one view of Logger information that is of interest to you.

Dashboards are an all-in-one view of the Logger information of interest to you. You can select and view any of several out-of-box dashboards or create and display your own custom dashboard.

Each Logger dashboard contains one or more panels of these types:

- **Search Results:** Search Results panels display events that match the query associated with the panel.
- **Monitor:** Monitor panels display the real-time and historical status of various Logger components such as receivers, forwarders, storage, CPU, and disk.
- **Summary:** Summary panels display summarized event information about your Logger—the number of events received of a specific resource or field type, and the timestamp of the last event received for that resource or field type.
- [Out-of-Box Dashboards](#)44
- [Custom Dashboards](#)63
- [Setting a Default Dashboard](#)69

Out-of-Box Dashboards

Logger comes with several out-of-box dashboards, described below. The Monitor dashboard is displayed by default unless you configure another dashboard to display as your default.

- The Event Count dashboard, described in ["The Event Count Dashboard" on page 54](#), displays how many events each receiver or forwarder handled.
- The Intrusion and Configuration Events dashboard, described in ["The Intrusion and Configuration Events Dashboard" on page 53](#), displays information about configuration changes and intrusions on your system.
- The Login and Connection Activity dashboard, described in ["The Login and Connection Activity Dashboard" on page 53](#), displays information about login and connection activity on your system.
- The Monitor dashboard displays the Summary panel, which shows the status of CPU Usage, Event Flow, Receivers, Forwarders, and Storage Groups in a summarized view. The other panels available in this dashboard are Platform, Network, Logger, Receivers, Forwarders, and Storage. These views are described in detail in ["The Monitor Dashboard" on page 46](#).

You cannot change or adjust the panels available in the out-of-box dashboards, except the System Overview dashboard (See ["The System Overview Dashboard" on page 52](#)). However, you can add specific Search Results panels to a custom dashboard, as described in ["Creating and Managing Custom Dashboards" on page 64](#).

You can add also Monitor and Summary panels to it. These panels provide the same information available through the default Monitor dashboard and the default Summary dashboard, however in a modular form that enables you to choose specific views. (See ["Summary" on page 41](#) for more information about default Summary dashboard.)

For example, if you want to view the EPS for the last 4 hours on all receivers, add the panel Type "Monitor Graph", and select "(Logger) All EPS Out-All EPS In - 4 hour" as the Graph, or if you want to view the EPS on Forwarders in a table form, select the "Monitor (Forwarders)" panel Type. Similarly, if you want to view only the summary information for receivers on your Logger, add the panel of Type "Summary (Receivers)". Besides the four Summary panels (Agent Severities, Agent Types, Receivers, and Devices), you can also create a user-defined Summary panel in which you can select **any indexed, non-time field** by which you want to categorize event summary. For example, if you want to add a Summary panel to display event summary categorized by "destinationAddress", you can add a panel of Type "Summary (User Defined)" for this field if it is indexed on your Logger.

You can also drill down on any of the resources listed in Monitor and Summary panels you add to view events by a specific resource or field value on the Analyze (Search) page. For example, you can click on a storage group in a Monitor panel to view its events in the last 24 hours, or you can click on an event name "Network Usage - Inbound" to view all events of that name in the last one hour. Additionally, you can access the Configuration page for any of the resources listed in the Monitor panels to configure them. For example, if you want to configure a receiver, click the Configure link on top of the Monitor (Receiver) panel.

Search Group filters that restrict privileges on device groups are not enforced on **Summary panels**. Therefore, Summary panels include counts of events in device groups to which a user does not have privileges. However, if the user tries to drill down to view events, search results in accordance with access privileges are returned as the search query is run on the Analyze page, which enforces all types of Search Group filters. Similarly, if a Search Group filter enforces privileges on both, storage groups and device groups, only the storage group enforcement is applied on Summary panels.

Users can create both shared and private dashboards.

- Shared dashboards are visible to all users with the appropriate privileges.
- Private dashboards are visible only to the creator or users with "admin" privileges.
- Only the creator or users with "admin" privileges can edit or delete dashboards of either type.

A user accessing a shared dashboard must have privileges to view the information displayed in the dashboard; otherwise, the information to which they do not have the privileges is not displayed, and the associated panel displays a message that indicates the reason for the undisplayed information.

Managing Out-Of-Box Dashboards

Each dashboard displays the search results of a Saved Search found in the standard system content along with the time and date the query was most recently refreshed.

While you cannot update the system content used in the out-of-box dashboard, you can then edit the search to meet your needs, save your changes, and use your new saved search in your own dashboard to find exactly what you are interested in. To create a new dashboard, follow the instruction in ["Creating and Managing Custom Dashboards" on page 64](#).

Note: Dashboards that display charts are aggregated queries. Therefore, the entire search must complete before the chart is displayed. This can take some time if there are a large number of events.


- The dashboards are not automatically refreshed. Click refresh  to refresh the search results.
- Click **View on Search Page** to open the **Analyze > Classic Search** page and run the Saved Search automatically.
- Click a chart value (a column, bar, or donut section) to drill down to events with specific field values. (Drill-down is not available for dashboards that display tables.)

Chart Drill-Down

When you click on a chart value (a column, bar, or donut section), the query is rerun on the **Analyze > Classic Search** page with an additional WHERE operator clause that includes the field name and value you clicked on the chart.

The drill-down information includes a histogram and a table of the search results. You can drill down on the histogram for further information. For more information on drilling down on a histogram, see ["Histogram Drill Down" on page 126](#).

Note: The saved search query associated with the Search Results panel in the dashboard is not modified. If you need to return to the dashboard from the drill-down screen, use the Back function of your browser.

The Monitor Dashboard

The Monitor Dashboard, displayed by default, contains the real-time and historical status of receivers, forwarders, and storage, CPU, and disk usage statistics. On Software Logger, the CPU and disk usage statistics indicate the total use of these resources on the system, not just the use of these resources by the Logger process.

The Monitor panels, available through a pull-down menu display Summary, Platform, Network, Logger, Receivers, Forwarders, and Storage information. You cannot change or adjust any of these out-of-box

panels, but you can create your own dashboards to monitor the things in which you are most interested. For more information, see ["Creating and Managing Custom Dashboards" on page 64](#).

All monitor panels, except the Summary panel, include a pull-down menu for duration control. The summary panel has buttons instead. In both cases, you can choose one of the following time spans for historical data: 4 hours, 24 hours, 7 days, 30 days, 90 days, or 365 days. As you hover your pointer over the data, more details are displayed. In the case of dashboards that displays two fields, details of both are displayed, and a legend indicates the color that represents each field.


In these dashboards, events per second (e/s) are displayed using standard metric prefixes (k, M, G, T) for numbers over 1000. Numbers under 1000 are displayed as integers.

The System Overview dashboard provides a different view of these panels. See ["The System Overview Dashboard" on page 52](#) for more information about that view.

Monitor Dashboard Summary Panel

The summary panel, displayed by default, shows the status of CPU Usage, Event Flow, Receivers, Forwarders, and Storage Groups in a summarized view.

Monitor dashboard - Summary panel



On the Summary panel, click on a Receiver, Forwarder, or Storage Group name to jump to the Search page and include the selected resource in the query.

Additionally, you can click **Configure** (⚙️ Configure) to open the Configuration page for Receivers, Forwarders, and Storage Groups.


Note: The total space allocated for a storage group includes a certain amount that has been set aside

to ensure that the group can receive new events when it is almost full. As a result, the percentage of used space for a storage group never reaches 100% (as displayed on the Monitor > Summary panel). For Software Loggers installed using the Minimal setting, the maximum % Used (On the Monitor > Summary panel) for each storage group reaches up to 66.33%. (Two storage groups of 3 GB each; 1 GB is set aside for new events in each group. After 2 GB of space has been used and the new events are being written to the last 1 GB, Logger automatically triggers retention and reclaims 1 GB of the used space. Thus, the % Used field for each storage group only reaches up to 66.33%.)

Monitor Dashboard Receivers Panel

The Receivers monitor panel shows the total Events per Second (EPS) received and displays values for each configured receiver. The list of receivers includes all receivers known to the system, including those that are disabled. (To create a new receiver, or to enable or disable one, see ["Working with Receivers" on page 353.](#))


Monitor dashboard - Receivers panel



Monitor Dashboard Platform Panel

The Platform monitor panel displays information about CPU usage, memory usage, bytes received and sent on the network, and raw disk reads and writes.


Monitor dashboard - Platform panel



Monitor Dashboard Network Panel

The Network monitor panel display a graph for each network interface card. (The number of network interface cards varies by the hardware model.) The graph displays the bytes transmitted, overlaid on the bytes received.


Monitor dashboard - Network panel



Monitor Dashboard Logger Panel

The Logger monitor panel displays information about events, searches, and memory. JVM Memory Usage chart displays the memory used by the Logger's back-end server process. For example, this could be the memory used to perform the search after receiving the search query from the UI.


Monitor dashboard - Logger panel



Monitor Dashboard Forwarders Panel

The Forwarders monitor panel shows total Events per Second (EPS) sent and displays values for each configured forwarder. The list of forwarders includes all forwarders known to the system, including those that are disabled. To create a new forwarder, or to enable or disable one, see ["Forwarders" on page 376](#).


Monitor dashboard - Forwarders panel



Monitor Dashboard Storage Panel

The Storage monitor panel displays disk read and disk write information. The list of storage groups compares allocated and used space in each group. Space is used in 1 GB files so a 5 GB storage group appears 20% used as soon as it is set up. For more information about storage groups, see ["Storage Groups" on page 405](#).

Monitor dashboard - Storage panel



The System Overview Dashboard


The System Overview dashboard provides an alternate view of several Monitor dashboard panels. This dashboard displays the CPU Usage, Platform Memory, Disk Read-sda, Disk Write-sda, Search Performed, Transmit-eth0, Receive-eth0, JVM Memory, All EPS In, and All EPS Out panels that you use to monitor your Logger. You can replace any of these panels with other Logger monitor panels to adjust the display to your needs.

To view the System Overview dashboard, open the Dashboards menu and click **System Overview** at the top of the Monitor Dashboard.



The System Overview dashboard displays.

System Overview Dashboard





One Monitor panel is displayed in a large format at the top of the screen, the others are smaller and displayed in rows across the bottom.

- Click 4h, 1d, 7d, 30d, 90d, or 365d at the top of the large panel to adjust the displayed time range.
- Hover your pointer over a section on the large panel for more detail.
- Click a small panel on the bottom of the screen to move it to the large display at the top.
- You can display other monitor panels in place of the out-of-box panels.

Note: You can only display existing monitor panels; you cannot display search results or summary panels.

The Forwarder, Receiver and Storage panels available for display varies, based on your Logger configuration.

To display a custom panel in place of one of the out-of-box panels:


1. Click the edit icon  next to the panel's name.
2. Start typing in the text box to see the list of available panels. For example, to display a receiver, start typing "re".
3. Click a panel in the list to select it, or click the cancel icon  to close the dialog without selecting another panel.

The Intrusion and Configuration Events Dashboard

The Intrusion and Configuration Events dashboard displays information about the following types of configuration changes and intrusions on your system.

- **Top Malicious Code Activity:** displays the most active malicious code.
- **Top Firewall Drops by Source:** displays events in which traffic was dropped by a firewall.
- **Configuration Changes by Product:** shows products that have had their configurations modified.
- **Windows Account Creations:** shows user accounts created on Microsoft Windows operating systems.

Intrusion and Configuration Events dashboard



For more information on chart drill down and how to edit out of the box dashboards, see "[Managing Out-Of-Box Dashboards](#)" on page 46


The Login and Connection Activity Dashboard

The Login and Connection Activity dashboard displays information about the following types of login and connection activity on your system.

- **Top Failed Logins by Product:** displays the top failed logins sorted by device product.
- **Top Failed Logins by User:** displays the top failed logins sorted by user name.

- **SSH Authentications:** displays the users most frequently logging in or attempting to log in using SSH.
- **VPN Connections:** displays the users most frequently logging in or attempting to log in using a VPN connection.

Login and Connection Activity Dashboard




For more information on chart drill down and how to edit out of the box dashboards, see "[Managing Out-Of-Box Dashboards](#)" on page 46

The Event Count Dashboard

The Event Count dashboard displays information about the following types of event input and output activity on your system.

- **Individual Receivers:** displays the events received per receiver.
- **Individual Forwarders:** displays events forwarded per forwarder.
- **All Receivers:** displays the total events received by all receivers.
- **All Forwarders:** displays the total events forwarded by all forwarders.

Event Count Dashboard




For more information on chart drill down and how to edit out of the box dashboards, see "[Managing Out-Of-Box Dashboards](#)" on page 46

Malware Overview Dashboard

The Malware Overview dashboard displays information using the following panels:

- Top Targets: displays the top machines with malware instances.
- Top Reported Malware: displays the top reported malwares.
- Reported Events By Time: displays reported malware events by time.
- Top Reported Events: displays the top reported malware events.

Malware Overview Dashboard




For more information on chart drill down and how to edit out of the box dashboards, see "[Managing Out-Of-Box Dashboards](#)" on page 46

The Attacks and Suspicious Activity Dashboard

The Attacks and Suspicious Activity dashboard displays information using the following panels:

- Top Attackers: displays the top attackers IP addresses.
- Top Targets: displays the top target IP addresses
- By Time: displays attacks and suspicious activity by time.
- Top Events: displays the top reported suspicious and attacks events.

Attack and Suspicious Activity Dashboard




For more information on chart drill down and how to edit out of the box dashboards, see "[Managing Out-Of-Box Dashboards](#)" on page 46

Operating System Errors and Warnings Dashboard

The Operating Systems Errors and Warnings dashboard displays information using the following panels:

- Top Hosts: displays the top machines with operating system errors and warnings.
- Top Events: displays the top reported operating system errors and warnings.

Operating System Errors and Warnings Dashboard




For more information on chart drill down and how to edit out of the box dashboards, see "[Managing Out-Of-Box Dashboards](#)" on page 46

The Vulnerability Overview Dashboard

The Vulnerability Overview dashboard displays information about vulnerabilities using the following panels:

- Top Vulnerable Hosts: displays the top vulnerable machines.
- Top Events: displays the top reported vulnerabilities.
- Distribution by Severity: displays the reported vulnerabilities distribution by severity.
- Top Vulnerabilities by Device Product and Signature ID: displays the top vulnerabilities by reporting scanner and signature ID.

Vulnerability Overview Dashboard




For more information on chart drill down and how to edit out of the box dashboards, see "[Managing Out-Of-Box Dashboards](#)" on page 46

The Insecure Services Dashboard

The Insecure Services dashboard displays information about insecure services and ports using the following panels:

- Top IP Addresses using Insecure Services: displays the top IP addresses with insecure services.
- Top Insecure Ports: displays the top reported insecure ports.
- Top IP Addresses using Insecure Ports: displays the reported IP addresses with insecure ports.
- Top Insecure Processes: displays the top reported insecure processes.

Insecure Services Dashboard




For more information on chart drill down and how to edit out of the box dashboards, see "[Managing Out-Of-Box Dashboards](#)" on page 46

The DGA Overview Dashboard

The DGA Overview dashboard monitors DGA domains on the organization using Microsoft DNS Trace Log ArcSight Connector by showing the following panels:

- Top Hosts by # Unique DGA Domains: displays the top clients by number of Unique DGA domains.
- Top Unique DGA Domains by # of Hosts: displays the top unique DGA domains by number clients.
- Top Host by DNS Events Sum Bytes Out: displays the top clients by outgoing bytes to DGA domains.
- Activity by Time: displays DGA activity by time.

DGA Overview Dashboard




For more information on chart drill down and how to edit out of the box dashboards, see "[Managing Out-Of-Box Dashboards](#)" on page 46

The MITRE Att&ck Overview Dashboard

This Dashboard provides overview about MITRE ATT&CK framework related events forwarded to Logger from ArcSight ESM and includes the following Panels:

- MITRE – Top Techniques: Displays the top MITRE Techniques reported on the organization.
- MITRE – Top Users : Displays the top Users with MITRE related events.
- MITRE – Top Attacker IPs: Displays the top Attacker IPs with MITRE related events.
- MITRE - Top Target IPs : Displays the top target IPs with MITRE related events.

MITRE Att&ck Overview Dashboard




For more information on chart drill down and how to edit out of the box dashboards, see "[Managing Out-Of-Box Dashboards](#)" on page 46

The MITRE Att&ck Events Statistics Dashboard

This Dashboard provides information about MITRE ATT&CK framework related events forwarded to Logger from ArcSight ESM and includes the following Panels:

- MITRE - Event by Time : Displays reported MITRE events by Time.
- MITRE - Top Fired Rules : Displays the top fired ESM rules related to MITRE events.

MITRE Att&ck Events Statistics Dashboard




For more information on chart drill down and how to edit out of the box dashboards, see "[Managing Out-Of-Box Dashboards](#)" on page 46

Custom Dashboards

A dashboard can contain a mix of Search Results, Monitor, and Summary panels. You can assemble various search queries that match events of interest to you, status of Logger resources such as receivers, forwarders, storage, CPU, and disk, or a combination of both on a single dashboard.

There is no limit on the number of Monitor and Summary panels you can add to a single dashboard; however, you can only add up to four Search Results panels.

Sample Custom Dashboard




Each Search Results panel is associated with a saved search query. You can only associate saved search queries that contain an aggregation operator such as chart or top for this type of panel.

Click **View on Search Page** in the Search Results panels to go to the **Analyze > Classic Search** page and view the event details; the panel query is automatically run and the search results are displayed.

Additionally, you can drill down from any chart to quickly filter down to events with specific field values. To do so, identify the value in the chart on a Search Results Chart panel and click it to drill down to events that match the value.


When you click on a chart value (a column, bar, or donut section), the query is rerun on the Analyze (Search) page with an additional WHERE operator clause that includes the field name and value you clicked on the chart.

Note: Dashboards that display charts are aggregated queries. Therefore, the entire search must complete before the chart is displayed. This can take some time if there are a large number of events.

- The dashboards are not automatically refreshed. Click refresh  to refresh the search results.
- Click **View on Search Page** to open the **Analyze > Classic Search** page and run the Saved Search automatically.
- Click a chart value (a column, bar, or donut section) to drill down to events with specific field values. (Drill-down is not available for dashboards that display tables.)

Creating and Managing Custom Dashboards

The options displayed in the **Dashboards > Tools** menu vary depending on your permissions.



You need these privileges (in the Logger Rights group) to perform dashboard operations:

- Use and view dashboards
- Edit, save, and remove dashboards

With these permissions, you can create a dashboard (see ["Adding a Custom Dashboard" on the next page](#)), and add panels to the dashboard you created. (see ["Adding and Managing Panels in a Dashboard" on page 66](#)).

Tip: If you are adding a Search Results panel, the saved search must exist. If no saved searches exist, the Search Results panel option is not displayed.

Adding a Custom Dashboard

To add a dashboard:

1. Open the **Dashboards** menu.
2. Click the **Tools** pull-down menu and select **Create Dashboard**.
3. Enter a meaningful name for the dashboard in the **Name** field.
4. Select whether the dashboard **Type** is Private or Shared.

The private dashboards are only visible to the user who created them, and the shared dashboards are visible to all Logger users; however, they will not see the information to which they do not have privileges.

5. Click **Create**.

After creating the dashboard you must add panels to it, as described in ["Adding and Managing Panels in a Dashboard" on the next page](#).

Editing a Custom Dashboard

The Edit Dashboard page allows you change the name and privacy settings for a custom dashboard. To add or edit dashboard panels, see ["Adding and Managing Panels in a Dashboard" on the next page](#).

The privacy options are:

- Private — Only you can see your dashboard.
- Shared — All Logger users can see your dashboard; however, they will not see the information to which they do not have privileges.

For example, if a user does not have privileges to a storage group and a panel in a Shared dashboard includes a query that accesses the events in that storage group, the panel will be blank when the user accesses the shared dashboard.

To edit a dashboard:

1. Open the **Dashboards** menu.
2. Click the **Tools** pull-down menu and select **Edit Dashboard**.
3. If you want to change the name of the dashboard, enter a new name in the **Name** field.
4. If you want to change the privacy setting of the dashboard, select the appropriate setting from the **Type** pull-down menu, and click **Save**.
5. To add or edit dashboard panels, see ["Adding and Managing Panels in a Dashboard" on the next page](#).

Deleting a Custom Dashboard

To delete a dashboard:

1. Open the **Dashboards** menu.
2. Select the dashboard that you want to delete.
3. Click the **Tools** pull-down menu and select **Delete Dashboard**.
4. Click **Yes** to confirm your action in the confirmation message, or click **No** to exit without making a change.

Adding and Managing Panels in a Dashboard

After you create a dashboard, you need to add panels to display the information you want to see. A dashboard can contain a mix of Search Results, Monitor, and Summary panels. There is no limit on the number of Monitor and Summary panels you add to a single dashboard; however, you can only add up to four Search Results panels for optimum performance.

Before you can add panels to a dashboard, you must first create the dashboard. See ["Creating and Managing Custom Dashboards" on page 64](#) for more information.

You can add the following types of panels:

- Search Results: Chart and Table
- Monitor: All four types available under the default Monitor dashboard
- Summary: All four types available under the default Summary dashboard and user-defined Summary panels.

Adding a Panel to a Dashboard

To add a panel to a dashboard:

1. Open the **Dashboards** menu.
2. Select the dashboard to which you want to add the panel.
3. Click the **Tools** pull-down menu and select **Add Panel**.
4. Configure these parameters and click **Add**.

| Parameter | Description |
|--------------|---|
| Type | <p>Select the type of panel:</p> <ul style="list-style-type: none"> • Search Results (Chart): Displays search results in a chart form. • Search Results (Table): Displays search results in a table form. • Monitor (Graph): Displays a graph of the selected resource. • Monitor (Forwarders): Displays forwarder information in a table form. • Monitor (Receivers): Displays receiver information in a table form. • Monitor (Storage Groups): Displays storage group information in a table form. • Summary (Agent Severities): Displays event summary categorized by agent severities configured on your Logger. • Summary (Agent Types): Displays event summary categorized by receivers configured on your Logger. • Summary (Receivers): Displays event summary categorized by receivers configured on your Logger. • Summary (Devices): Displays event summary categorized by devices configured on your Logger. • Summary (User Defined): Displays event summary categorized by the field you select when adding the panel. <p>Note: If no saved search queries exist on your Logger, the "Saved Search" panel types are not available as selections in the pull-down menu.</p> |
| Title | <p>Enter a meaningful name for the panel.</p> <p>A default name is present in this field, but you can change it.</p> |
| Graph | <p>Only applicable to Monitor Graph panels.</p> <p>Select the type of graph you want the panel to display. Some of the available options are CPU Usage - 4 hour, Platform Memory Usage - Daily, and Disk Read-Write - Weekly.</p> |
| Saved Search | <p>Only applicable to Search panels.</p> <p>Select the saved search query to use for searching events that will be displayed in the panel.</p> |
| Chart Type | <p>Only applicable to Search Result Chart panels.</p> <p>Type of chart to display matching events. You can select from: Column, Bar, Donut, Area, Line, Stacked Column, Stacked Bar. Default: Column</p> |
| Chart Limit | <p>Only applicable to Search Result Chart panels.</p> <p>Number of unique values to plot. Default: 10</p> |
| Field Name | <p>Only applicable to Summary (User Defined) panels.</p> <p>The event field name by which the event summary on a Summary panel will be categorized. Default: agentSeverity</p> |



Editing a Dashboard Panel

Once you add a panel to a dashboard, whether you can edit it depends on the type of panel. You can edit the Search Results panels and the user-defined Summary panels; the Monitor panels and some of the Summary panels are not editable.

The following table lists the panels you can edit and what you can edit in them.

| Action | Description |
|--------------------------------------|--|
| All Panels | |
| Delete | Removes a panel from a dashboard. |
| Search Result Panels | |
| Edit Panel | Change Title, associated saved search, Chart Type, or Chart Limit |
| Edit Saved Search | Access the Edit Saved search page to edit the associated saved search query |
| View on Search Page | Runs the panel's query on the Search Results page (Analyze > Classic Search) and displays matching events on that page |
| Refresh | Refreshes the current contents of the panel. Note: All other panel types are automatically refreshed; therefore, an explicit refresh is not required for them. |
| Summary Panels - User Defined | |
| Edit Panel | Change Title or field name by which events are categorized. |

To edit a panel:

1. Open the **Dashboards** menu.
2. Select the dashboard that contains the panel you want to edit.
3. If you are editing a user-defined Summary panel:
 - a. Click the Edit () icon.
 - b. Edit the title, field name, or both.
4. If you are editing a Search Result panel:
 - a. Click the () icon.
 - b. Select **Edit Panel** if you want to edit the panel title, select a different saved search; or, if applicable, chart type or chart limit.
 - c. Select **Edit Saved Search** if you want to access the Edit Saved Search page (**Configuration | Search > Saved Searches**) to edit the saved search query.
5. Click **Save**.

Deleting a Dashboard Panel

To delete a panel from a dashboard:

You cannot delete panels from the default Monitor dashboard or the default Summary dashboard. However, Monitor and Summary panels added to the dashboards you created under the Dashboards menu option can be deleted.

1. Open the **Dashboards** menu.
2. Select the dashboard that contains the panel you want to delete.
3. Click the (✕) icon.
4. Click **Yes** to confirm your action in the confirmation message, or click **No** to exit without making a change.

Changing the Layout of a Dashboard

To change the layout of a dashboard:

You can only change the layout of the dashboards you create. The Monitor dashboard layout cannot be changed.

1. Open the **Dashboards** menu.
2. Select the dashboard that contains the panel you want to rearrange.
3. Click the **Tools** pull-down menu and select **Change Layout**.
4. Point your cursor in the blue band that shows the panel title and drag the panel to a different position.
5. Click **Save** after you rearrange the panels.

Setting a Default Dashboard

When you set a dashboard as default, it is the default dashboard screen that displays when you navigate to the Dashboards menu. This setting is user-specific; therefore, your default dashboard can be different from that of another user.

The Summary page (accessible from the Summary navigation option in the top-level menu bar) is the default home page for all Logger users. That is, unless another page has been selected as your home page, the Summary page is displayed when you first log in.

You can configure Logger to display a specific dashboard as your home page, including one you created.

To select a specific dashboard as your home page:

1. Select the **Dashboard** option when configuring the Personal **Default start page for <username>**, following the instructions in ["Logger Options" on page 36](#).
2. Open the **Dashboards** menu.
3. Select the dashboard that you want to configure as default.
4. Click the **Tools** pull-down menu and select **Select as Default**.
5. Click **Yes** to confirm your action in the confirmation message, or click **No** to exit without making a change.

Chapter 3: Searching and Analyzing Events

This topic applies to both Classic Search and Search Pages

When you want to analyze events matching specific criteria, include them in a report, or forward them to another system such as ArcSight ESM, you need to search for them. To search for events, you create queries. The queries you create can vary in complexity based on your needs. Queries can be simple search terms or they can be complex enough to match events that include multiple IP addresses or ports, and that occurred between specific time ranges from a specific storage group.

The following topics describe how to search for specific events in Logger using Classic Search or Search pages. They discuss the methods available for search, how to query for events, how to save a defined query and the events that the query finds for future use. They also describe how to set up alerts to notify particular users when Logger receives events that match specified criteria.

| | |
|--|-----|
| • The Process of Searching Events | 71 |
| • Understanding Classic Search Field Colors | 73 |
| • Search page | 74 |
| • Elements of a Search Query | 78 |
| • Using the Advanced Search Builder | 98 |
| • Search Analyzer | 102 |
| • Regex Helper Tool | 103 |
| • Search Helper | 104 |
| • Searching for Events | 108 |
| • The Search Results Display | 122 |
| • Saving the Search Results | 134 |
| • Saving Queries, Creating Saved Searches and Saved Filters. | 138 |
| • Enriching Logger Data Through Static Correlation | 146 |
| • Viewing Alerts | 149 |
| • Live Event Viewer | 150 |
| • Using Global ID | 154 |

The Process of Searching Events

This topic applies only to Classic Search page

The search process uses an optimized search language that allows you to specify multiple search commands in a pipeline format. In addition, you can customize the display of search results, view search results as charts, and so on.

The most straightforward way to run a search is to enter the keywords or information you are searching for (the query) in the Search text box, select the time range, and click **Go!** You can enter a simple keyword, such as, **hostA.companyxyz.com** or a complex query that includes Boolean expressions, keywords, fields, and regular expressions. The system searches for data that matches the criteria you specified and displays the results in color-coded columns indicating its index status. For more information, see ["Understanding Classic Search Field Colors" on the next page](#).

The search results are displayed in the table and as a histogram as soon as they are returned, even if the query has not finished scanning all data. The Active Search list displays any searches in progress, as well as completed searches that have not yet expired. You can also add a chart to your search to display the most important information in a more meaningful fashion. Charts are not displayed until all the data is returned.

There are several convenient ways to enter a search query. You can type the query in the Search text box, use the Search Builder tool to create a query, click a field in the current search results, or use a previously saved query (referred to as a filter or saved search).

When you type a query, the Search Helper provides suggestions and possible matches to help you build the query expression. (See ["Search Helper" on page 104](#) for more information.)

In addition to typing the query in the Search text box, you can do the following:


- Create queries by using the Advanced Search tool. For more information, see ["Using the Advanced Search Builder" on page 98](#).
- Save queries and use them later. For more information, see ["Saving Queries, Creating Saved Searches and Saved Filters." on page 138](#).
- Create new queries from the predefined queries that come with your system. For more information, see ["System Filters/Predefined Filters" on page 140](#).

Although a search query can be as simple as a keyword, you will be better able to utilize the full potential of the search operation if you are familiar with all the elements of a query, as described in ["Elements of a Search Query" on page 78](#).

This example query finds events containing the word "Logger." Type **Logger** in the search box and then click **Go!** Aggregated search operators such as **chart**, **top**, and **rare** generate charts of search results. This example query finds events containing the word "Logger" and charts the top ten events by the contents of the name field. Type the following query in the search box and then click **Go!**

Logger | top deviceEventClassId

A chart similar to this one displays.







For more information on the search operators, see ["Search Operators" on page 524](#). For more information on creating and using charts, see ["Chart Drill Down" on page 129](#) and ["Refining and Charting a Search from Field Summary" on page 133](#).




Understanding Classic Search Field Colors

This topic applies to both Classic Search and Search page

Each column in the Search Results table is color-coded to show what type of field it contains, and whether or not the field has been indexed. Colored column labels can help you refine your searches for the fastest results.


Field type icons will also display on Logger pages where search Fields are used, such as the Field set editor, the default Fields page, and search auto-complete.

| Icon | Column Color | New Search | Classic Search | Field Type | Can Field be Indexed? |
|---|--------------|------------|----------------|---|-----------------------|
|  | Dark green | | Yes | Super indexed | Indexed by default |
|  | Green | | Yes | Indexed | Indexed by default |
|  | Light green | | Yes | Logger Common Event Format (CEF), including custom fields | Yes (indexable) |
|  | Light gray | | Yes | Metadata | No |
| | No color | Yes | Yes | Non-Logger CEF | No |






| Icon | Column Color | New Search | Classic Search | Field Type | Can Field be Indexed? |
|---|--------------|------------|----------------|---|-----------------------|
|  | Killarney | Yes | | Super indexed | Indexed by default |
|  | Clay Creek | Yes | | Indexed | Indexed by default |
|  | Turquoise | Yes | | Logger Common Event Format (CEF), including custom fields | Yes (indexable) |

Search page

This topic applies only to Search page

Search page displays the number of events scanned and found, execution time, and amount of events displayed per page. To access this page, select **Search** option from the **Analyze** drop down. The user can return to the actual Logger page by clicking the  **Logger** icon anytime.

Click      to refine the search. Each functionality is described below:

-  **Search settings:** It defines search criteria. Based on the level of rights granted, select between peer and **local only** search as appropriate. To filter the search, date and time can be selected using time and date picker respectively.
-  **Enable/ Disable highlight:** By default , it highlights the search displaying a variety of colors when one of the categories below is added. To disable this function, click the icon.
 - Field name: sub divided in metadata, indexed, indexable, superindexed.
 - Operator
 - String
 - Keyword
 - Boolean
 - Number and Punctuation
-  **Clear query:** It clears the query box. Button will be disable if no text has been added in the query box.
-  **Filter/ Saved searches:** It loads previously saved filters and / or searches. For more information see ["Saved Searches/ Filters " on the next page](#)
-  ["Custom Fieldsets" on the next page](#)
- **Classic Search** **Classic Search:** It executes the same search in the classic search page while keeping the time when the first search was run. When selecting the dynamic option, the parameters chosen will remain while exporting them in classic search.
- **Custom Time Range:** It specifies a search start and end date. Years and months lay out in one single column on the left side of the window while days are shown in the right side of the window. For more information, see ["Time Range" on page 86](#).

- **Search time:** It enables the user to select between Logger Receipt Time and End Time.
- **Pagination:** It exhibits a certain quantity of events per page. To edit this number of events, simply change the number as appropriate. You can also alter between first, previous, next, and last page. Pagination will work for all views.

Note: The following functions cannot be opened simultaneously: **Customize Fieldsets**, **Compare Events** and **Saved Searches**. Logger only supports one emergent window at a time.


Custom fieldset creation and raw data visualization functions are also available in this page. For more information, see ["Custom Fieldsets" below](#) and [" Page Views " on the next page](#).

Custom Fieldsets

This topic applies only to Search page

You can create your own fieldset by clicking the icon located in the search page. To add a fieldset, drag and drop a field to the **selected fields** column.

To customize fieldsets:

1. Click .
2. Drag and drop any field to the **Selected Fields** column.
3. Click **OK** to accept or **Cancel** to discard the changes.

If you click **OK**, the fieldset appears in the Custom category. It is labeled as "Custom (not saved)" and is not visible to other users. It will remain available to you for this session. Once you log out of the current session, the temporary fieldset will be deleted. You can only have one temporary custom fieldset at a time.

Note: Ok will only save temporarily the custom fieldset. To execute the search with the customize fieldset just created, click **Go**.


When ***user** is included in the Selected Fields list of a custom fieldset, the created or defined fields display.



Saved Searches/ Filters

This topic applies only to Search page

Saved Search / Filter functionality provides a prompt access to searches previously saved in Classic Search page and system filters predefined by Logger. Kindly note this functionality tab will only be enabled if user has rights. For more information, see ["Users/Groups" on page 495](#).

To load filter/ saved search

1. Click the 
2. Select one of the following tabs:
 - **Filters:** It shows the filters by category (system filter), type, description.
 - **Saved Search:** It displays the saved searches by type, description, start/end date, start end/time, search time field, and local only search.
3. Look for the saved query/ filter in the window recently opened. Scroll down the list or type a word to speed up your search.







As you type, search items will be limited based on the matching text. Categories and types can be collapsed as needed. You can also sort the information in ascendant or descendant order by clicking the arrow next to each column title.
4. Click one of the following icons:
 -  **Load + Close:** To load a query in the search query field, click the icon. Start and end date, search settings, and search type (Logger Receipt Time or End Time) are predefined in this search.
 -  **Close:** To cancel the operation, click the icon.


Page Views

This topic applies only to Search page


Each event is available in its raw form or parsed data. By default, the parsed data is displayed. The view menu bar allows the user to review the data in 5 different ways as described below .



1.  **Hide/ Show Histogram:** It allows to hide the histogram information displayed in all views by default.
2.  **Show/ Hide RAW:** It shows raw data for all events. This view is only enabled when **grid view** is active.
3.  **RAW view:** It only exhibits the **Logger** and **Raw Data** along with **Event Time, Receipt Time** and **DeviceReceiptTime**.
4.  **Column View:** It displays events per columns.
5.  **Grid View:** This is the default view where events are distributed per rows. It permits comparison between specific (CEF and non-CEF) events in a pivot table format. To view the event raw data, click the  icon on each event. Within this view, you can also access the following windows:

- **Event Details:** This emergent window appears by clicking on the event and it shows the **raw event**, **agent**, **destination**, **device**, **deviceCustom**, **extra fields** and **root** data. In this window, the following icons  allow the user to easily review first, previous, next and last event information as well as show/ hide null fields, and expand / collapse categories. This emergent window can be closed at any time.

Note: If more than 1 event is selected in the grid view, this window is not displayed. Logger will enable the **Compare Events** window instead.

-  **Compare Events:** This emergent window compares from 2 to 10 events information per column. This window can be minimized, maximized, or closed as appropriate.

Histogram

Results are presented in a histogram view emphasizing the time information (X axis) and the quantity of events (Y axis). Logger also permits to narrow the results on the table by clicking on the histogram columns. To analyze the information from several items on the train, make sure these are in a consecutive order. Otherwise, Logger only shows the data of the last column selected.

Charts

This topic applies only to Search page

Search results can also be displayed in a chart format. When the user executes a search with a chart operator, Logger delivers a chart along with a correspondent table of events distributed by category. When this format is enabled, view menu bar is replaced with the following icons:

Display Limit: 

The following chart types are supported by Logger 7.0:

1. Column
2. Bar
3. Donut
4. Area
5. Line
6. Stacked Column
7. Stacked Bar

Multi-Series Charts:

A multi-series chart combines multiple aggregation function values along the Y-axis in a single chart. Stacked column and stacked bar charts are available for multi-series search. Donut chart view is grayed out (not available) for this task.

Display Limit:

It limits the amount of events shown in the chart from 1 to 100 charts. To narrow the results, add a number < total number of events in the **display limit** field. To apply the updates, it is only needed to click enter or click outside the window.

Elements of a Search Query

A simple search query consists of a query expression, a time range, a search time field, and a field set. An advanced Logger search query can also include constraints that limit the search to specific device groups, storage groups, and peer Loggers.

- [Query Expressions](#) 78
- [Search based on Event Time](#) 85
- [Time Range](#) 86
- [Fieldsets](#) 89
- [Constraints](#) 91
- [Syntax Reference for Query Expressions](#) 93

Query Expressions

A query expression is a set of conditions used to select events when a search is performed. An expression can specify a very simple term to match such as "login" or an IP address; or it can be more complex enough to match events that include multiple IP addresses or ports, and that occurred between specific time ranges from a specific storage group.

Specify the query in the Search text box by using the following syntax:

<Indexed Search> | <Search Operators>

The query expression is evaluated from left to right in a pipeline fashion. First, events matching the specified Indexed Search portion of the query are found. The search operator after the first pipe (|) character is then applied to the matched events followed by the next search operator, and so on to further refine the search results.

The search results table and the histogram display the events that match the query as they are found. As additional events are matched, the search results table and the histogram are refreshed. Aggregation

operators such as **HEAD** and **TAIL**, require a query to finish running before search results can be displayed. See ["Search Operators" on page 524](#) for more information.

- The indexed search section of the query is described in ["Indexed Search Portion of a Query" below](#).
- The search operator portion of the query is described in ["Search Operator Portion of a Query" on page 85](#).
- Additional points to take into consideration when writing queries are described in ["About Building Search Queries" on page 111](#).

Indexed Search Portion of a Query

The Indexed Search section of the query uses fields to search for relevant data quickly and efficiently. You can use a search expression to specify keywords to search for in the event text or to search using field-based expressions in a Boolean format.

Keyword Search (Full-text Search)

Keywords are simply the words you want to search for, such as **failed**, **login**, and so on. You can specify multiple keywords in one query expression by using Boolean operators (**AND**, **OR**, or **NOT**) between them. Boolean expressions can be nested, for example, **(John OR Jane) AND Doe***. If you need to search for the literal occurrence of **AND**, **OR**, or **NOT** (in upper-, lower-, or mixed case), enclose them in double quotes ("") so the search engine does not interpret them as operators.

Note: Although the Boolean operators **AND**, **OR**, and **NOT** can be specified in upper-, lower-, or mixed case when used as an operator, Micro Focus recommends that you use uppercase for ease of reading the query.

Guidelines for Writing Keyword Search Expressions

Follow these guidelines when specifying keyword search expressions:

- Follow the requirements described in ["Syntax Reference for Query Expressions" on page 93](#).
- Additional points to take into consideration when writing queries are described in ["About Building Search Queries" on page 111](#).
- Keyword search is not case sensitive.
- Use Boolean operators (**AND**, **OR**, or **NOT**) to connect multiple keywords. If no Boolean operator is specified between two keywords, the **AND** operator is applied by default. Also, use the Boolean operators to connect keywords to fields you specify.
- Use double quotes ("") to enclose a single word for an exact match. Otherwise, the word is treated as **<search string>***. For example, to search for **log**, type "log". If you type **log** (without the double quotes), the search will match all words that begin with log; for example, log, logger, logging, and so on.

- When specifying Boolean operators (**AND**, **OR**, or **NOT**) as keywords, enclose them in double quotes (“ ”). For example, “AND”.
- Use the backslash (\) as an escape character for \, “, and *. However, the backslash will not escape these characters if the keyword is enclosed in double quotes.

The following table summarizes how special characters are treated in a keyword search.

Using Special Characters in Keyword Searches

| Character | Usage | | | | | | | | | | | | |
|---|--|--------|-------|--------|--|---------|----------|--------|--|------|-----------|--|--|
| Space Tab Newline , ; () [] { } “ * | <p>You cannot specify keywords that contain the characters in the left column. Therefore, to search for a phrase such as <i>failed login</i>, enter “failed” AND “login”.</p> <p>Note: * is a valid character for wildcard character searches.</p> | | | | | | | | | | | | |
| = : / \ @ - ? # \$ & _ % > < ! | <p>To specify a keyword that contains any of the characters in the left column, enclose the keyword in double quotes (“ ”). You can also specify an asterisk(*) at the end of the keyword for an exact match.</p> <p>Examples:</p> <ul style="list-style-type: none">• “C:\directory”• “result=failed” | | | | | | | | | | | | |
| * asterisk | <p>You can use the wildcard character asterisk(*) to search for keywords, however, the wildcard cannot be the leading character in the keyword. Therefore, the following usages are valid:</p> <table><tr><td>log*</td><td>log*</td><td>log*</td><td></td></tr><tr><td>log*app</td><td>log*app*</td><td>"log*"</td><td></td></tr></table> <p>However, the following usages are not valid:</p> <table><tr><td>*log</td><td>*log*app*</td><td></td><td></td></tr></table> | log* | log* | log* | | log*app | log*app* | "log*" | | *log | *log*app* | | |
| log* | log* | log* | | | | | | | | | | | |
| log*app | log*app* | "log*" | | | | | | | | | | | |
| *log | *log*app* | | | | | | | | | | | | |

Field-Based Search

The Logger schema contains a predefined set of fields. You can add fields that are relevant to the events you collect on your Logger to its schema. A field-based search can only contain fields in Logger’s schema. ["Adding Fields to the Schema" on page 431.](#)

The Logger indexing capability allows schema **fields** to be indexed. Logger’s search operation and reports utilize the indexed fields to yield significant search and reporting performance gains. Although you can include both indexed and non-indexed fields to a search query, search and reporting performance will be much faster if all fields in a query are indexed. For more information and a list of fields you can index, see ["Indexing" on page 146.](#) For discussion on field-based query performance, see ["Performance Optimizations for Indexed Fields in Queries" on page 102.](#)

- You can specify multiple field conditions in one query expression by using the listed operators between them. The conditions can be nested; for example:
(name=“John Doe” OR name=“Jane Doe”)AND message!=“success”

Note: If a query includes the Boolean operator **OR** and the metadata identifiers (discussed in ["Constraints" on page 91](#)), the expression to be evaluated with **OR** must be enclosed in parentheses, as shown in this example:

```
(success OR fail) _storageGroup IN ["Default Storage Group"]
```

If the expression is not enclosed in parentheses, an error message displays.

- Any literal operator in the table can be specified in upper-, lower-, or mixed case. To search for these words as literals in events, enclose them in double quotes (“”). For example:

```
message CONTAINS "Between"
```

- When using a query operator to search for full or partial IPv6 addresses, the address must be in canonical format. Do not use IPv4-mapped IPv6 addresses. See ["Limitations on Field-Based Search Operators" on page 85](#) for details.
- To determine the data type of a field, see ["Default Fields" on page 333](#).
- To determine the size of a custom field, see ["Custom Fields" on page 335](#).

Field Based Search Operators

The field operators you can use in a query expression are listed in the table below. In addition to the field operators, you can use search operators, as discussed in ["Search Operator Portion of a Query" on page 85](#).

Field-Based Search Operators

| Operator | Example | Notes |
|----------|--|--|
| AND | name="Data List" AND message="Hello" AND 1.2.3.4 | Valid for all data types. |
| OR | (name="TestEvent" OR message="Hello") AND type=2 AND 1.2.4.3 | Valid for all data types. |
| NOT | NOT name="test 123" | Valid for all data types. |
| != | destinationPort != 100 message!="failed login" message!=failed*login (* means wildcard) "test" message!=failed*login (* is literal in this case) | Valid for all data types. |
| = | bytesIn = 32 message="failed login" message="failed*login" (* means wildcard) | Valid for all data types. The size of each field in the schema is predetermined. If the string you are searching for is longer than the field-length, you should use a STARTSWITH rather than an = search, and include |

Field-Based Search Operators, continued

| Operator | Example | Notes |
|------------|--|--|
| | | no more than the number of characters in the field size. To determine the size of a default field, see "Default Fields" on page 333 . To determine the size of a custom field, see "Custom Fields" on page 335 . |
| >* | bytesIn > 100 | Valid for all data types. |
| <* | startTime < "\$Now - 1d" | * These operators evaluate the condition lexicographically. For example, deviceHostName BETWEEN AM AND EU searches for all devices whose names start with AM, AMA, AMB, AN, AO, AP and so on, up to EU. Therefore, any device whose name starts with AK, AL, and so on is ignored. Similarly, devices with names EUA, EUB, FA, GB, and so on will be ignored. |
| >=* | endTime >="01/13/2015 07:07:21" endTime >="2015/13/01 00:00:00 PDT" endTime >="Sep 10 2015 00:00:00 PDT" | |
| <=* | startTime <=" \$Now - 1d" | |
| IN* | priority IN [2,5,4,3] destinationAddress IN ["192.0.2.4", "192.0.2.14"] _deviceGroup IN ["DM1"] _storageGroup NOT IN ["Internal Event Storage Group", "SG1"] _peerLogger IN ["192.0.2.10", "192.0.2.11"] | |
| BETWEEN* | priority BETWEEN 1 AND 5 | |
| STARTSWITH | message STARTSWITH "failed" | Valid for string (text) data types only. |
| ENDSWITH | message ENDSWITH "login" | Valid for string (text) data types only. |
| CONTAINS | message CONTAINS "foobar" | Valid for string (text) data types only. Note: This operator requires a full canonical IPv6 address. Do not use an IPv6 address fragment. |
| IS | sessionId IS NULL sessionId IS NOT NULL | Valid for all data types. |

Field-Based Search Operators, continued

| Operator | Example | Notes |
|----------|--|---|
| INSUBNET | <pre>sourceAddress insubnet "192.0.2.*" agentAddress insubnet "2001:db8::-2001:db8::ffff:ffff:ffff" agentAddress insubnet "192.0.*.*" AND NOT deviceAddress insubnet "192.0.2.*" agentAddress insubnet "192.0.1.0-192.0.2.0" AND NOT destinationAddress insubnet "198.51.100.0/24" agentAddress insubnet "192.0.*.*" AND NOT deviceAddress insubnet "192.0.2.*" agentAddress insubnet "192.0.2.0/24" AND deviceAddress insubnet "198.51.100.0/24" deviceAddress insubnet "192.0.2.0/24" OR destinationAddress insubnet "2001:db8::/32" agentAddress insubnet "2001:db8::/32" OR sourceAddress insubnet "192.0.2.0/16"</pre> | <p>Filters IPv4 and IPv6 addresses based on subnets in address fields such as sourceAddress, deviceAddress, agentAddress and destinationAddress.</p> <p>You can specify a subnet in one of the following ways:</p> <ul style="list-style-type: none"> • In CIDR notation: "address/prefix-length", such as 192.0.2.23/24. • As an address range: address1-address2, such as 192.0.2.0-192.0.2.255. • As a wildcard expression where one or more asterisks replace data on the right-hand side of an address, such as 192.0.2.*. <p>For more examples of searching for IPv6 addresses using INSUBNET, see "Using the INSUBNET Operator to Search for IPv6 Addresses" on page 122</p> |

Field-Based Search Expression Guidelines

Follow these guidelines when specifying field-based search expressions:

- Follow the requirements described in ["Syntax Reference for Query Expressions" on page 93](#).
- Addition points to take into consideration when writing queries are described in ["About Building Search Queries" on page 111](#).
- For faster searches, follow the recommendations in ["Searching for Rare Field Values" on page 117](#) and ["Tuning Search Performance" on page 117](#).
- By default, field-based search is case sensitive. You can change the sensitivity from the Field Search Options section of the Configuration | Search > Search Options page. For more information, see ["Global Search Options" on page 328](#).

- You can specify any predefined Logger schema field. For example, **cat = /Monitor/CPU/Usage**. For a complete list, see ["Indexing" on page 146](#).
- You can specify any custom field you have added to the schema. For example, **SSN=333-333-3333**. For more information about custom schema fields, see ["Adding Fields to the Schema" on page 431](#).
- You cannot specify user-defined fields created through a predefined or user-defined parser in the Indexed Search portion of a query. (The Indexed Search portion of a query is the expression before the first pipeline character.)

A query expression (Indexed Search | Search Operators) is evaluated from left to right in a pipeline fashion. By design, a parser—predefined or user-defined—is applied to an event when the Search Operators are processed in a search query. Therefore, field creation when a parser is applied to an event occurs later than the Indexed Search stage. As a result, you cannot specify these fields in a field-based search query.

For example, the Apache Access Log parser creates the field **SourceHost**. You cannot specify the following query expression:

```
SourceHost="192.0.2.0"
```

However, you can use this field after the first pipeline, as shown in this example.

```
| where SourceHost="192.0.2.0"
```

Or, if you want to search only the Apache Access Logs for **SourceHost="192.0.2.0"**, you can specify this expression:

```
| where parser="Apache Access Log" and clientIP="192.0.2.0"
```

Additionally, you can run a full-text (keyword) search on **"192.0.2.0"**, as follows:

```
"123.456.789" | where SourceHost="192.0.2.0"
```

- If an event field contains data of an unexpected type (for example, a string when an integer is expected), the data is ignored. Therefore, search for that data value will not yield any results. For example, if the port field contains a value 8080A (alphanumeric) instead of 8080 (numeric), the alphanumeric value is ignored. The data types of the schema fields are available from the Configuration | Search > Default Fields page. For more information on how to view this information, see ["Default Fields" on page 333](#).
- For optimal search performance, make sure that event fields on ALL peers are indexed for the time range specified in a query. If an event field is indexed on one system but not on its peers for a specific time range, a distributed search will run slower on the peers. However, it will run at optimal speed on the local system. Therefore, the search performance in such a setup will be slow.
- For faster report generation, ALL fields of a report (including the fields being displayed in the report) need to be indexed. That is, in addition to the fields in the **WHERE** clause of the query, the fields in the **SELECT** clause also need to be indexed.

Limitations on Field-Based Search Operators

When using a query operator (such as **STARTSWITH**, **ENDSWITH**, and **INSUBNET**) to search for full or partial IPv6 addresses, the address must be in canonical format (as specified in [RFC 5952](https://tools.ietf.org/html/rfc5952)). Do not use IPv4-mapped IPv6 addresses.

For queries using the **CONTAINS** operator, use only the full IPv6 address. Do not use an IPv6 address fragment.

For more information on canonical format, refer to <https://tools.ietf.org/html/rfc5952>, section 4: [A Recommendation for IPv6 Text Representation](#).

Search Operator Portion of a Query

The Search Operators portion of the query enables you to further refine the data that matched the indexed search filter. See "[Search Operators](#)" on [page 524](#) for a complete list of search operators and examples of how to use them.

The **rex** search operator is useful for syslog events (raw or unstructured data) or if you want to extract information from a specific point in an event, such as the 15th character in an event. Other operators such as **head**, **tail**, **top**, **rare**, **chart**, **sort**, **fields**, and **eval** are applied to the fields you specify or the information you extract using the **rex** operator.

Search based on Event Time

This topic applies to both Classic Search and Search page

Search based on event time allows the user to easily find an event by executing a search based on the time this one actually occurred or was received in Logger. When executing a search or an operation that depends on it, search type parameter is added and could be one of the following:

- **End time (Event Time):** Look for events that occurred within the time range specified.
- **Logger Receipt time:** Look for events received by Logger within the time range specified.

Note: Events received by Logger before upgrading to 7.0 version cannot be searched based on event time functionality.

Enable / disable:

It only applies to non-indexed fields searches

By default, this feature is enabled. However, the user has the possibility of disabling it at a global scale during the ingestion and replace the event time by the receipt time for all the events sent to Logger. To disable it, access the Logger properties file and set the following:
receivers.timeparsing.enable=false. Then, restart the receivers process.

Search end time and CEF

End time search is only supported in CEF events. For non CEF events, Logger uses the receipt time as search time.

Note: Set the receiver as CEF in the source type to properly use the search end time functionality.

In CEF events, the event time is displayed as EndTime field ("end" in the raw event). If this is not available, Logger uses the ReceiptTime field instead ("rt" in the raw event). In case none of the values ("rt" and "end") are available, Logger will use the ReceiptTime as the default option.

Searches based on event time for CEF events must contain millisecond values for EndTime ("end") or ReceiptTime ("rt") fields. Other search formats for this search type functionality are not currently supported by Logger.

Time Range

This topic applies to both Classic Search and Search Pages

An event is timestamped with the receipt time when it is received on the Logger. By default, a search query uses the receipt time to search for matching events. However, user can also use the event time as a search option.

Under most circumstances, the Logger receipt time is same as the event time. However, the event time and the Logger receipt time for an event can be different because there is usually a small lag between the time an event leaves a device and it is received at the Logger. If the device's clock is ahead or behind the Logger clock, the lag or lead can be significant.

A search operation requires you to specify the time range within which events would be searched. You can select from many predefined time ranges or define a custom time range to suit your needs.

When defining a time range for your query, be sure to take the information in ["Impact of Daylight Savings Time Change on Logger Operations" on page 464](#) into consideration.

Predefined time range: When you select a predefined time range such as "Last 2 Hours" or "Today", the time range is relative to the current time. For example, if you select "Last 2 Hours" at 2:00:00 PM on July 13th, events from 12:00:00 to 2:00:00 PM on July 13th will be searched. If you refresh your search results at 5:00:00 PM on the same day, the time window is recalculated. Therefore, events that match the specified criteria and occurred between 3:00:00 and 5:00:00 PM on July 13th are displayed.

Custom time range: You can specify a time range in a 24-hour format to suit your needs. For example, a custom time range is:

Start: 8/13/2015 13:36:30

End: 8/13/2015 22:36:30

By default, the end time for a custom time range is the current time on your Logger and the start time is two hours before the current time.

You can also use variables to specify custom time ranges. For example, a dynamic date range might start at \$Now - 2h (two hours ago) and end at \$Now (the current time). The dynamic search is relative to when the query is run. Scheduled search operations use this mechanism to search through newer event data each time they are run.

The "Dynamic" field in the user interface enables you to specify the dynamic time. Following is a typical example of a dynamic search that limits results to the last two hours of activity:

Start: \$Now - 2h

End: \$Now

The syntax for dynamic search is:

<current_period> [+/- <units>]

Where **<current_period>**, such as **\$Now**, either stands alone or is followed by either a plus ('+') or minus ('-') and a number of units, such as 2h for two hours. The **<current_period>** always starts with a '\$' and consists of a word, case-sensitive, with no spaces, as shown in the table "Current Period" below. The **<units>** portion, if given, consists of an integer and a single, case-sensitive letter, as shown in the table "Units" below.

Current Period

| Period | Description |
|----------------|---|
| \$Now | The current minute |
| \$Today | Midnight (the beginning of the first minute) of the current day |
| \$CurrentWeek | Midnight of the previous Monday (or same as \$Today if today is Monday) |
| \$CurrentMonth | Midnight on the first day of the current month |
| \$CurrentYear | Midnight on the first day of the current year |

Units

| Unit | Description |
|---------------|---|
| m (lowercase) | Minutes (Do not confuse with 'M', meaning months) |
| h | Hours |
| d | Days |
| w | Weeks |
| M (uppercase) | Months (Do not confuse with 'm', meaning minutes) |

Time Stamps in Logger

This topic applies only to Classic Search page

Events consist of a receipt time, event time, a source (host name or IP address), and an un-parsed message portion.

End Time is the time at which the activity related to the event ended.

Logger Receipt Time is the time the events are written to the Storage Group (disk). All events are timestamped with the receipt time when received on the Logger.

Note: Under most circumstances, the Logger receipt time is same as the event time. However, the event time and the Logger receipt time for an event may be different because there is a small lag between the time an event is received and when it is stored on the Logger. Other things may also cause some lag. For example, if event time parsing is enabled in file receiver, the receipt time may lag behind event time.

- Logger uses the receipt time field to find matching events when forwarding as well as for storage retention and archives.
- The Logger receipt time of an event is used to determine whether an event will be forwarded to a destination when a forwarder filter specifies a time range by which events are evaluated for forwarding.
- Logger uses the receipt time of an event to determine its archival day.
- Search results are sorted based on the search time field selected.
- The histogram is based on the search time field selected.
- The default fields are automatically indexed. For the remaining fields, Logger uses the receipt time of an event and the time when a field was added to the index to determine whether that event will be indexed. If the receipt time of the event is equal to or later than the time when the field was added to the index, the event is indexed; otherwise, it is not.

In addition to the event time and the receipt time, you may see several other time stamps in Logger events, including the following:

Agent Receipt Time is the time the Connector received the event. Logger does not use this field but you can search it.

Device Receipt Time is the time the event related to the activity was received. Logger use this field as backup when executing search based on even time if end time is not present in the CEF event.

End Time is the original time of the event on the device. Logger use this field as default when executing search based on event time.

Manager Receipt Time is the time the ESM received the event. Logger does not use this field, but you can search it.

Fieldsets

This topic applies to both Classic Search and Search Pages


A fieldset determines the fields that are displayed in the search results for each event that matched a search query. By selecting the fieldset, you select which fields you see in the search results. For information, see ["Changing the Displayed Search Results Using Field Sets" on page 128](#). You can use a predefined fieldset or create your own.

Predefined Fieldsets

The system provides a number of predefined fieldsets.

To view the list of available fieldsets:

1. Click the down-arrow in the Fields dialog box. The System Fieldsets list is displayed.



To display the search results using a specific fieldset:

1. Click the fieldset from the drop-down list.

Note: Only fields available for matched events are displayed in a Search Results display (or the exported file). Therefore, even if you select the **All Fields** fieldset, you might not see all fields displayed in the search results, only the fields included in the events found by the search.

For more information about fieldsets, see ["Managing Fieldsets" on page 333](#).

"User-Defined Fields" Fieldset

When you use a search operator that defines a new field, such as **rex**, **rename**, or **eval**, a new column for each field is added to the currently selected display. These newly defined fields are displayed by default. The **User Defined Fields** fieldset enables you to view only the newly-defined fields.

"Raw Event" Fieldset

The **Raw Event** fieldset displays the whole raw syslog event in a column called `rawEvent`, with the event formatted to fit in the column.

Although the Raw Event field is most applicable for syslog events, you can also display the raw event associated with CEF events in the `rawEvent` column. To do so, make sure the connector that is sending events to the Logger populates the `rawEvent` field with the raw event.

Note: To see the raw events in the `rawEvent` column, enable the Search Option, "Populate `rawEvent` field for syslog events". See ["Global Search Options" on page 328](#) for more information.

Generating Search Results

If **Raw Event** is selected as the only system fieldset in the search, results are displayed. However, these results cannot be exported as Logger generates an empty report.


When exporting search results, Logger discards automatically the **raw messages**. All other data selected by the user is used to create the export file. Moreover, fieldsets that contains only **rawMessages**, displays no results.

Custom Fieldsets

This topic applies only to Classic Search page

You can create your own field set by selecting **Customize** from the **Fields** pull-down menu. To add a fieldset, drag and drop a field to the **selected fields** column.

Use these buttons to edit the custom field set.



You can save the custom field set or use it only for the current session. If you click **OK**, the field set appears in the Custom category. It is labeled as "Custom (not saved)" and is not visible to other users. It will remain available to you for this session. Once you log out of the current session, the temporary field set will be deleted. You can only have one temporary custom field set at a time.

If you click **Save**, the field set appears under the Shared Fieldsets category and is visible and available to the other users, as shown in the following figure. After a field set is saved, you can edit and delete it.

When saving a custom field set, you can specify it as the default for this system. If you do so, it is the default field set for all users on that system. If do not select it as the default, the field set is used only for your search results and does not affect other users connecting to the same system. For information about deleting custom field sets, see ["Managing Fieldsets" on page 333](#).

Note: Field sets are not included in the saved filter definition.

The ***user** field, shown below, controls the display of fields defined by search operators (**rex**, **rename**, **extract**, or **eval**) as well as the fields created when a parser is applied to an event. When ***user** is included in the Selected Fields list of a custom field set, the created or defined fields display.

Constraints

Using constraints in a query can speed up a search operation as they limit the scope of data that needs to be searched. Constraints enable you to limit a query to events from one or more of the following:

- Particular device groups
- Particular storage groups
- Specific peers

For example, you might want to search for events in the SG1 and SG2 storage groups on the local system only, or for events on specific peers.

For information about storage groups and peers, see ["Storage" on page 404](#), ["Device Groups" on page 345](#), and ["Peer Nodes" on page 450](#).

Follow these guidelines when specifying constraints:

- Use the following operators to specify constraints in a search query expression:

| Metadata Identifier | Example |
|----------------------------|--|
| <code>_deviceGroup</code> | <code>_deviceGroup IN ["DM1", "HostA"]</code> where DM1 is a device group, while HostA is a device. Note: You can use this field to specify individual devices. |
| <code>_storageGroup</code> | <code>_storageGroup IN ["Internal Event Storage Group", "SG1"]</code> |
| <code>_peerLogger</code> | <code>_peerLogger IN ["192.0.2.10", "192.0.2.11"]</code> |

- If a query includes the Boolean operator OR and metadata identifiers, the expression to be evaluated with OR must be enclosed in parentheses, as shown in this example:

(success OR fail) _storageGroup IN ["Default Storage Group"]

If the expression to be evaluated with OR is not enclosed in parentheses, an error message is displayed on the user interface screen.

- When specifying multiple groups in a constraint, ensure that the group names are enclosed in square brackets; for example, `_storageGroup IN ["SGA", "SGB"]`.
- You can apply constraints to a search query by:

- a. Typing the constraint in the Search text box.

Once you type `"_s"` (for storage group), `"_d"` (for device group), or `"_p"` (for peer) in the Search text box, Search Helper automatically provides a drop-down list of relevant terms and operators from which you can select.

Caution: If a search query contains constraints and a regular expression, make sure that the constraints are specified before the regular expression. For example, `_peerLogger IN ["192.0.2.10"] name contains abc | REGEX=":\d31"`

- b. Selecting Storage Groups or peers from the Advanced Search tool. To access the Advanced Search tool, click **Advanced Search** beneath the text box where you type the query. See ["Using the Advanced Search Builder" on page 98](#).

Syntax Reference for Query Expressions

This topic applies to both Classic Search and Search pages

To create valid and accurate query expressions, follow these requirements.

Query Syntax Requirements

| Behavior | Full Text Search | Field Search | Regular Expression |
|---|---|--|---|
| Case sensitivity | Insensitive (Cannot be changed.) | Sensitive (Can be changed using Tuning options. See "Global Search Options" on page 328.) | Insensitive (Can be changed using Tuning options. See "Global Search Options" on page 328.) |
| Escape character | \ Use to escape \. You cannot escape any other character. | \ Use to escape \, ", and *. Examples: name=log\\ger (matches log\ger) name=logger* (matches logger*) | \ Use to escape any special character. Example: To search for a term with the character "[": REGEX= "logger\[|
| Escaping wildcard character | Cannot search for * Example: log* is invalid | Can search for * by escaping the character Example: name=log* is valid | Can search for * by escaping the character Example: name=log* is valid |
| Exact Match/Search string includes an operator or a special character | Enclose keyword in double quotes; Otherwise, keyword treated as keyword*. Example: log (matches log, logging, logger, and so on) "log" (matches only log) Tip: See the list of special characters that cannot be searched even when enclosed in double quotes, later in this table. | Enclose value in double quotes Example: message="failed login" | No special requirement. |

Query Syntax Requirements, continued

| Behavior | Full Text Search | Field Search | Regular Expression |
|--|--|---|--|
| Nesting, including parenthetical clauses, such as (a OR b) AND c | <p>Allowed</p> <ul style="list-style-type: none"> Use Boolean operators to connect and nest keywords. Metadata identifiers (_storageGroup, _deviceGroup, and _peerLogger), but can only appear at the top level in a query expression). If the query contains a regular expression, the metadata identifiers need to precede the regular expression. | <p>Allowed</p> <ul style="list-style-type: none"> Use any operator listed in the "Field-Based Search" on page 80 section to connect and nest field search expressions. Metadata identifiers (_storageGroup, _deviceGroup, and _peerLogger), but can only appear at the top level in a query expression. | <p>Multiple regular expressions can be specified in one query using this syntax:</p> <pre> REGEX= "<REGEX1>" REGEX="<REGEX2>" . . .</pre> |

Query Syntax Requirements, continued

| Behavior | Full Text Search | Field Search | Regular Expression |
|-----------|---|---|---|
| Operators | <p>Upper-, lower-, or mixed case Boolean operators—AND, OR, NOT. If an operator is not specified, AND is used.</p> <p>To search for literal operator AND, OR, NOT, in an event, enclose them in double quotes.</p> <p>Example: "AND", "OR", "Not"</p> <div> <p>Note: If a query includes the Boolean operator OR and the metadata identifiers <code>_storageGroup</code>, <code>_deviceGroup</code>, and <code>_peerLogger</code>, the expression to be evaluated with OR must be enclosed in parentheses</p> </div> <p>Example:</p> <pre>(success OR fail) _storageGroup IN ["Default Storage Group"]</pre> | <p>Use any operator listed in the "Field-Based Search" on page 80 section.</p> <ul style="list-style-type: none"> Unless a value is enclosed between double quotes, a space between values is interpreted as an AND. For example, name=John Doe is interpreted as John AND Doe. If an operator is not specified between multiple field expressions, AND is used. To search for literal operator, enclose the operator in double quotes. Examples: message STARTSWITH="NOT" message="LOGIN DID NOT SUCCEED" If a query includes the Boolean operator OR and the metadata identifiers <code>_storageGroup</code>, <code>_deviceGroup</code>, and <code>_peerLogger</code>, the expression to be evaluated with OR must be enclosed in parentheses. Example: <pre>(success OR fail) _storageGroup IN ["Default Storage Group"]</pre> | <p> and the operators described in "Time Range" on page 86.</p> <p>Use this operator to AND multiple regular expressions in one query expression.</p> |

Query Syntax Requirements, continued

| Behavior | Full Text Search | Field Search | Regular Expression |
|--|--|--|---|
| <p>Primary Delimiters:</p> <p>Space</p> <p>, ; () [] } " * > < !</p> | <p>You can search for keywords containing primary delimiters by enclosing the keywords in double quotes.</p> <p>Examples:</p> <p>"John Doe""Name=John Doe""www.microfocus.com"</p> | <p>You can search for these characters. Enclose value in double quotes if value contains any of these characters.</p> <p>Example: name="John*"</p> | <p>Cannot contain ^ in the beginning and \$ at the end as a matching character unless the regular expression you specify must look for an event that contains only the pattern you are specifying.</p> <p>Special regular expression characters such as \ and ? need to be escaped.</p> <p>Example:</p> <p> REGEX= "^test\$" will search only for events containing the word test.</p> |
| <p>Secondary Delimiters:</p> <p>= . : / \ - ? # \$ & _ %</p> | <p>You can also search for keywords containing secondary delimiters once you have configured the full-text search options as described in "Global Search Options" on page 328.</p> <p>Example:</p> <p>You can search for microfocus.com in a URL</p> <p>http://www.microfocus.com/apps by specifying microfocus.com as the search string.</p> | <p>You can search for these characters. Enclose value in double quotes if value contains any of these characters.</p> <p>Example: name="John"</p> | <ul style="list-style-type: none"> Cannot contain ^ in the beginning and \$ at the end as a matching character unless the regular expression you specify must look for an event that contains only the pattern you are specifying; for example, REGEX= "^test\$" will search for events containing the word "test" (without quotes) only. Special regular expression characters such as \ and ? need to be escaped. |
| Syntax | <p>keyword1 boolean_operator keyword2 boolean_operator keyword3 ...</p> | <p>field_name operator field_value</p> <p>(List of fields in the "Event Field Name Mappings" on page 603 section.)</p> <p>(List of operators in the "Field-Based Search" on page 80 section.)</p> | <p> REGEX="<REGEX1>" REGEX="<REGEX2>" ...</p> |

Query Syntax Requirements, continued

| Behavior | Full Text Search | Field Search | Regular Expression |
|---|---|--|---|
| Tab Newline { " * | <p>Cannot search for these characters.</p> <p>Examples:</p> <p>"John[Doe]" is invalid</p> | <p>No restrictions.</p> <p>Enclose special character in double quotes. Escape the wildcard character and double quotes.</p> <p>Example:</p> <p>name="John*\ \ "Doe" (matches John* "Doe")</p> | <p>No restrictions.</p> <p>Special regular expression characters such as ()[]{}" , and * need to be escaped.</p> |
| Time format, when searching for events that occurred at a particular time | <p>No specific format. The query needs to contain the exact timestamp string. For example, "10:34:35".</p> <div> <p>Note: The string cannot contain spaces. For example, "Oct 19" is invalid.</p> </div> | <p>Use this format to specify a timestamp in a query (including double quotes):</p> <p>"mm/dd/yyyy hh:mm:ss"</p> <p>Or</p> <p>"yyyy/mm/dd hh:mm:ss timezone"</p> <p>Or</p> <p>"MMM dd yyyy hh:mm:ss timezone"</p> <p>where</p> <p>mm = month</p> <p>dd = day</p> <p>yyyy = year</p> <p>hh = hour</p> <p>mm = minutes</p> <p>ss = seconds</p> <p>timezone = EDT, CDT, MDT, PDT</p> <p>MMM = First three letters of a month's name; for example, Jan, Mar, Sep, and so on.</p> <p>Use the <= and >= operators to narrow down the time range. Do not use = or !=.</p> | <p>No restrictions.</p> |

Query Syntax Requirements, continued

| Behavior | Full Text Search | Field Search | Regular Expression |
|----------|--|--|-------------------------------|
| Wildcard | <p>* Cannot be the leading character; only a suffix or in-between a keyword.</p> <p>Examples:</p> <ul style="list-style-type: none"> *log is invalid log* is valid lo*g* is valid | <p>* Can appear anywhere in the value.</p> <p>Examples:</p> <p>name=*log (searches for ablog, blog, and so on.)</p> <p>name="*log"</p> <p>name=*log</p> <p>(both search for *log)</p> | <p>* Can appear anywhere.</p> |

Using the Advanced Search Builder

This topic applies only to Classic Search page

The Advanced Search tool is a Boolean-logic conditions editor that enables you to build search queries quickly and accurately. The tool provides a visual representation of the conditions you are including in a query. You can specify keywords, field-based conditions, and regular expressions using this tool. You can also specify search constraints such as peers, device groups, and storage groups (see ["Constraints" on page 91](#)). This section describes how to use the tool.

- [Accessing the Advanced Search Builder](#) 98
- [Nested Conditions](#)100
- [Alternate Views for Query Building in Search Builder](#) 101


Accessing the Advanced Search Builder

This topic applies only to Classic Search page

To display the Advanced Search builder:




Click **Analyze > Classic Search** to open the search page, and then click **Advanced Search**, to the right of the **go** button.

The Advanced Search builder displays.



To build a new search query in the Advanced Search builder:

1. Click **Analyze > Classic Search** to open the search page, and then click **Advanced Search**.
2. Select the Boolean operator that applies to the condition you are adding from the top of Search Builder.
You can select these operators:

| Operator | Meaning |
|---|---------|
|  | AND |
|  | OR |
|  | NOT |

3. If you want to load a system or saved filter, or a saved search, click the  icon. Select the filter or the saved search from the displayed list and click **Load+Close**.


For more information, see ["Saving Queries, Creating Saved Searches and Saved Filters." on page 138](#) and ["System Filters/Predefined Filters" on page 140](#).

4. To add a keyword (full-text search) or field condition:
 - a. Locate the field you want to add under the Name column.
To specify a keyword (full-text search), use the **fullText** field under the Name column.

- b. Click the Operator column associated with the field, select the operator from the displayed list, and press **Enter**.
- c. Only operators applicable to a field are displayed in the list.
- d. In the Condition column associated with the field, enter a value and press **Enter**.

To edit a condition, right click on the condition for a pull-down menu that enables you to edit, cut, copy, or delete the condition.

Note: You cannot specify a range of IP addresses. Therefore, to search for multiple IP addresses in a range, use the **CONTAINS** operator and wildcard characters in the Condition column; for example, enter **192.0.2.***.


5. Repeat the steps above until you have added all the conditions.
6. If your search query will include a regular expression, type it in the Regex field.
7. If you want to constrain your search query to specific device groups, storage groups, and Loggers, click the  icon next to the constraint category. Select the relevant groups and Loggers. (To select multiple groups, hold the Ctrl-key down.)

You can specify devices or device groups in the Device Groups constraint.

The Logger constraint category is displayed only if Loggers are configured on your Logger.

If multiple values are selected for a constraint, those values are OR'ed together. For example, if you specify Device Group A, B, C, the query will find events in Device Group A, B, or C.

8. Click **Go**.

The query is automatically displayed in the Search text box and is ready to be run. You can also click the  icon to save the query (referred as Saved Filter or a Saved Search) for a later use. For more information about saving queries, see ["Saving Queries, Creating Saved Searches and Saved Filters." on page 138](#).

Nested Conditions

This topic applies only to Classic Search page

You can create search queries with nested conditions in Search Builder. To do so, click the operator under which you want to nest the next condition and add the condition as described in ["Accessing the Advanced Search Builder" on page 98](#).

To add a nested condition:

1. Select the new operator from the icons above the query.
2. Select a condition from the menu below the query.
3. Add an operator and a supported condition for the query, for example **deviceProduct =**

Microsoft.

4. Click **Go!**


Alternate Views for Query Building in Search Builder

This topic applies only to Classic Search page

By default, a tree view representation of the conditions is displayed, as shown in the previous figures in this section. You can change the view to a color-block scheme and the location where the fields you select are displayed. They can in the lower part of the screen or to the right of where conditions are displayed.

To change views:

Click **Display** in the Search Builder tool and select the view of your choice.





Search Analyzer

This topic applies only to Classic Search page

A query's performance is dependent on many factors such as load on the system, size of data to be searched, indexed or non-indexed fields included in the query, the complexity of a query (a large number of conditions, wildcard characters, nesting), and so on.

The Search Analyzer tool analyzes a query to determine if any of the fields included in the query are non-indexed for the time range specified and thus affect the query's performance.

You can run this tool as needed; for example, if a query runs slower than expected. You can use Search Analyzer on a query after you have run it or while building a query using the Search Builder. Click  to access the Search Analyzer tool.



- [Performance Optimizations for Indexed Fields in Queries](#)102

Performance Optimizations for Indexed Fields in Queries

Even though a search query includes indexed fields, you might not realize the performance gain you expect in these situations:

- When you include indexed and non-indexed fields in a query. Therefore, Micro Focus recommends that you identify the fields that you will most commonly use in queries and index all those fields. See ["Understanding Classic Search Field Colors" on page 73](#) to help you identify indexed and non-indexed fields within your query.
- When you include fields that are not super-indexed or field operators other than = in a needle-in-a-haystack search, your search speed may not see the expected performance increase for super-indexed

fields. For fastest results when searching for rare values, be sure to follow the recommendations in ["Searching for Rare Field Values" on page 117](#).


- When you perform search on data in a time range in which a currently indexed field (included in the query) was non-indexed.

For example, you index the “port” field on August 13th at 2:00 PM. You run a search on August 14th at 1:00 PM to find events that include port 80 and occurred between August 11th and August 12th. The “port” field was not indexed between August 11th and the 12th; therefore, the query runs slower.

- When you include a field in your search query that Logger is in the process of indexing. Therefore, allow some time between adding a field to the index and using it in a search query.

Regex Helper Tool



This topic applies only to Classic Search page

The Regex Helper tool  enables you to create regular expressions that can be used with the **rex** pipeline operator to extract fields of interest from an event. (For information about rex, see ["Search Operator Portion of a Query" on page 85](#) or ["Using the Rex Operator" on page 563](#).) This tool not only simplifies the task of creating regular expressions for the **rex** operator but also makes it efficient and error free.

The tool, which is only available for non-CEF events (unstructured data), parses **raw syslog events** into fields and displays them as a list. You select the fields that you want to include in the **rex** expression of a query. The selected fields are automatically inserted in a search query as a rex expression.

To use the tool, you need to perform the following steps:

Note: These steps are also depicted in the figure that follows the steps.

1. Enter a search query that finds events of interest to you. (For information about running a search, see ["Searching for Events" on page 108](#).)
2. Identify a syslog event that you want to analyze further. For example, in the shown figure, event #7 is the event we will analyze further.
3. Click the  icon (in the left-most column) for the identified event to expand it and display its raw event.
4. Click the  icon (next to the word **RAW**) to launch the Regex Helper tool.
5. Select the fields that you want to extract.
6. Click **OK**.

The rex expressions pertaining to the selected fields are automatically entered in the Search query box. In this example we want to extract the IP addresses from events. Therefore, the IPAddress_1 field is selected in the Regex Helper tool. (The Regex Helper tool assigns incremental labels if a data type appears more than

once in an event. For example, IP addresses are assigned IPAddress_1, IPAddress_2, IPAddress_3, and so on labels.)

Once the IP address is selected and you click **OK**, the **rex** expression that includes the regular expression for those IP addresses is displayed in the Search text box, as shown in the following example.


```
_deviceGroup in ["Logger Internal Event Device [Apache URL Access Error Log]"] | rex "(?<IPAddress_1>\d+\.\d+\.\d+\.\d+) \S+ \S+ \[(?<TimeStamp_1>\d+/\S+/\d+:\d+:\d+:\d+ \S+)\.?"
```

From this point, you can include additional pipeline operators in this query to create charts, identify the top five IP addresses, and so on. In the following example, the above query is modified to identify the top IP addresses.

```
_deviceGroup in ["Logger Internal Event Device [Apache URL Access Error Log]"] | rex "(?<IPAddress_1>\d+\.\d+\.\d+\.\d+) \S+ \S+ \[(?<TimeStamp_1>\d+/\S+/\d+:\d+:\d+:\d+ \S+)\.?" | top IPAddress_1
```

Search Helper

This topic applies only to Classic Search page



Search Helper is a search-specific utility that automatically displays relevant information based on the query currently entered in the Search text box.

Search Helper is available by default; if you do not want the Search Helper to display information automatically, click the **"Auto-open is ON"** link (in the Search Helper window). The link toggles to **"Auto-**

open is OFF". To access Search Helper once it has been turned off, click the down-arrow button to the right of the Search text box.

Search Helper displays auto-complete search functionality, a search history, a search operator history, a link to the help system, and suggested next operators.

- [Autocomplete Search](#) 105
- [Opening Filters and Saved Searches via Autocomplete](#) 106
- [Search History and Search Operator History](#) 107
- [Examples, Usage, Suggested Next Operators, and Help](#) 107

Autocomplete Search

This topic applies only to Classic Search page

The autocomplete functionality provides full-text keywords and field suggestions based on the text currently entered in the Search box. The suggestions enable you to select keywords, fields, field values, search operators, or metadata terms from a list instead of typing them in, thus enabling you to build a query expression more quickly.

When you start typing, the suggestion list displays many types of entries.

If the entered text is contained in both full-text keywords and schema fields, all of them are displayed in the suggested list.

If you type "|" (the pipeline character), the list of operators available on Logger are displayed.

The full-text keyword suggestions are obtained from the full-text keywords that are already indexed on your Logger.

If the Logger schema field is indexed, superindexed, or able to be indexed, an icon matching its index state displays to the left of the field name. See ["Understanding Classic Search Field Colors" on page 73](#) for more information.

Note: System-defined fields are not available as fields in the auto-complete . For more information about system-defined fields and Logger searches, see ["About Building Search Queries" on page 111](#) and ["Additional Fields in the Search Results" on page 126](#).

The full-text keywords and field values display a count next to each suggestion that indicates the number of the instances of the keyword or field value stored on Logger.

The count represents the number of values stored for a field. The count is dependent on many factors and may not be exact. It does not indicate how many events might match the query. Many factors determine the number of event matches, including the time range, search constraints, and search operators for the query.

Note: The autocomplete suggestions and counts are based on data stored on the local system only. Counts are reset when the Logger restarts. Peer data is not included.

Search Group filters (that restrict privileges on storage and device groups) are not enforced on the autocomplete list. Therefore, the list includes keywords, fields, field values, and counts of events in storage and device groups to which a user might not have privileges.


When an archive is loaded back on Logger, the autocomplete list does not include the full-text keywords or field values that were available before the events were archived. This happens because summary data is not archived along with the event data. Therefore, when the event data is loaded back from an archive, the archive data is not included in the summary.

Opening Filters and Saved Searches via Autocomplete

This topic applies only to Classic Search page

Logger 6.0 adds the autocomplete constants **\$filter\$** and **\$ss\$** to enable you to open Filters and Saved Searches directly from the search box.

If you type **\$filter\$** in the search box, the available Filters show up in the autocomplete. (Filters include only the query.) You can click a suggestion to select it or continue typing the filter name to narrow down the options. Once you select a filter from the autocomplete, Logger replaces the search box contents with the Filter definition.



If you type **\$ss\$** in the search box, the available Saved Searches show up in the autocomplete. (Saved searches include the query, the start date/time, the end date/time, local only, and so on.) You can click a suggestion to select it or continue typing the saved search name to narrow down the options. Once you select a saved search from the autocomplete, Logger replaces the search box contents with the Saved Search definition.

To use an autocomplete suggestion:

1. From the search autocomplete list, click the suggestion to move it up to the search box.
2. Click **Go!** to run that search, or continue typing to narrow your search further.

Search History and Search Operator History

This topic applies only to Classic Search page

The **Search History** displays recently run queries that match the currently entered search. Click a recent query to run it again. To see the search history, start typing a search or click the down-arrow next to the **Go!** button. The **Search Operator History** displays the fields used previously with the search operator that is currently typed in the Search text box. The Search Operator History only displays if you have previously used the operator you have currently typed to perform searches on this system. Click the operator to add it to your search.

All Fields

Last 10 minutes

Logger | where

Examples

... | where eventId is NULL
... | where eventId=10006093313 OR deviceVersion CONTAINS "4.0.6.4924.1"
... | where eventId >=10005985569 OR categories="/Agent/Started"

Auto-open is ON

Help

Display events that match the criteria specified in the where expression.

Usage
... | where <expression>

<expression> can be any valid field-based query expression, as described Indexed Fields.
more »

Suggested Next Search Operators
chart , sort


Examples, Usage, Suggested Next Operators, and Help

This topic applies only to Classic Search page

The **Examples** section lists examples relevant to the latest query operator you have typed in the Search text box.

The **Usage** section provides the syntax for the search operator.

The **Suggested Next Operators** section provides a list of operators that generally follow the currently typed query. For example, if you type **logger** |, the operators that often follow are **rex**, **extract**, or **regex**. You can select one of the listed operators to automatically append to the currently typed query in the Search text box. This list saves you from guessing the next possible operators and manually typing them in.

The **Help** section provides context-sensitive help for the last-listed operator in the query that is currently typed in the Search text box. Additionally, if you click the  icon, Logger online Help launches.

Searching for Events

This topic applies only to Classic Search page

The topics in this section explain how to search for events on Logger.

| | |
|--|-----|
| • Running a Search | 108 |
| • About Building Search Queries | 111 |
| • Search Hit Limits | 112 |
| • Concurrent Searches | 112 |
| • Searching Peers (Distributed Search) | 115 |
| • Tuning Search Performance | 117 |
| • Searching for Rare Field Values | 117 |
| • Searching for IPv6 Addresses | 120 |

Permissions and Prerequisites


Enable the following User Group permissions for Logger search users:

- Default Logger Search Group > Search > Search for events (local searches only)
- Default Logger Search Group > Search > Search for events on remote peers (for distributed searches)
- Default Logger Rights > Peers > View registered peers (to see peers)

Other permissions may also apply. See ["Setting Logger User Permissions" on page 510](#) for information.

Running a Search

You can use the options displayed on the search page to help create and run your search query.



Search Bar Legend

| Description | Description |
|-----------------------------|------------------------------|
| Load saved search or filter | Set time range |
| Save query | Open search history |
| Clear query | Start or cancel search |
| Open Search Analyzer | Open Advanced Search Builder |
| Update search options | Enter query |
| Select fieldset | Export search results |
| Search time field | Go to Search |

In addition to the options displayed on the search page, the Configuration > Search Options page allows you to tune search operations to suit your environment. See ["Global Search Options" on page 328](#). For information about concurrent and active searches, see ["Concurrent Searches" on page 112](#).

To search for events on Logger:


1. Open the **Analyze** menu and click **Classic Search**.
2. Click the down-arrow to view and adjust the search options. Use the default values or change them as needed:
 - **Local Only:** This option is only displayed when peers have been configured for your system. Local Only is checked by default. If you want to include peers in your search, uncheck the Local Only checkbox. If you do not see this checkbox, no peers have been configured on your Logger. See ["Searching Peers \(Distributed Search\)" on page 115](#) for more information.
 - **Field Summary:** Lists the selected CEF fields in the displayed events. By default, the selected fields include: deviceEventClassId, deviceProduct, deviceVendor, deviceVersion, and name; you can edit this list to suit your needs. Selecting this option enables the Discover Fields option. See ["The Field Summary Panel" on page 130](#) for more information about the Field Summary and Discover Fields options.
 - **Discover Fields:** Lists the non-CEF fields discovered in raw events. This option is only taken into consideration when Field Summary has been selected.
 - **Auto Refresh:** By default, search results are not automatically refreshed, and will expire in ten minutes (the default), or whenever the configured expiry time is reached (See ["Concurrent Searches" on page 112](#)). Select this option to have the Search results auto refresh for the selected search. You can select from the following refresh intervals: 30 seconds, 60 seconds, 2 minutes, 5 minutes, or 15 minutes.
 - **Sort:** Select Oldest Event First or Newest Event First, depending on how you want the search results to display.

3. **Fieldset:** By default, all fields (All Fields) are displayed in the search results. However, you can select another predefined field set or specify a customized field set. See ["Fieldsets" on page 89](#) for more information.
4. **Time Range:** By default, the query is run on the data received in the last ten minutes. Click the drop-down list to select another predefined time range or specify a custom time range. See ["Time Range" on page 86](#) for more information.
5. **Search type:** Allows to search based on the time events occurred or were receipt by the Logger. See ["Search based on Event Time" on page 85](#) for more information.
6. **Go to Search:** Enables to execute the search on Search Page. For more information, see ["Search page" on page 74](#).
7. Specify a query expression in the Search text box using one or more of the following methods.

Note: Refer to ["Keyword Search \(Full-text Search\)" on page 79](#), ["Field-Based Search" on page 80](#), and ["Searching for Rare Field Values" on page 117](#) for instructions, exceptions, and invalid characters before you create a query expression.

- a. Type the query expression in the Search text box. For information about building a query expression, including lists of applicable operators, see ["Elements of a Search Query" on page 78](#).
- b. When you type a query, Logger's Search Helper enables you to quickly build a query expression by automatically providing suggestions, possible matches, and applicable operators. See ["Search Helper" on page 104](#) for more information.
- c. Use these guidelines to include various elements in a search query:
 - For a complete list of fields in Logger schema, see ["Field-Based Indexing" on page 147](#).
 - Metadata terms (`_storageGroup`, `_deviceGroup`, `_peerLogger`)
Type `"_s"` (for storage group), `"_d"` (for device group), or `"_p"` (for Logger) in the Search text box to obtain a drop-down list of constraint terms and operators.
 - Regular expression term (`| REGEX=`)

Note: If your query expression includes multiple device groups and storage groups to which search should be constrained, make sure that the group names are enclosed in a square bracket; for example, `_storageGroup IN ["SGA", "SGB"]`.

- Click **Advanced** to use the Search Builder tool. (See ["Using the Advanced Search Builder" on page 98](#) for more information.) Also, use this option to specify device groups, storage groups, and Loggers to which search should be limited.
- d. Click the  icon to load a saved filter, a system filter, or a saved search. Select the filter or the saved search from the displayed list and click **Load+Close**.
For more information, see ["Saving Queries, Creating Saved Searches and Saved Filters." on page 138](#) and ["System Filters/Predefined Filters" on page 140](#).
 8. Optionally, you can start a concurrent search in a new browser tab. See ["Concurrent Searches" on page 112](#).

About Building Search Queries

Take the following points into consideration when writing search queries.

- Values in the system-defined fields, which include **Time**, **Device**, **Logger**, **parser**, **source**, and **sourceType**, cannot be searched by either keyword or field based searches. These fields are system-defined and do not exist in the raw event text. Therefore, searching for data in these fields returns no result.

While the parser field includes only the name of the parser and is not searchable, the parser defines fields based on its associated source type, and those fields are searchable. See ["Additional Fields in the Search Results" on page 126](#) for more information.

Note: Fields that are not searchable are not highlighted by mousing over them in the search results and are not marked as fields in the auto-complete search. See ["Refining a Search from the Search Results Table" on page 127](#) and ["Autocomplete Search" on page 105](#) for more information.

- Null values are not included in the Search results. For example, when performing a search on event data such as **NOT deviceCustomString1=bar**, the search returns results that match deviceCustomString1 not equal to "bar", but does not return events where the deviceCustomString1 value is NULL. You must explicitly call out NULL values with **<field> IS NOT NULL** or **<field> IS NULL**.

Note: Logger can be configured to make NOT search conditions include NULL values, by setting the search option **Include NULL field value in NOT operator results** to yes. For more information, see ["Global Search Options" on page 328](#).

- Data contained within a string that has already been tokenized cannot be searched. Searchable keywords are determined by the set of delimiters used to parse the raw text string into searchable units called tokens. These delimiters are controlled on the **Configuration > Search Options** page.
 - Logger includes the following primary delimiters for use during full-text (keyword) search: space, tab, newline, comma, semi-colon, (), [], { }, " , ' , and *. If only these primary delimiters are set to yes on the **Configuration > Search Options** screen and the raw event contains a string like this:
dmz : 10.9.9.9/20, then that entire string would be a single, searchable keyword.
 - The **Configuration > Search Options** screen also enables you to use secondary delimiters when searching. If the secondary delimiters are also set to yes, the following list of delimiters would further tokenize the string: =, ., , , /, \, @, -, ?, #, &, _ , > , and < . As a result, if the raw event contains the string:
dmz : 10.9.9.9/20, then the searchable keywords for this event, will be **dmz**, **10**, **9**, and **20**.

See ["Global Search Options" on page 328](#) for more information on setting primary and secondary delimiters.

Search Hit Limits

Logger displays more than one million rows in the search result.

Maximum Hit Limit for Search UI/ Search API

- The Logger default (set in the **Configuration > Search Options** page) is set to one million results, but a Logger admin can adjust this number from **one** to **ten million** results.

Other considerations

In regards to hit limit searching, take note of the following information:

- Logger performance may be affected as maximum row limit is increased.
- The maximum hit limits for Search UI and for searches via API are set from the **Configuration > Search > Search Options** page. You must have administrator permissions to edit this page. See ["Running a Search" on page 108](#)
- This option is named "**Max hits of Search UI**" in Logger UI. See ["Running a Search" on page 108](#)["Running Searches" on page 335](#)
- This option is named "**Max hits of Search API**" in API. See [Logger Web Services API](#).
- Search result export has the same maximum row limit as "**Max hits of Search UI**".

Concurrent Searches

Logger can now run concurrent searches from different browser tabs.

Using the **Active Searches** list on the Search home page, each user can see, reopen, or delete their searches at any time before they expire. Click the Session ID to start a new instance of the search in a new browser window. See ["Using the Active Search List" on the next page](#).

Maximum Concurrent Searches

How many concurrent searches you can realistically run depends upon your system load, search size, and other factors.

- The Logger default (set in the Configuration > Search Options page) is set to **0** (unlimited) running or finished searches, but a Logger admin can adjust this number to between **1** (no concurrent searches) and **1000**.
- This value limits the total number of searches in memory (running or finished) *by the Logger*, not by the user.

For example: For a Logger set to a maximum of ten concurrent searches, if user **A** is running six searches, user **B** will get an error if she tries to run more than four concurrent searches before some of the searches expire.

Expiry Time

The amount of time Logger holds the search results in memory before deleting them can also affect your search capacity. Each search you run consumes Logger storage space and CPU bandwidth.

- For this reason, the default expiry time for searches is **ten minutes**. A Logger admin can adjust this time to between **1-60** minutes.
- Clicking the Session ID opens the search results in a new tab and resets the expiry time. Using the pagination link (moving through the display pages) for a search also resets the expiry time.
- The expiry time affects both concurrent and standalone search results.

Other considerations

When running concurrent searches, take note of the following information:

- The maximum search and expiry time is set from the Configuration > Search > **Search Options** page. You must have administrator permissions to use this page. See ["Concurrent Search Options" on page 331](#).
- Administrators can view and delete ongoing searches from the Configuration > Search > **Running Searches** page. See ["Running Searches" on page 335](#).
- Dashboard searches, while they are running, are included in the search maximum, but are not listed in the Active Search list. (Dashboard searches expire 65 seconds after completing.) If a dashboard search becomes a problem, an Admin can cancel the dashboard update from the dashboard page.
- Maximum search limits do not apply to Saved or Scheduled searches.
- Maximum search limits do not apply to searches and queries run from the Reports tool. However, running Reports while also running Search queries will likely affect your performance.
- When configuring the maximum search limit, take in consideration the number of Logger Search Reports and the limit of concurrent searches. Maximum search limits do not apply to searches and queries executed from Reports Tool using MySQL Reports but it is impacted by the Logger Search Reports. Running Reports while also running Search queries will likely affect your performance.

Using the Active Search List

The Active Search list displays information about your running and completed searches, until they reach the configured expiry time, are reopened.

Note: If Auto refresh is enabled for a search, the search will regenerate new results at the interval you specify. Other reports are not affected. See ["Auto Refresh Search Results" on page 129](#).

Open the Active Search List

1. From the Search home page, start a search. See ["Running a Search" on page 108](#).
2. Click **Active Searches**. Your list of running and completed searches display.

Tip: If no active searches are running, the Active Search list is not available.

Reopen an active search

1. While a search is still active (has not yet expired), click **Active Search**.
2. Click the **session ID** for the search you want to reopen.

The search results display in a new browser tab.

Reset the expiry time for an active search

1. While a search is still active (has not yet expired), interact with the search in one of these ways:
 - Click a search histogram bar. See ["The Histogram" on page 124](#).
 - Page through the report using the search page tools on the bottom-right of the search. See ["Adjusting the Displayed Search Results" on page 123](#).

The search expiry time resets.

Delete an active search

1. While a search is still active (has not yet expired), click **Active Search**.
2. From the Active Search list, click the **X** to the far right for the report you want to delete. This deletes the search.

Closing the browser or logging out will also delete any unsaved searches.

Running Concurrent Searches

The Active Search list is enabled for viewing whenever you have running or unexpired searches in Logger memory.

Prerequisites

Users must be assigned to the following User Groups to access this feature:

1. To enable and configure concurrent searches:
 - Default System Admin Group
2. To run concurrent searches:
 - Default Logger Search Group

See ["Setting Logger User Permissions" on page 510](#)

Tip: Your Admin can tell you what the search limit and expiry time is for your Logger.

To run two or more concurrent searches:

1. From the **Analyze > Classic Search** main page, start a search. See ["Running a Search" on page 108](#)
2. While the first search is underway, open a new browser tab, and log into the same Logger.
3. Enter the next search string and start the second search.
4. Repeat steps 2 and 3 to run more concurrent searches, up to the maximum specified for your Logger.

Searching Peers (Distributed Search)

When you run a search query, by default, only your local Logger is searched for matching events. However, when specifying a query, you can select an option to run the search on the peer Loggers.

Note: Peer search communications have a timeout limit of 30 seconds. If you need to expand this time frame due to a slow responding peer nodes experience, contact support.

Prerequisites

To perform peer searches and view their search results, you need the following groups and permissions:

A user needs to belong to these user groups with the listed permissions set to perform peer searches and view their search results:

- Logger Search Group with “Search for events on remote peers” enabled.
- Logger Rights Group with the “View registered peers” enabled.

Follow these guidelines for searching across peers:

- Specify the peer Loggers to search, as described in ["Constraints" on page 91](#).
- Logger supports searching up to 100 peers in the same search.
- For best search performance and functionality, all peers must be on the latest version of Logger. Searches across peers are limited by the ability of the earliest version peer.
 - If an operator does not exist on a peer version, the query will not run on that peer.
 - Peers on earlier version will have the performance of that version, so search result for those peers will be returned more slowly.
- For best performance of non-pipeline searches, do not include the **regex**, **rex**, **parse**, **keys**, **transaction**, **extract**, or **lookup** search operators in the query.

- If the peer Loggers do not have the same storage or device group names, a search query operation skips searching for events for those groups on those peers.
- If there are custom schema fields in your Logger schema, those fields must exist on all peers. A search query containing those fields will not run across peers, and will return an error. See ["Adding Fields to the Schema" on page 431](#).
- When a Logger becomes unavailable during a search operation, error messages are displayed. The displayed message varies depending on the error detected. This is most likely because there is a problem with the network or the peer is down. In some cases it may be because there is an issue with the peering relationship. The error messages may still display for the search that was in progress even after the problem is fixed. However, you can ignore such messages if they go away when you run a new distributed search. For more information about peers, see ["Peer Nodes" on page 450](#).
- Using search heads enables faster peer searches for searches that use search operators, particularly aggregation operators, such as chart, sort, top. For best search performance when writing queries to be executed on a search head, specify all peers to be searched in the query and exclude the local Logger. See ["Setting up Search Heads for Faster Peer Searches" on page 32](#).

Note: Peer search speed improvements gained by using search heads apply only to searches run through the user interface. Using search heads does not improve the speed of scheduled searches or searches run through Logger Web Services.

Example queries for searching across peers:

Search that sorts five fields:

```
_peerLogger IN ["peer1", "peer2", ...] | sort deviceEventCategory eventId  
deviceCustomNumber1 deviceCustomNumber2 deviceCustomNumber3
```

Search with field extraction:

```
_peerLogger IN ["peer1", "peer2", ...] | rex "(?<src_ip>\d{1,3}\.\d{1,3}\.\d{1,3}\.\d{1,3})"
```

Search evaluating a variable:

```
_peerLogger IN ["peer1", "peer2", ...] | eval (int)urllength=len(requestUrl)  
| sort urllength
```

Search with results grouped and counted as a top 50 list:

```
_peerLogger IN ["peer1", "peer2", ...] | and priority > 0 | top 50 name
```

Search for events with a long URL:

```
_peerLogger IN ["peer1", "peer2", ...] | eval n=len(requestUrl) | where n =  
"1023"
```


Tuning Search Performance

Search performance depends on many factors and will vary from query to query. Some of factors that can affect search performance are listed below. To optimize search performance, ensure that you follow these recommendations:

- When searching for uncommon field values, use superindexing to narrow the range of data that needs to be searched, as described in ["Searching for Rare Field Values" below](#).
- Enable field-based indexing for all fields that occur in your events. When events are indexed, Logger can quickly and efficiently search for relevant data. By default, a recommended set of fields are indexed on your Logger; you might need to add additional fields, as described in ["To add fields to the field-based index:" on page 326](#).
- Avoid specifying a time range that results in a query that needs to scan multi-millions of events.
- Limit the search to specific storage groups and peers.
- Reduce other load on the system when your query needs to run, such as scheduled jobs, large number of incoming events, and multiple reports being run.
- Before running a query, make sure all Loggers on which it will run support the query features.

For more information on improving search performance, refer to the Logger Best Practices guide.

Searching for Rare Field Values

To enable you to quickly search common IP address, host name, and user name fields for rare field values; Logger creates superindexes on new data as it comes in. Searches written to take advantage of super-indexed fields will tell you very quickly if there are no hits and will return results more quickly than regular searches when there are very few hits. Therefore, they are excellent for fast needle-in-a-haystack searches. For more information, see ["Superindexing" on page 149](#).

Note: Since superindexes are built on new data as it comes in, they only apply to data collected by Logger 5.5 or later. Any data brought forward from an upgrade from an earlier version of Logger will not be superindexed and will not exhibit this search speed improvement.

Using Super-Indexed Fields to Increase Search Speed

To take advantage of superindexing and get the fastest search results, run an equal to (=) search, such as **sourceAddress=192.0.2.0**, and write the indexed search portion of your query to find uncommon values in the super-indexed fields listed in the table below.

Super-indexed Fields

| | | | |
|--------------------|--------------------|-------------------|---------------------|
| deviceEventClassId | deviceProduct | deviceVendor | destinationHostName |
| destinationPort | destinationAddress | destinationUserId | destinationUserName |
| deviceAddress | deviceHostName | sourceHostName | sourcePort |
| sourceAddress | sourceUserId | sourceUserName | |

Note: Unlike the indexed fields discussed in ["Field-Based Indexing" on page 147](#), you cannot add to the list of super-indexed fields.

Search on super-indexed fields only using the = operator, and only **AND** with non-super-indexed fields for fastest search performance. Superindexes speed up searches that use the equal to (=) operator in the indexed search portion of the query expression. They have no performance impact on searches that use greater than (>), less than (<), not equal to (!=), or other operators in the indexed search portion of the query. While Logger supports full-text search, search on fields that are not super-indexed, and searches that use operators such as >, less than <, !=, and so on; such searches may not provide the greatest search speed.

Using AND and OR with the = operator can be very powerful when searching super-indexed fields. However, to obtain the greatest search speed improvement, you must use them carefully. The table below provides examples to help you understand how to write queries that take advantage of the power of superindexing.

Note: To see the faster search results, all fields you use in your query must be indexed.

Query Examples for Superindexing in Needle-in-a-Haystack Searches

| Query | Does It Improve Search Speed? |
|--|--|
| arcsight (full text) | No difference. This is a full text query, and so does not take advantage of super-indexed field-search speed improvements. |
| 192.0.2.0 (full text that looks like a super-indexed field) | No difference. While this could be an IP address, it is a full text search, not an = search against one of the super-indexed fields, and so does not take advantage of super-indexed field-search speed improvements. |
| sourceAddress = 192.0.2.0 (= on a super-indexed field) | The search speed is improved and the results return very quickly when there are no hits. If Logger has not encountered 192.0.2.0 as a sourceAddress, it quickly returns the message "No results were found". If it has encountered that sourceAddress, the range of events to be searched is narrowed down. |
| sourceAddress = 192.0.2.0 OR sourceAddress = 192.0.2.2 | The search speed is improved and the results return very quickly when there are no hits. |

Query Examples for Superindexing in Needle-in-a-Haystack Searches, continued

| Query | Does It Improve Search Speed? |
|--|--|
| (= using OR on super-indexed fields) | If Logger has not encountered 192.0.2.0 or 192.0.2.2 as a sourceAddress, it quickly returns the message "No results were found". If it has encountered one or the other, the range of events to be searched is narrowed down. |
| sourceAddress = 192.0.2.0 AND destinationAddress = 192.0.2.2 (= using AND on super-indexed fields) | <p>The search speed is improved and the results return very quickly when there are no hits.</p> <p>If Logger has not encountered 192.0.2.0 as a sourceAddress, it quickly returns the message "No results were found".</p> <p>Similarly, if Logger has not encountered 192.0.2.2 as a destinationAddress, it quickly returns the message "No results were found", even if it has encountered 192.0.2.0 as a sourceAddress.</p> <p>If Logger has encountered both, the range of events to be searched is narrowed down.</p> |
| sourceAddress != 192.0.2.0 (!= on a super-indexed field) | <p>No difference.</p> <p>Superindexing does not help with negations, so this query does not take advantage of super-indexed field-search speed improvements.</p> |
| sourceAddress != 192.0.2.0 OR destinationAddress = 192.0.2.2 (!= using OR on Super-indexed fields) | <p>No difference.</p> <p>Since there is a negation on the sourceAddress and this is an OR condition, this query does not take advantage of super-indexed field-search speed improvements.</p> |
| sourceAddress != 192.0.2.0 AND destinationAddress = 192.0.2.2 (!= using AND on Super-indexed fields) | <p>The search speed is improved and the results return very quickly when there are no hits.</p> <p>Since this is an AND condition, both conditions need to be true.</p> <p>Even though there is a negation on the sourceAddress, if Logger has not encountered a destinationAddress address of 192.0.2.2, this AND condition will never be satisfied. In that case, it quickly returns the message "No results were found".</p> <p>If Logger has encountered that destinationAddress, the range of events to be searched is narrowed down.</p> |
| sourceAddress = 192.0.2.0 AND arcsight (= on super-indexed field AND full text) | <p>The search speed is improved and the results return very quickly when there are no hits.</p> <p>If Logger has not encountered a sourceAddress of 192.0.2.0, this AND condition will never be satisfied. In that case, it quickly returns the message "No results were found", even though there is a full text search.</p> <p>If Logger has encountered that sourceAddress, the range of events to be searched is narrowed down.</p> |
| sourceAddress = 192.0.2.0 OR arcsight (= on super-indexed field OR full text) | <p>No difference.</p> <p>Regardless of whether Logger has encountered a sourceAddress of 192.0.2.0, the OR condition requires a full text search for "arcsight", so this query does not take advantage of super-indexed field-search speed improvements.</p> |

Query Examples for Superindexing in Needle-in-a-Haystack Searches, continued

| Query | Does It Improve Search Speed? |
|---|--|
| <code>name = "CPU Usage" AND sourceAddress = 192.0.2.0</code> (indexed field AND super-indexed field) | <p>The search speed is improved and the results return very quickly when there are no hits.</p> <p>Even though name is not one of the super-indexed fields, because the query uses an AND condition, Logger quickly returns the message "No results were found" if it has not encountered a sourceAddress of 192.0.2.0.</p> <p>If Logger has encountered that sourceAddress, the range of events to be searched is narrowed down.</p> |
| <code>name = "CPU Usage" OR sourceAddress = 192.0.2.0</code> (indexed field OR super-indexed field) | <p>No difference.</p> <p>Even though sourceAddress is one of the super-indexed fields, because it is in an OR condition with name, which is not super-indexed, this query does not take advantage of super-indexed field-search speed improvements.</p> |
| <code>sourceAddress = 192.0.2.0 AND (sourceHostName = myhost.com OR sourcePort = 80) AND (destinationAddress = 192.0.2.2 OR arcsight)</code> (super-indexed field AND (nested OR condition) AND (nested OR condition)) | <p>Results return very quickly when there are no hits.</p> <p>If Logger has not encountered a sourceAddress of 192.0.2.0, the top level AND will never be true. It quickly returns the message "No results were found" in that case.</p> <p>If Logger has not encountered a sourceHostName of myhost.com AND it has not encountered a sourcePort of 80, then the OR condition will never be true. Thus the top level AND condition will never be true. It quickly returns the message "No results were found" in that case.</p> <p>If Logger cannot show that the above conditions are false, then there will be no difference in search speed.</p> <p>Even though destinationAddress is one of the super-indexed fields, because it is in an OR condition with a full-text search for "arcsight", the range of events to be searched cannot be narrowed down.</p> |

Searching for IPv6 Addresses

If you have IPv6 address fields configured in your Logger, you can filter on IPv6 addresses in Logger address fields as you would for IPv4 addresses.

Canonical Format for IPv6 addresses

When using a query search operator to search for full or partial IPv6 addresses, the address must be in canonical (normalized) format. Do not use IPv4-mapped IPv6 addresses. See "[Limitations on Field-Based Search Operators](#)" on page 85. For complete information about canonical format, refer to <https://tools.ietf.org/html/rfc5952>, section 4: A Recommendation for IPv6 Text Representation.

- Address fields that are indexed by default require canonical format for IPv6 addresses. They include:
 - **destinationAddress**
 - **deviceAddress**
 - **sourceAddress**
- Address fields that are not indexed are not limited to canonical IPv6 addresses. They include:
 - **agentAddress**

However, queries on the **agentAddress** field will be slower, due to on-the-fly, just-in-time indexing of that field. If you issue many queries on the **agentAddress** field, consider indexing that field on Logger. If you need additional fields normalized, contact [customer support](#). If you need to index additional fields, see ["Search Indexes" on page 326](#).

Tip: In searches containing a search operator, IPv6 addresses in the results are displayed in canonical format. To view the original IPv6 address, expand the 'raw message' tab in the search results. See ["Search Operators" on page 524](#) and ["Viewing Raw Events" on page 128](#).

Searching for Partial IPv6 Addresses

You can search for a partial IP address if the partial address you enter is already in the canonical format. All IPv6 address you enter in queries are converted to the canonical format, so that they will match the IPv6 address as stored in the database. If your query includes a partial address that is not in the correct format, it will not match the IPv6 address as stored in the database, and so will not return any results.

Field-based and Keyword Searches

If you run a keyword or field-based search for one of these address fields, it will find ALL matching events for equivalent IPv6 values, regardless of the format of the original IPv6 addresses.

IPv4-mapped IPv6 addresses are matched with IPv4 addresses, and vice-versa. For example, **src=: :ffff:10.10.11.12** will match events in which **src=10.10.11.12**.

Note: This functionality is not available for the **INSUBNET** operator or for the lookup function. See ["Using the INSUBNET Operator to Search for IPv6 Addresses" on the next page](#).

Aggregation Operators with IPv6

Aggregation operators behave the same for both field-based or keyword searches. The results will be combined for equivalent IPv6 addresses into one line displaying the IPv6 address in canonical format. You can search for IPv6 addresses by entering them in any valid format. Note that this pertains only to the results display. Logger does not change any of the actual events and values.

Example: IPv6 address searches

- `sourceAddress IS NULL`
- `destinationAddress = 2001:db8:85a3:0042:1000:8a2e:0370:7334`
- `deviceAddress IS NOT NULL`

Using the INSUBNET Operator to Search for IPv6 Addresses

You can use the INSUBNET operator to filter IPv4 and IPv6 addresses in the regular Logger address fields and any custom fields added to the Logger schema. Examples of filtering for IPv4 addresses are given in ["Field-Based Search" on page 80](#). For limitations on this operator, see ["Limitations on Field-Based Search Operators" on page 85](#).

Example: Use INSUBNET to filter IPv6 addresses:

- `sourceAddress insubnet "2001:db8::/32"`
- `agentAddress insubnet "2001:db8::-2001:db8::ffff:ffff:ffff"`
- `destinationAddress insubnet "2001:db8::*:*:*:"`

Example: Use INSUBNET to filter a combination of IPv4 and IPv6 addresses:

- `deviceAddress INSUBNET "192.0.2.0/24" OR destinationAddress INSUBNET "2001:db8::/32"`
- `agentAddress INSUBNET "2001:db8::/32" OR sourceAddress INSUBNET "192.0.2.0/16"`

The Search Results Display

This topic applies to both Classic Search and Search pages

After you have initiated a search, the search results are displayed in the bottom section of the same screen in which you ran the search. A search operation can take time when millions of events need to be searched. When the first screen of events that match the specified conditions is available, Logger automatically pauses the search and displays the matched events.

Event data is categorized by field name and each field is displayed as a separate color-coded column. For example, the time when an event was received on the Logger (Logger Receipt Time) is displayed in a gray-shaded column indicating metadata and labeled **Time**.


- [Adjusting the Displayed Search Results](#)123
- [Canceling a Search in Progress](#)124
- [The Histogram](#) 124

- The Search Results Table126
- Additional Fields in the Search Results126
- Refining a Search from the Search Results Table127
- Changing the Displayed Search Results Using Field Sets128
- Multi-line Data Display 129
- Auto Refresh Search Results129
- Chart Drill Down129
- The Field Summary Panel130


Adjusting the Displayed Search Results

This topic applies to both Classic Search and Search pages

Search results are sorted by the Logger receipt time. The events are displayed either oldest first or newest first, depending on what you selected when you ran the search. If you want to change the sort order, you will need to rerun the search. To change the sort order, open the search options drop-down and in the Sort field select Oldest event first or Newest event first.



By default, 25 events are displayed on one screen. To change the number of events displayed per screen, open the Events per Page pop-up menu, located at the bottom of the search results, and select the number of events to display.



Some searches may return many pages of results. To move from page to page in the search results, click the appropriate arrow or type number of the page that you want to move to and then press Enter.

Each event is available in its raw form or parsed data. You can show or hide the raw event data from this page. See ["Viewing Raw Events" on page 128](#) for details. In addition to changing how the data is displayed, you can refine your search from the search results display. See ["Refining a Search from the Search Results Table" on page 127](#) for details.

Canceling a Search in Progress

This topic applies to both Classic Search and Search pages

When a query is running, search results are displayed as matching events are found. Therefore, when you click **Cancel**, any matching events found so far are displayed as the search results. This might be helpful in cases when the query needs to scan a large data set, but the search results displayed so far display the events you were looking for. You can further process the displayed (partial) results; for example, export the results, use the histogram to drill down in the results, or click on any text in the Search Results to add it to the query for further drill-down in the search results.

Note: Partial results do not display if a query includes the operators **HEAD**, **TAIL**, or **SORT**. Additionally, if a query includes chart operators such as **CHART**, **RARE**, or **TOP**, and the query is terminated early, Logger does not display a chart of the partial results.

To cancel a search that is running in the search window:

1. While the search is in progress, the **Go!** button changes to **Cancel**—click **Cancel** to stop the search.

Note: Cancel does not delete the search.

The Histogram


This topic applies both to Classic Search and Search page

The Search Results page displays a histogram that provides a graphical representation of the events that match a search query. Depending on the type of search executed, the histogram is based on Logger receipt time or event time.

The X-axis represents event time and Y-axis represents the number of matching events, as shown in the following figure. The time distribution on the X-axis is determined automatically, based on the time range specified in the query.

Note: The time range on the X-axis might not match the time range specified in the search query because the start and end times on the X-axis are determined by the event times of the first and last matching events of the search query.

Histogram showing mouseover details



A histogram is progressively built and displayed as events match a search query. If the search query needs to scan a large amount of data or a large time period, the histogram displayed initially might refresh multiple times while the query is running. To view the complete (and final) histogram of a search query, wait until the query has finished running (that is, the screen does not display the circular “waiting” icon anymore).

The first one million matching events are plotted on the histogram. If a search query matches more than one million events, an informational message is displayed on the screen. If you need to use the histogram view for event analysis for a search query that matches more than one million events, ArcSight suggests that you adjust the time range specified in your search query so that than less than one million are matched. This will allow you to obtain a complete and meaningful histogram. You can also use a pipeline operator such as top, head, or chart to further refine search results so that the total number of hits is under one million events.

Displaying the Histogram

You cannot disable the histogram; however, you can click the Histogram icon above the upper-right corner of the histogram to hide it. To display a hidden histogram, click the icon again.

Mouse-Over

You can mouse-over any histogram bar to highlight it and view the number of matching events and the date and time period that the bar represents. For example, in the last figure, the highlighted bar represents 1,676 events from 5–6 p.m. on July 18th. The matching events listed below the histogram do not change, and the histogram continues to display all matching events.

Histogram Drill Down

You can drill down to events in a specific time period by clicking the bar on the histogram that represents that time period. The bar you drilled down to is highlighted and the events matching that time period are listed below the histogram. The histogram continues to display all of matching events, as shown in the following figure. To deselect the time period, click the bar again. You can also select multiple consecutive bars on the histogram to view matching events in all of the selected time units.

The Search Results Table

This topic applies to both Classic Search and Search page

The search results table displays the number of events scanned, the number of events found, the index status of each event type, and how long the search took.

Below the histogram, events are shown in table form, one row per event. Terms that match your query are highlighted to make it easy to see why an event matched the query. As you roll the mouse over other terms in the events table, they highlight in green.

You can drill down into the displayed search results by clicking a green-highlighted term to add it to the current query. For example, if you search for “login” and roll over the word “fail” in the search results, “fail” will highlight in green. Click the word “fail” to change the query to “login AND fail.”

Tip: You can also highlight and copy text from any displayed column. This feature is handy when you need to copy an IP address or a URL. (Click and drag your cursor over it to select the text. Then, right-click to display the **Copy** option.)

By default, a Field Summary panel is displayed on the left side of the matched events. This section lists the fields that occur in matching events and the number of unique values for each in those events. For more information about Field Summary, see ["The Field Summary Panel" on page 130](#).

Additional Fields in the Search Results

This topic applies only to Classic Search page

In addition to Logger's schema fields, you may see other types of fields in the Search results.

User-Defined Fields

User-defined fields are created when a search query includes operators such as **rex**, **extract**, and **rename**. See ["Search Operators" on page 524](#) for information on these operators. These fields are displayed as additional columns in the All Fields view (of the System Fieldsets). To view only these columns, select **User Defined Fieldsets** from the System Fieldsets list.

System-Defined Fields

When a search query matches events that were received from a defined source type and were parsed using a pre-defined or user-defined parser, the search results include a parser field, and may include fields for the source type, and source, depending on the setting in the Search Options page. For more information, see ["Global Search Options" on page 328](#).

System-defined fields contain no event data and are not searchable. See ["About Building Search Queries" on page 111](#) for more information.

| Field | Description |
|-------------|---|
| parser | <p>Indicates whether or not an event was parsed, and if so, which parser was used.</p> <div>Note: While the parser field itself is not searchable, the parser defines searchable fields based on its associated source type. These fields vary based on the source type. For more information, see "Parsers" on page 371.</div> <p>If the event was parsed, this field contains the name of the parser. If the event was not parsed successfully, this field contains "Not parsed". If no parser is defined for the source type or if there is no source type, the field is blank.</p> |
| source type | <p>The type of file from which the event was received, as defined on the Source Type page (Configuration Data > Source Types). For more information, see "Source Types" on page 367.</p> <p>If no source type was applied when the event was received, this field is blank. You can control whether this field is displayed from the Search Options page.</p> |
| source | <p>The name of the log file from which the event was received. For example, /opt/mnt/testsoft/web_server.out.log</p> <p>If no source was applied when the event was received, this field is blank. You can control whether this field is displayed from the Search Options page.</p> |

Refining a Search from the Search Results Table

This topic applies only to Classic Search page

Use these shortcuts to select terms from the displayed search result columns or the raw events to refine your search query:

- Click a term in search results to add it to the search query, and rerun the search immediately.
- Flag the **Enable Multi-select of field values** checkbox (☐ **Enable Multi-select of field values**.) and then click multiple terms to add to the search query. When multiple terms are added, they are joined by AND operators. Click **Go!** to run the search.
- Ctrl+click to replace the entire search query with <field name> + "CONTAINS" + <selected term>, and rerun the search immediately.

- Alt or Shift + click the term in search results to add NOT to the term, and rerun the query, thus eliminating the events that match the term you selected.
- Add multiple NOT conditions by holding the Alt key and selecting terms in search results. When multiple conditions are added, they are joined by AND operators. If **Enable Multi-select of field values** is checked, click **Go!** to run the search. If it is not checked, the search runs when you click the term.
- Combine **Ctrl+Alt**, (or **Ctrl+Shift**) to replace the search query with **NOT + <field name> + "CONTAINS" + <selected term>**.

Note: Fields that are not searchable are not highlighted by mousing over them in the search results and cannot be clicked on to add to the search. For more information about what is searchable, see ["About Building Search Queries" on page 111](#), and ["Additional Fields in the Search Results" on page 126](#).

Changing the Displayed Search Results Using Field Sets

This topic applies only to Classic Search page



By default, the Search Results are displayed using the All Fields field set, which displays all fields contained in an event. Once you select another field set, it becomes your default view until you change it the next time. For a detailed discussion about field sets, see ["Fieldsets" on page 89](#).

If you view the Search Results using the Raw Event field set, remember these guidelines:

- Even though the rawEvent column displays the raw event, this column is not added to the Logger database and is not indexed. Therefore, you can only run a keyword (full-text) or regular expression to search on the event.
- You can use the Regex Helper tool to identify strings from the raw syslog events in the rawEvent column that you want to add to a query. (You cannot use the Regex Helper for CEF events displayed in the rawEvent column.) See ["Regex Helper Tool" on page 103](#) for details about the Regex Helper tool.

Viewing Raw Events

Each event is available in its raw form or parsed data. By default, the parsed data is displayed.

To view the raw data of an event, click the  icon to the left of the event. Otherwise, click  to observe raw data for all displayed events.

Note: You can also view the Syslog raw events in a formatted column called **rawEvent** if you have enabled the "Populate rawEvent field for syslog events" option on the Search Options page. See ["Global Search Options" on page 328](#). See ["Predefined Fieldsets" on page 89](#) to learn more about displaying raw events.

Multi-line Data Display

This topic applies only to Classic Search page

An event field might span multiple lines separated by characters such as newline (\n) or carriage return (\r). For example,

```
0x0000: 0000 0100 0000 0000 0000 0000 0000 0000 .....  
0x0010: 0000 0000 0000 0000 0000 0000 0000 0000 .....  
0x0020: 0000 0000 0000 0000 0000 0000 0000 .....
```

The Logger user interface displays these in multi-line format and does not remove the line separators and collapse the message into one line.

Auto Refresh Search Results

This topic applies both to Classic Search and Search page

The Auto refresh feature executes a search over specified intervals, updating the search results if new events match the query. Set this option from the Search Options menu.

Depending on your needs, you can auto update the search results every:

- 30 seconds
- 60 seconds
- 2 minutes
- 5 minutes (default)
- 15 minutes

You can enable this option for a search operation before or after running it. Once you enable this option for a search, the setting persists for all search operations on that tab until you explicitly disable it. Concurrent searches on other tabs are not affected and must be configured separately.

To auto update search results:

1. Select **Analyze > Classic Search** from the Navigation bar.
2. From the Search Options menu, check the **Auto refresh** box and select the refresh interval you want.

Chart Drill Down

This topic applies to both Classic Search and Search page

Aggregated search operators such as **CHART**, **TOP**, and **RARE** generate charts of search results. The chart drill down feature enables you to quickly filter down to events with specific field values.

You identify the value on a search results chart and click it to drill down to events that match the value. For example, in the following chart, if you want to see events in which the device event class ID is **eps 102**, click the column labeled **eps:102** to display events shown in the second figure.

When you click on a chart value (a column, bar, or donut section), the existing search query is modified to include the **WHERE** operator with the field name and value, and automatically rerun.

To return to the original query from the drill-down screen:


1. Use the Back function of your browser.

The Field Summary Panel

This topic applies only to Classic Search page

When a query is run, the Field Summary panel lists the CEF and non-CEF fields that occur in matching events and the number of unique values for each in those events. This panel is only displayed for queries that do not generate charts. If a peer search is performed, the summarized field values include counts from peer Loggers.

The Field Summary panel contains two sections: **Selected Fields** and **Discovered Fields**. The Selected Fields section lists the CEF fields, while the Discovered Fields section lists the non-CEF fields discovered in raw events.




- [Displaying the Field Summary Panel](#)131
- [Selected Fields List](#)131
- [Field Summary Drill Down](#)132
- [Discovering Fields in Raw Event Data](#)132
- [Refining and Charting a Search from Field Summary](#) 133

Displaying the Field Summary Panel

This topic applies only to Classic Search page

By default, the Field Summary feature is enabled and the Discover Fields option is disabled. These options are controlled globally in the ["Global Search Options" on page 328](#), and locally with checkboxes in the search results display options. Selecting these options on the **Analyze > Classic Search** page overrides the setting for these options on the Search Options page. For more information on the Discover Fields option, see ["Discovering Fields in Raw Event Data" on the next page](#).

You can display or hide the Field Summary panel by using the Fields Summary checkbox in the search results display options.



Selected Fields List

By default, the Selected Fields list contains these fields:

- `deviceEventClassId`
- `deviceProduct`
- `deviceVendor`
- `deviceVersion`
- `globalEventId`
- `name`

You can edit this list to suit your needs. By default, this list displays the top 10 values for each field.

You can change the fields displayed in the Field Summary panel's Selected Fields list by changing the fieldset. You can use one of the predefined fieldsets or create your own to include only the fields you need.

To change the Selected Fields list:

1. Define or update an existing custom field set to include fields you want the Selected Fields list to contain. See ["Fieldsets" on page 89](#) for information on creating custom field sets.
2. Select the custom field set you defined to view search results.
3. After running a search query, if you select a different field set, the Field Summary panel displays the

following message: "The Field Summary is out of sync with the events table".

This message indicates that the fields listed in the Field Summary panel do not match the ones specified in the newly selected field set. To display the fields specified in the new field set, click **Update now**.

Field Summary Drill Down

You can drill down on any of the listed fields or a specific value of the listed fields in the Fields Summary panel.

For example, you might want to view all events containing **deviceEventClassId** (specific field) or you might want to view events of **deviceEventClassId "storagegroup:100"** (specific value of a field).

For fields whose values are of type **STRING**, you can view all events, view the top ten, or create charts of the matching events. For fields whose values are of type **NUMERIC**, you can perform mathematical operations such as **average**, **min**, and **max**.

Every time you run a query or drill down on a specific field or value, a new query using the newly selected criteria is run and the Field Summary list is updated.

To view drill down in the field summary:

1. Click Analyze | Search to open the search page.
2. Click the search options down arrow (▼) to configure the search display options and check **Field Summary**.
3. Run a search.
4. In the Field Summary list, click the field name you want more detail on.
5. The **<fieldname><number of values>** dialog box displays the top ten field values.
6. Optionally, click **Display events containing <fieldname>** to run a search that displays only those events.
7. Optionally, click a field value to run a search that displays only those events.
8. Optionally, create a chart of the results as discussed in ["Refining and Charting a Search from Field Summary" on the next page](#).

Discovering Fields in Raw Event Data

This topic applies only to Classic Search page

The Field Summary feature can automatically discover non-CEF fields from a raw event if the Discover Fields is enabled. By default, the Discover Fields option is disabled.

If you need to enable the Discover Fields option for all searches on your Logger, change the default values (“No”) on the Search Options page (Configuration | Search > Search Options) to “Yes” for these options, as shown in the following figure.



The screenshot shows a section titled "Field Summary Options". It contains two dropdown menus. The first is labeled "Use Field Summary" and is set to "Yes". The second is labeled "Discover fields" and is set to "No".

However, if you need to use the Discover Fields option occasionally—not for all searches—you can enable this option for one-time use on the user interface page from where you run the search query (**Analyze > Classic Search**). To do so, click the **Discover Fields** checkbox in the search display options before running the query.

Note: Selecting these options on the Search page overrides the setting for these options on the Classic Search Options page.

Tip: To auto discover fields, the raw event must contain data in the “key=value” format, and none of these characters can be the first character of the “value”: comma, space, tab, and semicolon.

For each “key=value” pair found in a raw event, a new field of the name “key” is created. The Field Summary includes a summary of the values for all the new fields under the Discovered Fields section. The discovered fields are assigned the type “String” by default. The auto-discovery capability works only if at least 2,500 of the first 10,000 matching events contain “key=value” pairs. If this threshold is not met, auto discovery is automatically turned off. However, this threshold does not apply if there are less than 10,000 matching events; in that case, fields are discovered regardless.


Refining and Charting a Search from Field Summary

When you click a field in the Field Summary, a dialog box labeled *<fieldname><number of values>* displays information about the field. From here, you can drill down to see more details and create a chart of the search results.


To view field details from field summary:

1. Run a search and drill down to the data you are interested in, as described in ["Field Summary Drill Down" on the previous page](#).
2. To create a chart of the search results, click one of the Chart on values, such as **Values by time** or **Top values**.
3. The results display in a Result Chart and a Result Table.
4. In the Result Chart, click **Chart Settings** to adjust the chart.
5. Enter a useful **Chart Title**.

- Select the **Chart Type** best suited to your data.
- Set the **Display Limit**. The highest valid value is 100.



6. In the Result Table, you can use navigation buttons to move forward and backward through list of results, and refresh the search.

To create a PDF or CSV file containing the search results, click **Export Results** . For more information, see ["Exporting Search Results" on the next page](#).

Saving the Search Results

This topic applies only to Classic Search page


You can save the results of any search by exporting them in PDF or CSV format:

- **PDF**: Useful in generating a quick report of the search results. The report includes a table of search results and any charts generated for the results. Both raw (unstructured data) and CEF (structured data) events, can be included in the exported report.
- Comma-separated values (**CSV**) file: Useful for further analysis with other software applications. The report includes a table of search results. Charts cannot be included in this format.

Data for the following time fields is exported in human-readable format: **deviceReceiptTime**, **startTime**, **endTime**, **agentReceiptTime**. For example, **2015/03/21 20:22:09 PDT**.


Example of a Quick Report in PDF Format (Search Results Export)

The following is an example of a quick report generated in PDF format. The chart is displayed first, followed by a table of matched events (not shown in this example). All generated charts (including stacked charts) can be exported.



Exporting Search Results

To export the results of your search:

1. Run a search query from the **Analyze > Classic Search** page or the **Analyze > Alerts** page.
2. Click the Export Results arrow  above the histogram.

Export Options? Help

☐ Save to local disk
 ☒ Save to Logger

File format CSV

Export file name

☐ Overwrite?

Fields ☒ All fields

Include Event Total ☐

Include only CEF events ☐

Rerun query ☐

Export

Cancel

- Select from the available options and then click **Export**. The displayed options change based on your selections.

| Option | Description |
|---------------------------|---|
| Save to local disk | Select to save the file to a local system from which you are accessing Logger or is it sent to the browser for viewing or saving. |
| Export to remote location | <p>Select to export the file</p> <p>On a Logger Appliance, the file is written to an NFS mount, a CIFS mount, or a SAN system.</p> <p>On Software Logger, data is always stored in the <code><install_dir>/data/logger</code> directory. This directory can reside locally on the system running the Logger software, or on a remote storage system such as NFS or CIFS.</p> <p>Note: The Logger Appliance supports mounting through the user interface. Software Logger uses its filesystem, which can contain remote folders mounted through the operating system.</p> |
| Save to Logger | Select to write the file to Logger's local system. |
| File Format | <p>Select CSV to produce a comma-separated values file.</p> <p>Select PDF to produce a report-style PDF that contains the search results in tables and charts. Charts are only included if the search query contains an operator that creates charts, such as chart, top, and so on.</p> |
| Export file name | <p>(Available only when the "Export to remote location" option is selected)</p> <p>Specify the name of the file to which events will be exported.</p> <p>If a file of the specified name does not exist, it is created. If a file of the specified name exists and the Overwrite box is not checked, an error is generated. If the Overwrite box is checked, the existing file is overwritten.</p> |

| Option | Description |
|---|---|
| Title | (Optional, available only when the File Format is "PDF") Enter a meaningful name that appears on top of the PDF file. If no title is specified, "Untitled" is included. |
| Fields | Displays the list of event fields to be included in the exported file. By default, all fields are included. Enter fields or edit the displayed fields by deselecting All Fields. To export fields created as a result of rex , extract , rename , or eval operators, or field created when a parser is applied to an event, ensure that *user is selected in the Fields list. Note: Export meta data fields along with other fields. Exporting only the meta data fields (Event Time, device and Logger) is not supported by Logger. |
| Chart Type (for PDF only) | (Available only when a chart is available in search results) Select the type of chart to include in the PDF file. You can select from: Column, Bar, Donut, Area, Line, Stacked Column, Stacked Bar. Note: If the Chart Type is different from the chart displayed on the Search Results screen, the value selected for this option overrides the one shown in the screen. Therefore, the exported PDF contains the chart you specify for this option and not the one shown on the screen. |
| Chart Result Limit (for PDF only) | (Available only when a chart is available in search results) Specify the number of unique values to plot. Default: 10 If the configured Chart Result Limit is less than the number of unique values for a query, the top values equal to the Chart Result Limit are plotted. That is, if the Chart Result Limit is 5 and 7 unique values are found, the top 5 values will be plotted. |
| Include Event Total | Select to include the total number of events in the exported search results. |
| Include Only CEF Events | Select to include CEF events in the exported search results. |
| Include Base Events (Available for Alerts only) | Select to include base events in the exported search results. Tip: The base events option is available ONLY when you Export the search results from the Analyze > Alerts page. |
| Rerun query | Select to rerun the query before exporting the search results. |

Scheduling an Export Operation

The time it takes to export search results is proportional to the number of events being exported. Therefore, for a large number of events, Micro Focus recommends that you schedule the export operation to be performed at a later time by saving the query and time parameters as a Saved Search, and then

scheduling a Saved Search Job. For more information about Saved Search jobs, including how to create a scheduled search, see ["Scheduled Searches/Alerts" on page 317](#).


Saving Queries, Creating Saved Searches and Saved Filters.


This topic applies only to Classic Search page

If you need to run the same search query regularly, you can save it in as a filter or as a saved search.

- Saving it as a filter saves the query expression, but does not save the time range or the field set information.
- Saving it as a saved search saves the query expression and the time range that you specified.

To save a query:

1. Define a query as described in ["Searching for Events" on page 108](#) or ["Using the Advanced Search Builder" on page 98](#).
2. Click the Save icon () and enter a name for the query in the Name field, as shown in the following figure.



The image shows a 'Save Query' dialog box. At the top, there is a title bar with 'Save Query' on the left and a help icon with the text '? Help' on the right. Below the title bar, there is a 'Name' label followed by a text input field. Underneath the 'Name' field, there is a 'Save as' label followed by two radio buttons: 'Filter' (which is selected) and 'Saved Search'. Below this, there is a 'Create Report' label followed by an unchecked checkbox. Further down, there is a 'Schedule it' label followed by an unchecked checkbox and the text '(You can change the schedule settings later)'. At the bottom, there is a 'Type' label followed by two radio buttons: 'Scheduled Search' (which is selected) and 'Scheduled Alert'. At the very bottom of the dialog, there are two buttons: a blue 'Save' button and a white 'Cancel' button with a black border.

3. In the Save as field, select whether you want to save this query as a Filter, as a Saved Search, or as a Dashboard panel.

If you select to save as a Saved Search, you can either keep the saved query as Saved Search or change it to a Scheduled Search or Schedule Alert by clicking the **Schedule it** Check box. (Queries with aggregation operators cannot be used in Saved Search Alerts.) For further information about Saved Search Alerts, see ["Saved Search Alerts" on page 323](#).

If the search query includes an aggregation operator such as chart or top, an option to save the query for a Dashboard panel is also displayed.

If you select the Dashboard panel option, dashboard options are displayed.

Enter the following parameters:

| Parameter | Description |
|--------------|---|
| Title | Enter a meaningful name for the panel that will be added to the Dashboard. |
| Saved search | Select an existing saved search from the drop-down box that will be overwritten with this query. OR Select "New saved search" to create a new saved search query. Enter the new name in the text box. |
| Dashboard | Select an existing Dashboard from the drop-down box to which the Search Results panel will be added. OR Select "New dashboard" to add the Search Results panel to a new Dashboard. Enter the name of the new Dashboard in the "Dashboard Name" field. |
| Panel type | Select the type of panel: <ul style="list-style-type: none">• Chart: Displays search results in a chart form• Table: Displays search results in a table form• Chart and Table: Adds two panels, one for displaying search results in the chart form and the other for displaying search results in the table form |
| Chart type | Select the type of chart to display matching events. You can select from: Column, Bar, Donut, Area, Line, Stacked Column, Stacked Bar. Default: Column |
| Chart limit | Only applicable to Search Result Chart panels. Specify the number of unique values to plot. Default: 10 |
| Search type | Specify whether the search will be based on occurred or received time. |

4. Click **Save**.
5. If you selected Schedule it, you are asked if you'd like to edit the schedule setting now. Click **OK**. If you click **Cancel**, the Saved Search or Alert is not created.
6. Set the schedule options as appropriate. For details about these options, see ["Scheduling Date and Time Options" on page 145](#).
7. For Scheduled Saved Searches, select the desired options. For details about the parameters, see ["Search Job Options" on page 321](#).
8. For Scheduled Alerts, select the desired options. For details about the parameters, see ["Alert Job Options" on page 322](#).
9. Click **Save**.

To save a query as a report:

- a. From **Analyze > Classic Search**, insert query.
Specific events will be displayed.
- b. Select if you want to save a Filter or a Saved Search and click **Create Report**

Note: The report will be saved with the name of your preference. Saving the same query as a report on a different date will automatically save it in a sequential order.

Tip: Users may change the fields of query objects based on Logger filters or saved searches. The report layouts of report objects cannot be changed but users can customize the report and select the new fields. When updating a query that includes a chart, a new report must be created.

System Filters/Predefined Filters

Your Logger ships with a number of predefined filters, also known as system filters. These filters define queries for commonly searched events. For example, unsuccessful login attempts or the number of events by source. Filter queries are available as Unified queries and as Regular Expression queries. Unified queries can be used for searching and reporting while Regular Expression queries are for defining alerts and forwarders.

Note: To effectively use the Firewall or UNIX Server use case filters (listed in the following table), define device groups that include the firewall devices or UNIX servers that you are interested in and then constrain your search to those device groups. If you do not create device groups specific to device types, the search results would match all Deny, Drop, or Permit events from all devices instead of only the firewall devices. Similarly, the "Unix-IO Errors and Warnings" filter would include IO errors and warnings from all devices and not only the UNIX servers.

The following is a list of all the system filters. For a description of each filter, see ["System Filters" on page 652](#).

To use a predefined system filter, follow instructions in ["Searching with Saved Queries" on page 144](#).

Note: Even though the filters in the System Alert category (listed in the last section of the following table) are displayed on the user interface of Software Logger, these filters do not apply to it.

System Filters

| Category | Unified Query Filters | Regular Expression Query Filters |
|---|--------------------------------------|---|
| Login Status use case | All Logins | All Logins (Non-CEF) All Logins (CEF format) |
| | Unsuccessful Logins | Unsuccessful Logins (Non-CEF) Unsuccessful Logins (CEF format) |
| | Successful Logins | Successful Logins (Non-CEF) Successful Logins (CEF format) |
| | Failed Logins | |
| Configuration | Configuration Changes | System configuration changes (CEF format) |
| Events use case | High and Very High Severity Events | High and Very High Severity CEF events |
| | Event Counts by Source | |
| | Event Counts by Destination | |
| | | All CEF events |
| Intrusion use case | Malicious Code | Malicious Code (CEF format) |
| Firewall use case | Deny (Firewall Deny) | |
| | Drop (Firewall Drop) | |
| | Permit (Firewall Permit) | |
| Network use case | DHCP Lease Events | |
| | Port Links Up and Down | |
| | Protocol Links Up and Down | |
| Connector System Status use case | CPU Utilization by Connector Host | |
| | Disk Utilization by Connector Host | |
| | Memory Utilization by Connector Host | |
| UNIX Server use case | CRON related events | |
| | IO Errors and Warnings | |
| | PAM and Sudo Messages | |
| | Password Changes | |
| | SAMBA Events | |

System Filters, continued

| Category | Unified Query Filters | Regular Expression Query Filters |
|------------------------------------|--|----------------------------------|
| | SSH Authentications | |
| | User and Group Additions | |
| | User and Group Deletions | |
| Windows Events use case | Account Added to Global Group Account Added to Global Group (CEF) | |
| | Audit Policy Change Audit Policy Change (CEF) | |
| | Change Password Attempt Change Password Attempt (CEF) | |
| | Global Group Created Global Group Created (CEF) | |
| | Logon Bad User Name or Password Logon Bad User Name or Password (CEF) | |
| | Logon Local User Logon Local User (CEF) | |
| | Logon Remote User Logon Remote User (CEF) | |
| | Logon Unexpected Failure Logon Unexpected Failure (CEF) | |
| | New Process Creation New Process Creation (CEF) | |
| | Pre-Authentication Failure Pre-Authentication Failure (CEF) | |
| | Special Privileges Assigned to New Logon Special Privileges Assigned to New Logon (CEF) | |
| | User Account Changed User Account Changed (CEF) | |


System Filters, continued


| Category | Unified Query Filters | Regular Expression Query Filters |
|----------------------|--|----------------------------------|
| | User Account Password Set User Account Password Set (CEF) | |
| | Windows Events (CEF) | |
| System Alerts | <p>The following filters search for specific internal alert events, which are written in CEF format to a special Internal Storage Group. These filters are available for both search methods. In addition to the following filters, you can define your own alerts based on the system health events listed in "System Health Events" on page 515.</p> <p>Note: Although these filters are displayed on Software Logger, these do not apply to it.</p> | |
| | CPU Utilization Above 90 Percent | CPU Utilization Above 90 Percent |
| | CPU Utilization Above 95 Percent | CPU Utilization Above 95 Percent |
| | Disk Failure | Disk Failure |
| | Root Partition Below 10 Percent | Root Partition Below 10 Percent |
| | Root Partition Below 5 Percent | Root Partition Below 5 Percent |
| | Device Configuration Changes | Device Configuration Changes |
| | Filter Configuration Changes | Filter Configuration Changes |
| | High CPU Temperature | High CPU Temperature |
| | | Bad Fan |
| | Power Supply Failure | Power Supply Failure |
| | RAID Controller Issue | RAID Controller Issue |
| | RAID Status Battery Failure | RAID Status Battery Failure |
| | RAID Status Disk Failure | RAID Status Disk Failure |
| | Storage Configuration Changes | Storage Configuration Changes |
| | Storage Group Usage Above 90% | Storage Group Usage Above 90% |
| | Storage Group Usage Above 95% | Storage Group Usage Above 95% |
| | Zero Events Incoming | Zero Events Incoming |
| | Zero Events Outgoing | Zero Events Outgoing |

Searching with Saved Queries

You can search using the Filters and Saved Searches that you create as well as the pre-defined system filters, explained in ["System Filters/Predefined Filters" on page 140](#).

To use an existing query:

1. Open the **Analyze** menu and click Search (**Classic Search** or **Search**).
2. Use one of these options to select the desired Filter, System Filter, or Saved Search.
 - Type **\$filter\$** or **\$ss\$** in the search text box and select a filter or a saved search from the dropdown list. See for more information, ["Opening Filters and Saved Searches via Autocomplete" on page 106](#).
 - Click the Load a Saved Filter icon () to view a list of all the saved filters and saved searches to display the Load Filter/Saved Search interface, as shown in the following figure.



The Load Filter/Saved Search interface enables you to quickly locate the saved filters and the saved search queries. Click on any of the column names to sort information. To view details of a filter or a saved search, click its row. Details are displayed in the text box below.

To load a filter, select the filter or saved search you want to use and click **Load+Close**. The filter rows display the search query.

To load a saved query, open the **Saved Searches** page, select a search, and click **Load+Close**.

Scheduling Date and Time Options

Tip: Make sure you are familiar with the information in ["Time/NTP" on page 462](#) before setting the schedule.

Choose Every Day, Days of Week, or Days of Month from the upper pull-down menu.

Note: When specifying multiple days, separate them with a comma. When specifying the time, use 24-hour format.

1. If **Every Day**, select one of the following options from the lower pull-down menu, and enter the necessary values:
 - **Hour of day:** (0-23) Enter the time you want the task to run (in 24 hour format) in the Hours field. Midnight is zero (**0**).
 - **Every:** Select Hours or Minutes from the right-most pull-down menu and specify how frequently you want the task to run.
 - **Hours:** (1-23) Enter how frequently in hours you want the task to run. The result is every n hours every day.
Minutes: (15-59) Enter how frequently in minutes you want the task to run. The result is every n minutes every day.
2. If **Days of Week**, select from the following options from the lower pull-down menu, and enter the necessary values:
 - **Days:** (1-7) Enter the days of the week you want the task to run (Sunday=1, Monday=2, and so on).
 - **Hour of Day:** (0-23) Enter the time you want the task to run in the text field to the right. **0** is midnight.
 - **Every:** Select Hours or Minutes from the right-most pull-down menu and specify how frequently you want the task to run.
Hours: (1-23) Enter how frequently in hours you want the task to run. The result is every n hours on the selected days.
Minutes: (15-59) Enter how frequently in minutes you want the task to run. The result is every n minutes on the selected days.
3. If **Days of Month**, select from the following options from the lower pull-down menu, and enter the necessary values:
 - **Days:** (1-31) Enter the day or days of the month you want the task to run.

Note: The number of days in a month vary. Scheduled tasks will only run if the specified day exists for that month. Tasks scheduled on the 31st day of the month will not run in April, February, June, November, and September. Tasks scheduled on the 29th day of the month will

only run in February during leap years.

- **Hour of Day:** (0-23) Enter the time of day you want the task to run. (You cannot select Every for this option.)

Examples:

- To run the scheduled job every 45 minutes of every day, select **Every Day** in the upper Schedule pull-down menu. Choose **Every** from the lower pull-down menu, enter **45** in the text box and select **Minutes**.
- To run the scheduled job every four hours on Tuesdays and Thursdays, select **Days of Week** from the upper Schedule pull-down menu and enter **3,5** as the **Days**. Then choose **Every** from the lower pull-down menu, enter **4** in the text box.
- To run the scheduled job on the 14th of each month at 3 AM, select **Days of Month** from the upper Schedule pull-down menu and enter **14** as the **Days**. Then choose **Hour of day** from the lower pull-down menu and enter **3** in the text box. (To run the scheduled job at 3 AM and 3 PM, you would enter 3,15.)

Enriching Logger Data Through Static Correlation

This topic applies only to Classic Search page

The **lookup** search operator enables you to augment data in Logger with data from an external file. This enables geo-tagging, asset tagging, user identification, and so on, through static correlation.

You can use the **lookup** operator to add information to your search results that is not part of the original data stored on Logger. You do this by creating an external file containing the data, uploading that Lookup file to Logger, and then using the **lookup** operator to create a join between Logger events and the uploaded Lookup file.

For example, if you want Logger search results to include which country source IP addresses are located in, you can create a file listing the IP addresses and countries and then upload that file to Logger as a Lookup file. After that, you can use the **lookup** operator to perform a join between the sourceAddress field in the Logger events and the IP address column in the Lookup file, and display the country in the search results.

- For information about creating Lookup files and uploading them to Logger, see ["Lookup Files" on page 336](#).
- For information on how to use the **lookup** operator when searching, see ["lookup" on page 539](#).

Indexing

Once you have initialized Logger, it starts scanning events automatically and indexing them.

Logger's storage technology enables automatic indexing of events in these ways:

- Full-text indexing: Each event is tokenized and indexed. See ["Full-Text Indexing \(Keyword Indexing\)" below](#).
- Field-based indexing: Event fields are indexed based on a predetermined schema. See ["Field-Based Indexing" below](#).
- Superindexing: Certain event fields are super-indexed so that you can find rare field values quickly. See ["Superindexing" on page 149](#).

All events received after initialization are indexed for full-text search, a default set of fields is indexed for field-based search, and a default set of fields is superindexed for fast needle-in-a-haystack searches.

All events are timestamped with the receipt time when received on the Logger. The default fields are automatically indexed. For the remaining fields, Logger uses the receipt time of an event and the time when a field was added to the index to determine whether that event will be indexed. If the receipt time of the event is equal to or later than the time when the field was added to the index, the event is indexed; otherwise, it is not.

Full-Text Indexing (Keyword Indexing)

For full-text indexing, each event (CEF or non-CEF) received on Logger is scanned and divided into keywords and stored on the Logger. The full-text search options control the manner in which an event is tokenized as described the Full-text Search Options section of the ["Global Search Options" on page 328](#).

Field-Based Indexing

The field-based indexing capability allows for fields of events to be indexed. The fields are based on a predetermined schema. The Logger's reports and the field search method utilize these indexed fields to yield significant search and reporting performance gains.

Field-based indexing for a recommended set of fields is automatically enabled at Logger initialization time. You can add more fields to an index at any time. (See ["To add fields to the field-based index:" on page 326](#) for instructions.) Once a field has been added, you cannot remove it.

A list of the default index fields, along with their field descriptions is available from the Logger Configuration menu. For instructions on how to view the default Logger Schema fields, see ["Default Fields" on page 333](#).

Note: Micro Focus strongly recommends that you index fields that you will be using in search and report queries.

The fields created when a predefined or user-defined rex parser parses the non-CEF events cannot be indexed using the field-based indexing capability. See ["Parsers" on page 371](#) for more information about rex parsers.

In addition to indexing the fields included in the field-based indexing list, Logger indexes event metadata fields—event time, Logger receipt time, and device address—for every event. The event metadata fields are also known as “internal” fields.

The following fields are available for indexing. The fields that Logger starts indexing automatically after Logger initialization are indicated in bold font.

Note: Logger allows indexing of the **requestUrl** field. This field returns website addresses from the World Wide Web. Indexing **requestUrl** will return results faster, but will also significantly increase the size of your search results, which may impact your search storage capacity.

| Index Fields | | |
|-----------------------------|----------------------------|--------------------------|
| agentAddress | deviceCustomDate2 | flexDate1Label |
| agentHostName | deviceCustomDate2Label | filePath |
| agentNtDomain | deviceCustomNumber1 | flexNumber1 |
| agentSeverity | deviceCustomNumber1Label | flexNumber1Label |
| agentType | deviceCustomNumber2 | flexNumber2 |
| agentZone | deviceCustomNumber2Label | flexNumber2Label |
| agentZoneName | deviceCustomNumber3 | flexString1 |
| agentZoneResource | deviceCustomNumber3Label | flexString1Label |
| agentZoneURI | deviceCustomString1 | flexString2 |
| applicationProtocol | deviceCustomString1Label | flexString2Label |
| baseEventCount | deviceCustomString2 | message |
| bytesIn | deviceCustomString2Label | name |
| bytesOut | deviceCustomString3 | priority |
| categoryBehavior | deviceCustomString3Label | requestClientApplication |
| categoryDeviceGroup | deviceCustomString4 | requestContext |
| categoryObject | deviceCustomString4Label | requestMethod |
| categoryOutcome | deviceCustomString5 | requestUrl |
| categorySignificance | deviceCustomString5Label | requestUrlFileName |
| categoryTechnique | deviceCustomString6 | requestUrlQuery |
| customerName | deviceCustomString6Label | sessionId |
| destinationAddress | deviceEventCategory | sourceAddress |
| destinationDnsDomain | deviceEventClassId | sourceHostName |
| destinationHostName | deviceExternalId | sourceMacAddress |

| Index Fields | | |
|-------------------------------|-------------------------|--------------------------|
| destinationMacAddress | deviceHostName | sourceNtDomain |
| destinationNtDomain | deviceInboundInterface | sourcePort |
| destinationPort | deviceOutboundInterface | sourceProcessName |
| destinationProcessName | deviceProduct | sourceServiceName |
| destinationServiceName | deviceReceiptTime | sourceTranslatedAddress |
| destinationTranslatedAddress | deviceSeverity | sourceUserId |
| destinationUserPrivileges | deviceVendor | sourceUserName |
| destinationUserId | deviceVersion | sourceUserPrivileges |
| destinationUserName | deviceZone | sourceZone |
| destinationZone | deviceZoneName | sourceZoneName |
| destinationZoneName | deviceZoneResource | sourcezoneResource |
| destinationZoneResource | deviceZoneURI | sourceZoneURI |
| destinationZoneURI | endTime | startTime |
| deviceAction | eventId | transportProtocol |
| deviceAddress | externalId | type |
| deviceCustomDate1 | fileName | vulnerabilityExternalID |
| deviceCustomDate1Label | flexDate1 | vulnerabilityURI |

Superindexing


In addition to full text and field based indexing, Logger and later creates superindexes for common IP address, host name, and user name fields. Superindexes enable Logger to quickly determine whether a particular field value has been stored on this Logger, and if it has, to narrow down the search to sections of data where that field value exists. Therefore, searches that can take advantage of superindexes return very quickly if there are no hits and return results more quickly than regular searches when there are very few hits.

- For information on how to use superindexes, see ["Searching for Rare Field Values" on page 117](#).
- A complete list of super-indexed fields is included in ["Using Super-Indexed Fields to Increase Search Speed" on page 117](#).

Viewing Alerts

You can configure Logger to alert you by e-mail, an SNMP trap, or a Syslog message when a new event that matches a specific query is received or when a specified number of matches occur within a given time

threshold. For more information, see ["Logger Alert Types" on page 388](#). In addition to receiving an alert via e-mail, an SNMP trap, or a Syslog message, you can view Alerts and the base events that triggered them on the **Analyze > Alerts** page



To view Alerts, choose a predefined time range, such as “Last 2 hours” or “Today,” or choose “Custom Time Range” to reveal additional fields for specifying a time range manually. This aspect works like Search. Refer to ["Time Range" on page 86](#) for more detail. Alerts search only considers internal events. Consequently, no search type option is displayed for this functionality.

Name the alert after it has been created. Use the **Show** options to view only events associated with a particular Alert. The default is All Alerts.

Alert events are labeled as ‘Action Engine’ and are triggered by base events. You can also select whether to view the base events and which fields to view by using the **Base Event Fields:** option.

Like on the Search page, the **Go** button triggers the search, the **Export Results** button enables you to create a PDF or CSV file that contains the search results, and the **Auto Refresh** option determines whether and how frequently the displayed search results are updated.

Live Event Viewer

This topic applies only to Classic Search page

The Live Event Viewer provides real-time view of the incoming events that match the criteria you specify. This functionality is useful in environments where the need to view an event quickly is important; for example, a financial institution might be interested in viewing a specific transaction type as soon as it occurs. Because the latency between the events arriving at Logger and the display time is quite less, events might not have been indexed on Logger before being displayed.

The Live Event Viewer composes of two tabs—Search Composer and Search Results. The Search Composer is for defining the search criteria and the Search Results tab displays the matching events in real time.

The following figure shows the Search Composer. If you specify more than one search term, the resulting query uses the AND operator to combine them. For example, if the first search term searches for “failure” and the second one **excludes** “admin,” the resulting query is “failure AND NOT admin.”

Search Composer

Search Composer

Search Results

Help

What do you want to find? Build a new filter or load an existing filter

1

FILTER

+

-

|

Exclude/Include Terms

Search Terms

2

Search For:

Choose if a logical NOT should be applied to the search term and enter the text to search for

Where do you want to look? Choose from device groups and storage groups.

3

Device Groups

Storage Groups

4

Start

Search Composer Legend

| Feature | Description | Feature | Description |
|---------|---|---------|---|
| 1 | Load a saved filter Save the current filter Add a filter row Remove a filter row Remove all filters | 3 | Specify device groups Specify storage groups |
| 2 | Enter search criteria | 4 | Start or Stop Live Event Viewer |

The Search Results tab provides the Play, Pause, Stop, Clear, and Export buttons that enable you to control the display in a manner similar to any electronic device, as shown in the following figure.

Micro Focus Logger (7.0)

Page 151 of 668

Search Results Tab

Search Composer Search Results Help

Filter **storageGroup(Default Storage Group)**

1 2 **storageGroup(Default Storage Group)**

3 Searching 3 events (3 scanned) 4 Display Buffer 1000 5 14:27 6 7

1 : 2019/02/12 06:32:53 PST n15-214-194-h65.arcsight.com [Auto_Test_TCP_Receiver--InstallLogger] searchDefaultStorageGroup local Default Storage Group search line 1

2 : 2019/02/12 06:32:53 PST n15-214-194-h65.arcsight.com [Auto_Test_TCP_Receiver--InstallLogger] searchDefaultStorageGroup local Default Storage Group search line 2

3 : 2019/02/12 06:32:53 PST n15-214-194-h65.arcsight.com [Auto_Test_TCP_Receiver--InstallLogger] searchDefaultStorageGroup local Default Storage Group search line 3

Search Results Legend

| Feature | Description | Feature | Description |
|---------|---------------------------------------|---------|------------------------|
| 1 | Play / Pause / Stop / Delete / Export | 5 | Events scanned so far |
| 2 | Filter specified in Search Composer | 6 | Events display maximum |
| 3 | Current state | 7 | Search timer |
| 4 | Events found so far | 8 | Matching event number |






The following list highlights the features of Search Results display:

- Events are displayed in the raw event format and not in the columnar, table form as displayed in the Search Results page (**Analyze > Classic Search**) when you run a search query.
- A user can launch a maximum of one Live Event Viewer. There can be a maximum of five Live Event Viewers running on Logger at any time.
- The regular expression search method is used to identify matching events. Therefore, you can specify regular expressions as the search term in the Search Composer.
- Buffer Size defines the maximum number of events displayed in the Viewer. By default, the Buffer Size is 1000; however, it can be set to any number between the range of 20 and 5000.
- By default, the search is run for 15 minutes and then stopped to preserve system resources. If you need to run the search for longer than 15 minutes, click the icon next to the countdown timer to reset the timer to 15 minutes.
- When you click Pause, the Search Results display is frozen. However, the search operation continues in the background and the new matching events are buffered until a maximum of 1000 events have been buffered or the search timer, which continues to count down even when the Search Results display is frozen, reaches 00:00.
- If the timer has not reached 00:00, you can click Play to resume the paused search operation. When you click Play, the buffered events are displayed. The newly found events are appended to the previously found events on the Search Results display screen.

- When you click Stop, the search for matching events and the countdown of the search timer stop. When you click Play, the search is started afresh—the currently displayed events are cleared from the Search Results screen, the search timer is reset to 15 minutes, and the search starts again.
- You must stop the search operation to export the matching events.

To launch a Live Event Viewer:



Note: Live Event Viewer is a resource-intensive application that can impact the overall performance of your Logger if run for a long period of time. Therefore, use this feature selectively and for short periods of time.

1. Open the **Analyze** menu and click **Live Event Viewer**.
2. In the Search Composer tab, enter the search terms or click the () icon to select a saved filter.
You can enter search terms that the event must contain (Search For:) or terms that the events must not contain (Exclude From Search:). Click the "Search For:" field to display a drop-down list from which you can select "Exclude From Search:".
If you specify more than one search term Logger uses the AND operator to combine them in the resulting search query.
 - To add additional search term click the () icon.
 - To remove a search term, click the () icon.
 - To remove all search terms, click the () icon.
3. Enter constraints to limit your search to specific device groups, devices, or storage groups in the "Where do you want to look?" section. Click the () icon to display a list from which you can choose the constraints.
4. Click **Start**.
5. The search results are automatically displayed in the Search Results display screen.

To update the Live Event Viewer query:

1. In the Search Composer tab of the Live Event Viewer, update the search terms.
2. Click **Stop** first and then click **Start** to start search using the new search terms.

To export Search Results display:

1. Make sure you have stopped the Live Event Viewer. To do so, click the () icon in the Search Results display window.
2. Click the () icon to open the Export Options window.
3. To export the displayed search results, select the Export options, as described in ["To export the results of your search:" on page 135](#) Then click **Export**.

Using Global ID

GlobalEventID allows to have a unique 64 bits identifier across all ArcSight platform modules. Ideally, each event (health, audit, base, and alerts) that enters the ArcSight Ecosystem should be checked and if required, assign a GlobalEventID. Once this is generated, it cannot be unassigned and it will remain even if future upgrades are made.

Users can search for **GlobalEventId** by accessing the Search page (**Analyze > Classic Search** or **Analyze > Search**). This feature is also included in Reports. This is an indexed field by default and cannot be super indexed.

Generator ID

Generator ID is a value available as a service and separately for all platforms that have the feature. Each platform that has the GlobalEventID functionality enabled requires one or more generator IDs for that function.

You can set up the generator IDs from either Logger or ArcSight Management Center. For more information on how to configure from ArcSight Management Center, see ArcSight Management Center Guide at [Micro Focus Community](#).

To configure generator ID from Logger:

1. Go to **Logger UI > Configuration > GlobalID Configuration**.
2. Set a different value from 1 to 16 383 for each process (field). It is mandatory to fill all fields.
3. Save the changes

Note: A different generator ID must be configured per platform per environment. Otherwise, it can cause duplicate GlobalEventIDs.

Note: Restart the following processes whenever a GlobalEvent ID parameter has been updated:
Servers, Web, APS, and Connector.

Enable and Disable

By default, this feature is enabled and generator ID's are -1. Consequently, events are generated with a GlobalEventId value of 0. Whether you enable or disable the feature, it is necessary to add generator IDs for all processes and restart the servers.

If you perform this action from Logger, this will not cancel the rest of GlobalEventID activities from the ArcSight Ecosystem as it will only affect Logger incoming and internal events.

Global ID Configuration

Enable Global ID feature ☐

Generator ID - Servers process

Generator ID - APS process

Generator ID - Receivers process

Generator ID - Connector process

*Server, APS, Receivers and Connector Process must be restarted so the Global ID changes take effect.

Save

Cancel

GlobalEvent ID Creation

GlobalEventID follows a sequential order that can register up to 1 million instances per second. Logger designates a GlobalEventID to all internal events. Logger only generates GlobalEvent ID values for CEF events.

Note: Internal events created, archived and stored before Logger 6.7 do not have a GlobalEvent ID. Logger does not generate one unless they are sent to a through Connector Forwarders or ESM forwarder with the GlobalEvent ID property. Logger will not generate a GlobalEvent ID for events received via TCP/UDP receivers.

Every time an event is forwarded through a Connector 7.11 or later, or to Logger version 6.7 or later, a GlobalEventID is generated. Nevertheless, Logger does not assign GlobalEventID if it has been already designated by the ArcSight Ecosystem for the events that comes to Logger.

Chapter 4: Reporting

Reporting is an essential tool for communicating the state of your network security to internal and external stakeholders. A report is a captured view or summary of events. Reports can be viewed from within Logger, or exported for sharing in a variety of file formats.

| | |
|--|-----|
| • The Reports User Interface | 156 |
| • Using the Right Tool for the Job | 159 |
| • Finding and Managing Reports | 165 |
| • Running Reports | 183 |
| • Viewing Reports | 190 |
| • Publishing Reports | 202 |
| • Exporting and Uploading Reports | 206 |
| • Emailing a Report | 209 |
| • Designing Custom Reports | 211 |
| • Building Dashboards | 244 |
| • Designing Queries, Parameters, and Templates | 250 |
| • Reports Administration | 285 |

The Reports User Interface

Logger Reports has been updated, improved, and expanded for this release. Multiple tabs, new tools, and rendering options are some of the new elements that will make your Reporting experience better.

| | |
|--------------------------------|-----|
| • Multitasking with Tabs | 156 |
| • The Reports Menu | 157 |
| • The Reports Home Page | 158 |

Multitasking with Tabs

Report activities now open within tabs. Logger supports up to ten open Report tabs, so you can move easily from screen to screen as you create, manage, and generate reports.

- The first tab is the **Home** page. See ["The Reports Home Page" on page 158](#).
- Reports, dashboards, queries, and other report functions can run concurrently in different tabs (but this may affect your Logger performance). See ["Best Practices for Running Reports" on page 184](#).

The Reports Menu

The Reports menu gives you easy access to all the reporting tools from any tab or page within Reports.

Note: Access permissions to these tools must be granted by an administrator. See ["Administrative Prerequisites" on page 163](#).

Description

Use **Explorer** to navigate to a desired report, query, parameter, dashboard, dashboard widget, or favorite item. In previous Logger releases, there were five different Explorers, one for each category or object. With this release, you can access any report or object from this menu. See ["Reports Explorer" on page 165](#).

Use **Schedule Reports** to run reports at times of low activity, at regular intervals, or to run reports that would otherwise time out after an hour. As part of scheduling a report job, you can set delivery options to, for example, email, save, or publish the resulting reports. See ["Scheduled Reports" on page 177](#).

Use **Design** tools to create and customize the different "objects" that together make up a report. See ["Design Tools: New Reports and Report Objects" on page 160](#).

New user interfaces include:

- **Dashboards** Easily create Smart dashboards that can display multiple charts using different queries. See ["Building Dashboards" on page 244](#).
- **New Report** Create, customize, and modify any Ad hoc or Smart report. The Smart View page will get you where you need to go to complete your objective. See ["Smart Reports" on page 217](#).

Logger veterans will recognize these familiar tools:

- **Queries** Create and edit the queries that power your reports. See ["Queries" on page 250](#).
- **Parameters** Create and edit the parameters that define the data values within report queries. See ["Parameters" on page 273](#).
- **Parameter Value Groups** Create and edit groups of parameter values to make applying report run-time values easier. See ["Parameter Value Groups" on page 281](#).
- **Template Styles** Create and customize report template styles, giving it a custom, finished look. See ["Template Styles" on page 284](#).

Use **Classic** tools if you are a long-time Logger user, and you prefer the familiar Ad hoc Designer and Dashboard tools to create and customize your dashboards and reports. See ["Designing Custom Reports" on page 211](#).

- **New Report** Create and customize Ad hoc reports in the Ad hoc Report Designer, with its familiar tab-based interface from earlier releases. Base a new report on an existing one, or create your own. See ["Classic: The Ad hoc Report Designer" on page 224](#).
- **Dashboards** Create, view, manage, and maintain Ad hoc dashboards. See ["Dashboard Migration Tool" on page 249](#).

Note: Classic Dashboard supports both Smart and Ad hoc report widgets, however, you can include only one query object per dashboard. To create a Smart Dashboard, see ["Building Dashboards" on page 244](#).

Use **Administration** tools to customize and configure your Logger Reports environment, troubleshoot report jobs, and backup and restore Report content. Administration tools are for users who support and maintain the Logger Reports environment.

- **Deploy Report Bundler** Load and deploy packages of new or updated reports to your Logger system. See ["Deploying a](#)

Description

[Report Bundle](#) on page 307.

- **Report Configuration** View or modify the report server configuration values, including investigate connection configuration. See ["Report Configuration" on page 287](#).
- **Report Category Filters** Assign and remove search group filters. See ["Report Category Filters" on page 301](#).
- **Report Categories** Add, modify, and delete Explorer Categories. See ["Report Categories" on page 289](#).
- **Job Execution Status** Admins can view the status of all Report jobs. See ["Job Execution Status" on page 296](#).
- **iPackager** Package reports and report objects, which can be imported to other Loggers, or redeployed after an upgrade. You can also deploy a report configuration on multiple Loggers. See ["iPackager Utility" on page 299](#).

Use **Report status** to view published reports and other reports. You can search by date, owner, root, execution type, status and name.

The Reports Home Page

The **Reports** Home Page is available in the **Home** tab, providing easy access to the following widgets:

- **Smart Report Designer** Provides access to create a smart report. See ["Creating a New Smart Report" on page 218](#)
- **View Dashboard** Provides direct access to create a dashboard. See ["Creating a New Smart Dashboard " on page 248](#)
- **Job Execution Status** lists the succeeded, failed and completed jobs. See ["Job Execution Status" on page 296](#)
- **Report Execution Status** Provides direct access to other reports. See ["Other Reports" on page 175](#)
- **iPackager** Allows to package repository objects, users and settings from local file system. See ["iPackager Actions" on page 300](#)
- **Deploy Report Bundle** Allows to load and deploy new reports packages. See ["Deploying a Report Bundle" on page 307](#)
- **Favorites** lists the Favorite Entities.
- **Recent Reports** lists the ten most recently run reports by run time. See ["Recent Reports" on page 171](#).
- **Published Reports** lists reports for which the output results have been saved for subsequent use. See ["Publishing Reports" on page 202](#).

The functions available to you from each list will vary by report type, display format, user permissions, and so forth.

Accessing the Reports Home Page

To access the Reports home page:

1. From the Logger navigation bar, click **Reports**.

To return to the Reports home page from within the Reporting tool:

1. Click the **home** tab (the upper-left tab)

Using the Right Tool for the Job

Use this handy table to understand the Logger workflow for Reports and Dashboards:

Reports and Dashboards

| To Do This | With (report object) | Execute From | | Opens In | Mode |
|---|-------------------------|--|-----------------------------|------------------------|------------------|
| | | Explorer Menu | Report Menu | | |
| <ul style="list-style-type: none"> • View a report | Smart report | Any Run option | None | Smartview | View* |
| | Ad hoc or Studio report | Any Run option except "Run as Smart Report" | None | Powerview | View only |
| <ul style="list-style-type: none"> • Modify a report • Create a new report from an old one • Create a new report | Smart report | Customize | Design > New Report | Smartview | View* |
| | Ad hoc or Studio report | Customize | Classic > New Report | Ad hoc Report Designer | Design |
| <ul style="list-style-type: none"> • Publish a report | Smart report | Smartview | None | Smartview | View* |
| | Ad hoc or Studio report | Powerview | None | Powerview | View only |
| <ul style="list-style-type: none"> • Create a new dashboard | Published Smart report | | Design > Dashboards | Smartview | Dashboard Design |
| <ul style="list-style-type: none"> • View a dashboard | Smart dashboard | View Dashboard | Design > Dashboards | Smartview | Dashboard Design |
| <ul style="list-style-type: none"> • Modify a dashboard • Create a new dashboard from an old one | Smart dashboard | | Design > Dashboards | Smartview Dashboards | Design |
| *Click the Edit Mode/Design mode toggle in Smartview to select the mode | | | | | |

For other reporting objects, tools, and tasks, see the following information:

Other Report Objects

| To Do This... | See... |
|---|--|
| <ul style="list-style-type: none">Find, organize, and select report objects for many tasksRun reports | "Reports Explorer" on page 165 |
| <ul style="list-style-type: none">Run or re-run a report you have used recently | "Recent Reports" on page 171 |
| <ul style="list-style-type: none">View, filter, and delete published reportsComment, upload, or export a published report | "Published Reports" on page 172 |
| <ul style="list-style-type: none">View, filter, and delete reports run in background modeView, upload, or export other reports | "Other Reports" on page 175 |
| <ul style="list-style-type: none">Schedule a report to run at a specified time and intervalEdit, enable/disable, or delete a scheduled reportRun reports that take more than one hour to complete | "Scheduled Reports" on page 177 |
| <ul style="list-style-type: none">Create and edit report queries, parameters, parameter value groups, and templates | "Designing Queries, Parameters, and Templates" on page 250 |

Design Tools: New Reports and Report Objects

The Logger Reports Design tools provide a place where you can easily create new reports, dashboards, queries, and other report objects.

If you are new to the Logger Report Designer, we recommend starting with an existing report as a basis for a new one. See ["Create a New Report from an Existing One" on page 213](#).

If you are starting a new report from scratch, or for more details on each of the settings in the Report Designer, see ["Create a New Query from Smart Designer" on page 255](#).

Frequently-Asked Questions

Logger report tools are transitioning from legacy Ad hoc tools to the Smart-enabled report tools. When deciding how to best use the Logger reports and tools, consider these frequently-asked questions.

How do Smart Reports differ from Ad hoc and Studio Reports?

Smart reports, dashboards, Smart designer and viewer are the next step in Logger report design and utilization. The Smart View pages (the designer and viewer) are intuitive web-based interactive interface, designed to visualize and analyze large amounts of data.

Smart Reports share most of the same functionality as Ad hoc and Studio reports, with some important exceptions:

- **Smart and iHTML formats** — Only Smart reports have Smart and iHTML formats available for viewing, export, and so on. Smart-enabled reports use a simple, non-paginated template, for fast web display of short (iHTML) and long (Smart) reports. Smart reports are designed to quickly render reports when you want to see the data with minimum processing. See ["Report Formats for Viewing and Export" on page 196](#).

Tip: To create a Smart report, Click **Design > New Report** from the menu, select your query or report, and save it as a Smart report. From the Smart designer, you can modify the new report. See ["Creating a New Smart Report" on page 218](#).

- **Smart dashboards** — Multi-query Smart dashboards can only be built from published Smart report widgets using the Smart (**Design > Dashboards**) tool. Either Dashboard designer can create Ad hoc dashboards, which are limited to one query per dashboard.

Note: This is a note. See ["Creating a New Smart Dashboard " on page 248](#).

- **Studio reports** — This is a legacy report type, and you should modify and manage them using the Classic report tools.

See also

- ["Smart Reports" on page 217](#)
- ["Creating a New Smart Report" on page 218](#)
- ["The Smart Report Designer" on page 215](#)
- ["Create a New Report from an Existing One" on page 213](#)
- ["The Smart Report Viewer" on page 193](#)
- ["Working with Logger Report Designers" on page 212](#)

Which Reports Open Where?

In this release, we introduce some new tools, while maintaining support for the familiar old ones.

- Explorer is now a single interface, with merged capabilities.
- Smart reports and dashboards have new capabilities that require upgraded user interfaces.
- Ad hoc reports have undergone a similar upgrade, to the Powerview designer.

From Explorer:

When you run HTML reports in Explorer, they display in one of these new user interfaces:

- **Smart Designer** is the new WYSIWYG design tool for Smart reports. You can modify all report options, charts, matrices, layouts, and more in real time. Also available through Design > New Report. See ["The Smart Report Designer" on page 215](#).

Smart Viewer is similar to Smart Designer, but with limited options for reports that open for viewing. See ["The Smart Report Viewer" on page 193](#).

- **Powerview designer** is the new WYSIWYG design tool for Ad hoc and Studio reports. You see your data view and your chart on the same page. See ["The Powerview Designer" on page 219](#).

Ad hoc Report Viewer is similar to Powerview designer, but with limited options for reports that open for viewing. See ["The Ad hoc Report Viewer" on page 191](#).

If the report uses any other kind of format, the report runs, and you may have the option to save the file, or open it in the correct application. See ["Exporting and Saving a Report" on page 206](#).

From Design > New Report:

When you click **New Report** from the Design menu, the Smart View page opens.

- If you select an existing report query, it will take you to Filter Data where you can choose the time range and the data your report will display. See, ["The Smart Report Viewer" on page 193](#).
- If you select an existing report (Ad hoc or Smart), it opens in Smart Designer. See, ["The Smart Report Designer" on page 215](#).
- If you click **Queries** from the Design menu, it will take you to the Query Object Editor. See, ["Designing a New Query" on page 256](#)

To enter a SQL query, click **Design**.


From Classic > New Report:

When you click **New Report** from the Classic menu, the Ad hoc Report Designer opens the Data Source tab and you need to choose the query object. See, ["Data Source" on page 228](#).

How Does the Smart Viewer Differ from the Ad hoc Viewer?

The look and layout are different, but the functionality is the same. Menu options include refresh, export, publish, comment, and upload. See ["Viewing Reports" on page 190](#).

Smart viewer and menus



Tip: The Smart viewer user interface (UI) is part of a migration towards the Smart tools, and eventual retirement of the ad hoc tools.

Ad hoc viewer and menus

How do Smart, Powerview, and Ad hoc Design Tools Differ?

The look and layout are different, but the basic functionality is the same. The Smart tools have some additional options for display, export, and so forth.

For creating or customizing reports, you have three options:

- **The Smart designer** — This tool is your one-stop shop for charts, maps, customizations, and tuning of Smart reports. See ["The Smart Report Designer" on page 215](#).
- **The Powerview designer** — This tool is to Ad hoc reports what the Smart designer is to Smart reports. Right-click within the report to create charts, maps, customizations, and save as a new report. See ["The Powerview Designer" on page 219](#).
- **The Ad hoc Report Designer** — Click **New Report** from the Reports Classic menu to create, modify, or reuse report objects and save them as new reports. See ["Classic: The Ad hoc Report Designer" on page 224](#).

Administrative Prerequisites

Before users can create and view reports, a Logger Administrator must perform the following tasks:

- Assign access rights to users and any user groups. See ["Assigning Access Rights" on the next page](#).
- Optionally, your system may require an adjustment to the Database Connection Timeout value, one of the Report Administration settings. See ["Adjusting Timeout Values for Long-Running Reports" on the](#)

[next page.](#)

Note: Your Logger must be running a valid GB per day or EPS license without one, Reporting is not available.

For a complete list of all the administrative report tools and options, see ["Reports Administration" on page 285.](#)

Assigning Access Rights

Administrators can set access rights to various report categories, reports, and report options (such as view, publish, and edit) based on user roles and Logger Report Group affiliation. For example, you can grant privileges to view some reports but not others, to view but not schedule or publish a report, or to view and schedule but not edit a report.

Access rights for report options and user groups are configured and managed from the **User Management** link on the System Admin menu. For more information on System Admin User/Group management, see ["Setting Logger User Permissions" on page 510.](#)

What Access Rights are Necessary?

Access rights are applied at the folder level. To access a particular report, a user must have access rights to all the higher-level folders in its path.

For example, if a user needs access to User Tracking reports (**Foundation > Intrusion Monitoring > User Tracking**), you must give them access rights to Foundation and Intrusion Monitoring nodes as well as User Tracking.

Some users may require access to a more limited subset of reports:

- If a user needs access to specific report **categories**, create a User Group with the access rights to just those categories, and assign them to that User Group. See ["Creating a Reports User Group" on page 285.](#)
- If a user needs access to specific **reports**, you can create a new category folder with only the required reports, and give them rights to that folder. See ["Report Categories" on page 289.](#)

Adjusting Timeout Values for Long-Running Reports

There are two timeout values that can affect long-running reports.

- The **client timeout** is 1 hour. If an ad hoc report takes more than an hour to run, it will time out. Use a scheduled report instead.
- The default **database connection timeout** for scheduled reports is 4 hours. If a scheduled report takes more than 4 hours to run, you can increase the database connection timeout from the Report Configuration page. See ["Report Configuration" on page 287.](#)

Another option is to restrict large reports to run only in the background. See ["Restrict Long Reports to Run in the Background" on page 186](#).

Finding and Managing Reports

Logger has a number of tools to help you find, organize, and manage reports.


- **Dynamic report lists** — Recent Reports, Published Reports, and Other Reports dynamically display the reports you use most often.
- **Report storage** — Explorer stores and manages all report, query, parameter, dashboard, dashboard widget, or Favorite report object for which you have access permissions. See ["Reports Explorer" below](#).
- **Report Administration** — Report Admins can use Administrative tools to manage report jobs and the category folders where they reside. See ["Reports Administration" on page 285](#).

Tip: Reports users with limited access rights will only see reports for which they have rights. See ["Assigning Access Rights" on the previous page](#).

- [Reports Explorer](#)165
- [Recent Reports](#)171
- [Published Reports](#) 172
- [Other Reports](#) 175
- [Scheduled Reports](#)177

Reports Explorer

Explorer is an organization tool that gives you quick access to any existing report, query, parameter, dashboard, dashboard widget, or Favorite report object for which you have access permissions. In previous versions of Logger, there were six Explorers, one for each report object type. In this release, the Explorers have been consolidated into one convenient tool for all report objects.



Reports and report objects, such as queries and parameters, are organized and grouped based on their function into folders (called Categories). For example, a report pertaining to a database can be stored under the Database category.

Explorer lists all categorized reports and report objects. It comes with some pre-defined, commonly used categories. You can also add custom categories based on your requirements, if you have access rights to do so.

Note: Administrators are the only users who have full Reports access by default. See ["Assigning Access Rights" on page 164](#).

To open Explorer:

1. From the top of the Reports menu, click **Explorer**.

This action toggles the Explorer to open or close, without opening a new tab. In this way, Explorer is available from any tab, and out of the way when you don't need it.

What are Report Objects?

Report objects are designed to be modular, and can be used for dashboards and complex reports. Report objects include:


- Standard and custom reports
- Published and scheduled reports
- Dashboards
- Dashboard widgets
- Query objects
- Parameter objects
- Categories (folders)

Working with Explorer


Explorer allows you to access, store, search, and manage your report objects in a categorized tree structure. As part of this process, you can:

- Browse for report objects
- Search by name, object type, the last modified date, etc.
- Filter by Report Type and Report Format
- Add, manage, and delete Categories (with appropriate permissions)
- Tag any report object as a Favorite for quick retrieval. See ["Explorer Favorites" on page 168](#).

To run a report manually

1. Click  beside a category folder to display the category objects and any subcategories.
2. Navigate to the report of interest and right-click the report.
3. From the context menu, select **Quick Run with Default Options**, **Run in Background**, **Run Report**, or **Run in Smart Format**.
4. Enter any run-time filter or parameter criteria. See ["Run-Time Filters, Criteria, and Parameters" on page 187](#)
5. Click **Run**, **Run Now**, **Preview**, or **Run in Background**. See ["Running Reports" on page 183](#).


To browse for report objects


1. Click  beside a category folder to display the category objects and any subcategories.
2. Navigate to the report object of interest.
3. Right-click an object in a category to perform an action on it. For a description of options, see ["Explorer Options and Context Menus" on page 169](#).

To search by name for a report object

1. Above the Name column, enter a matching string in the search tool, **device** in this example.


Name

2. Click  to filter the results. All report objects that include the word "device" will display.
3. To cancel the search filter, click **X** to reset the Explorer display.

To filter by object type


1. Click the drop-down menu in the Object Type column head to see the object filter list.
2. Toggle which objects to display by checking or unchecking the object(s).



3. Click outside the filter list to refresh the Explorer and display the selected objects.

To change the column list sorting order

1. Click within the column header you want to change. A small gray triangle displays.



2. Click ▲ to filter the results by that column. Click ▼ to toggle sort order A-Z, Z-A, or by date.

To manage Explorer categories:

1. Navigate to a category folder of interest.
2. Right-click the category folder. The Category context menu displays.
3. Select an action from the menu. See ["Explorer Options and Context Menus" on the next page](#).

Tip: Report Admins can also work with Categories and Category filters directly, using the Reports Administration tools. See ["Report Categories" on page 289](#) and ["Report Category Filters" on page 301](#).

Explorer Favorites

For quick access to frequently-used items, you can mark any report, query, parameter, dashboard, or dashboard widget as a favorite.



Note: Favorite objects cannot be organized into categories.

To add a Report object as a Favorite:

1. From Explorer, select the report object for which you want easy access.
2. Right-click the object. The action menu displays.
3. Click **Add to Favorites**. A confirmation message displays.

To access an object from your Favorites list:


1. From Explorer, click the Favorites star to the left of the X (close) icon.

| Explorer-Favorites   | | | | |
|--|-------------|-------------|---------------|--------------------|
| Name | Object Type | Report Type | Report Format | Last Modified Date |
| <input type="text" value="Search Here"/> | | | | |

Report objects that you have designated as Favorites display.

2. Select the report object and right-click to open the action menu.
3. Select an action.

To remove an object from your Favorites list:



1. From Explorer, click  to open your Favorites list.
2. Right-click the report object.
3. Select **Delete from Favorites**.

Explorer Options and Context Menus



Explorer is the central location for accessing and maintaining existing reports and report objects. Right-click on a category folder or other report object to open a context menu for that folder or option. Menu options vary with the object type and parameter requirements.

All Explorer objects have these menu options.

All Explorer Objects


| Icon | Menu Option | Description |
|---|---|--|
|  | Add to Favorites Delete from Favorites | Include or remove this object from your Explorer Favorites list. See "Explorer Favorites" on the previous page . |
|  | Copy {object} Paste | Use this option to copy an Explorer object into another Category folder. Right-click a category folder and select Paste to save the copy. |

All Explorer Objects, continued

| Icon | Menu Option | Description |
|---|-----------------------|--|
|  | Cut {object} Paste | Use this option to move an Explorer object into another Category folder. Right-click a category folder and select Paste to move the object. |
|  | Delete {object} | Deletes the Explorer object. Caution: Take care to only delete <i>copies</i> of the default object, not the default object itself. |

Reports generally have these Explorer menu options. For a description of the various run options, see ["Understanding Run Report Options" on page 183](#)

Explorer Reports

| Menu Option | Description |
|---|---|
| Quick Run with Default Options | Run the report using default or last saved preferences. If the report has user parameters, enter them in the Report Parameter tab and select Run Now or Run in Background to run the report. |
| Run in Background | Run the report as a background process, using the default or last saved preferences. If the report has user parameters, enter them in the Report Parameter tab and select Run Now or Run in Background to run the report. |
| Run Report | Run the report after setting new preferences, such as the report format. |
| Run in Smart Format | Generate the report in multipage interactive HTML format. These Smart reports open in a paginated web format, and allow you to customize the grid and interactive charts. |
| List Published Outputs | Displays a list of the published reports for the selected report in a new tab. |
| Customize Report | Opens either the Smart Designer (for Smart reports) or the Ad hoc Report Designer, ready for modifications or saving as a new report. Tip: To customize a report using Powerview designer, run an editable Ad hoc report. |
| Copy Report | Copy the Report file to the clipboard. |
| Copy Report as Link | Add a link to a report object in another directory, similar to a shortcut. |
| Properties | Displays the Properties window for the report. |
|  Download Report | Saves a copy of the report offline, in IBM WebSphere ILOG JRules Rule Language (IRL) format. Note: You must have a suitable application that supports IRL on the offline system to open this kind of file. |
| View Description | Opens a description of the report in an informational window. |
| View Statistics | Opens a pop-up window with the execution statistics of the report. |

Categories have the following Explorer menu options:

Explorer Categories

| Menu Option | Description |
|------------------|--|
| Add New Category | Add a new Category folder to Explorer. |
| Refresh | Refresh the Category contents. |
| Properties | Displays the Properties window for the Category. |

Queries have the following Explorer menu options:

Explorer Queries

| Menu Option | Description |
|---------------------|--|
| Edit Query Details | Opens the selected query in the Query Object Editor for editing. |
| Create Query Object | Opens the Query Object Editor for building a query. |

Parameters have the following Explorer menu options:

Explorer Parameters

| Menu Option | Description |
|------------------------------|--|
| Edit Parameter Details | Opens the selected parameter in the Parameter Object Editor for editing. |
| Create Parameter Object | Opens the Parameter Object Editor for building a query. |
| Create Parameter Value Group | Opens the Parameter Value Group page for creating a new parameter value group. |

Recent Reports

The **Recent Reports** widget lists the last ten reports of currently running, recently run, or accessed reports (removed automatically after 30 minutes or otherwise specified in the property file). By default, all reports display, except scheduled reports.

Caution: When you run reports from this list, reports open in their respective **designer**, not the usual **viewer**. This allows you modify the report, not just export or comment on it. Remember to **Save As** before you modify an original report.


Running a Recent Report

To run a recent report:

1. From the **Home** Reports tab, access the **recent reports** widget.

Re-running a Recent Report

To re-run a recent report:

1. Click the **Recent Reports**  icon to expand the list of recent reports.
2. Click a radio button to select a report. After you select a report, the **Run** and the **Re-Run** buttons display in the top-left corner:
3. Click **Re-Run**. The Report Settings menu opens in the **Data Source** tab.
4. Optionally, select a Template. The default is **Plain**. See ["Working with Logger Report Templates" on page 284](#).
5. Select a report format. The default is **HTML**. See ["Report Formats for Viewing and Export" on page 196](#).
6. Click **View Options** to set appropriate options for the format, such as pagination, zip file, page settings, and so on. See ["View Options" on page 198](#).
7. When you have made your changes, click one of the following actions to generate your report:

| Action | Description |
|--------------------------|--|
| Run | Runs the report, and opens the rendered report in the appropriate viewer. |
| Preview | Displays a short sample of the report, including title and column headings. |
| Run in Background | Schedules the report to run as a background process, and confirms the action in a new tab. |


The report opens in a new tab. From here, you can use the viewer tools to publish, render, comment, and other tasks.


- Reports that are run in Smart Format display in the Smart Viewer. See ["The Smart Report Viewer" on page 193](#).
- Ad hoc reports display in the Ad hoc Viewer. See ["The Ad hoc Report Viewer" on page 191](#).
- Reports that are run in the background open in the Other Reports page, where you can select and open the report. See ["Running Background Reports" on page 185](#).

Published Reports

Once a report has run and been published, you can view, export, or delete them from the **Published Reports** widget on the Recent Reports tab.


To open a published report from the Published Reports widget

1. From the Recent Reports tab, click  to open **Published Reports**. You can also access from the **published reports** widget at reports home tab.

2. Optionally, use the **Filters** menu to filter the results. See ["Working with Published Reports" on page 204](#).
3. Select a published report.
4. Optionally, click  to open the Show Comments window for that report.
5. Select a view icon for the report (See ["View Options" on page 198](#)). The report then renders in the selected view format.
 - Reports that are run in Smart Format display in the Smart Viewer. See ["The Smart Report Viewer" on page 193](#).
 - Ad hoc reports display in the Ad hoc Viewer. See ["The Ad hoc Report Viewer" on page 191](#).

To publish a report, see ["Publishing a Report" on page 202](#)

My Reports



The screenshot shows the 'My Reports' section of the application. At the top, there is a dropdown menu set to 'Published Reports'. Below this, the title 'Published Reports' is displayed on the left, and a 'Filters' icon is on the right. A filter bar shows 'Published Name Includes' with an empty search box. Below the filter bar, a navigation bar shows a '(Root)' button and several folder icons: Cloud, Default Reports, Device Monitoring, Foundation, Logger Administration, OWASP, and SANS Top 5. The main area contains a table with the following columns: Sr.No., File Name, Generated Time, and Expiry Time. The table is currently empty. At the bottom, a pagination bar shows 'No Records Found', a 'Jump to Page' input with the value '1', and a 'GO' button, followed by '(0/0) rows'.

| Sr.No. | File Name | Generated Time | Expiry Time |
|--------|-----------|----------------|-------------|
|--------|-----------|----------------|-------------|



Working with Published Reports

You can render, save, and delete reports from the Published Reports widget, as well as view any comments attached to the report. How the report displays or generates within the widget depends on the file format you select:


- Report formats that can display within a browser display in a new tab.
- Report formats that must be viewed in another application open in a new window, where you can save, export, and upload the report.

If the list of Published Reports is long, you can filter the list by published name, date, source report, and other options.


To view a published report

1. From the Recent Reports tab, click  to open **Published Reports**.
2. Select a published report.
3. From the icon menu, click a view format. See ["View Options" on page 198](#). The report displays in the appropriate viewer. See ["Report Formats for Viewing and Export" on page 196](#).
4. Click **Apply**.
5. Click  in the upper-right to return to the Published Reports list.

To download a published report



1. From the Recent Reports tab, click  to open **Published Reports**.
2. Select a published report.
3. From the icon menu, click a file format such as PDF, CSV, Excel, Word, or Text. See ["View Options" on page 198](#).

A new tab opens and displays a message similar to the following:





4. Click on Open or Save option before closing this window or tab.
5. Enter any necessary information and click **OK**.

To view comments for a published report


1. From the Recent Reports tab, click  to open **Published Reports**.
2. Select a published report.
3. From the icon menu, click . The **Show Comment** window displays any comments made to that report.
4. When you are finished, click **Done**. See ["Adding a Comment to a Report" on page 194](#).

To delete a Published Report



1. From the Recent Reports tab, click  to open **Published Reports**.
2. Select a published report.


3. Click the  icon and confirm your request. The report instance is deleted from the Published Reports list.

To filter the Published Reports list

1. From the Recent Reports tab, click  to open **Published Reports**.
2. Click **Filter** to open the filter menu.
3. Enter your filter criteria.

Note: Access to these filter criteria depends upon your Logger Reports access rights policy, your role, and your individual access rights. Other permissions may be necessary. See ["Assigning Access Rights" on page 164](#).

| Filter Criteria | Description |
|-------------------------|--|
| Published Name Includes | Enter a text string with some or all of the published report name. |
| Updated Between | Enter a date range to restrict the update time for report results. Enter a date manually in MM/dd/yyyy format, or click  to open a calendar date picker. |
| Select Report | Click the  icon to open the Object Selector window. Select a report or a folder. |
| Select Owner | Select from among the report owners for which you have access rights. |
| Private Owned By | Select from among the private reports for which you have access rights. |
| Public Owned By | Select a public report owner from the list for which you have access rights. |

4. Optionally, click  (**Root**) to open the category filter, and navigate to the published report you want to find.
5. Click **Apply**. The filtered list displays.

Other Reports

The **Other Reports** dynamic list displays, by default, information about all reports except for Published Reports. You can filter this list to be as wide or as granular as you desire. See ["Filtering the Other Reports List" on the next page](#).

Other reports guidelines:

- Reports run manually (Execution Type: **Run**) expire after an hour in this list.
- Background and Scheduled reports do not automatically expire.


- Completion date as well as execution time allow the user to review the time used for that particular report.

To view or download a report on the Other Reports list

1. Select a report to see the options for viewing, or downloading the report for viewing elsewhere. See ["View Options" on page 198](#).

Tip: Only Smart reports include iHTML and Smart report options.

To delete background reports



1. Select a report with an execution type of **Run in Background**.
2. Click  to the right of that report. Confirm the deletion.

Tip: Only background reports can be deleted from this list.



Filtering the Other Reports List

If you are looking for a particular report object, or a particular instance of that object that was run in the background, use the Filters menu to locate it.

To Filter Other Reports

1. From the Report Status tab, click  to open **Other Reports**.
2. From Other Reports widget, click  to open the **Filters** menu.

3. Enter any of the following optional filter criteria:

| Filter Criteria | Description |
|------------------|---|
| Select Report(s) | Click  to open the Object Selector window. Select a report or a folder. |
| Execution Type | Filter by run type: <ul style="list-style-type: none">• All—Display all run types• Run—Display reports run directly from a report list• Schedule—Display scheduled reports• Run in Background—Display background run reports |
| Status | Filter by run status: <ul style="list-style-type: none">• Running—Display reports that are still being executed• Completed—Display reports that have finished generating |
| Select Owner | Select an individual user, or leave the default as "All Users" or "Admin" |
| Date From and To | Enter a date range to display all reports run within that time. Enter a date manually in MM/dd/yyyy format, or click  to open a calendar date picker. |




4. Click **Apply**. The filtered list displays.

Scheduled Reports

You can schedule a report to run as a scheduled job, either on a one-time basis, or at regular intervals. As part of scheduling a report job, you can set delivery options to publish and/or email the resulting reports.

Micro Focus recommends that you schedule your reports whenever possible, so that reports that take more than an hour to generate will not time out, and will run during periods of light load.

Note: If not completed, by default, a scheduled report times out in 4 hours.

| Scheduled Reports | | | | | |
|-------------------|--------|---------------|-----------------------------|---|---|
| Add | | | | | |
| Task | Type | Schedule | Next Run Time | | |
| Test | Report | Daily at 8:00 | Mar 22, 2018 8:00:00 AM PDT |  |   |

Prerequisite


To schedule reports, a user must belong to a Logger Reports Group, a Logger Search Group, and a Logger Rights Group. See ["Users/Groups" on page 495](#).

Scheduling a Report

You can schedule a report to run daily at a specified time or every so many hours, or on specified days of week or month, at a specified time.


Tip: Time changes due at the beginning or end of Daylight Savings Time may affect your scheduled reports. For more information, see ["Impact of Daylight Savings Time Change on Logger Operations" on page 464](#).

To configure a scheduled report:

1. Click **Schedule Reports** from the Reports menu. The Schedule Reports page opens in a tab.
 - a. If there are scheduled reports you have privileges to view, they are listed. Your reports include options to edit or delete them.
 - b. If there are no scheduled reports, you see "There are no report jobs to display."
2. Click **Add** to display the Add Report Job page.
3. In the **Name** field, enter the report display name.
4. Select the **search type:** event occurred or receipt time.
5. Use the **Schedule** options to specify how frequently the report should run:
 - **Every day**—Run a daily report at a specified time, or every specified number of hours.
 - **Days of week**—Run the report on a specified day of the week. For example: **Su, M, T, W, Th, F, Sa**.
 - **Days of month**—Run the report on a specified day of the month. For example: **1,5,20,21**.
 - **Hour of day**—Run the report at a specific time of day. For example: **0300**.
 - **Every**—Run the report every specified number of hours or minutes. For example, **90 minutes**.
6. Select a report from the **Report Name** pull-down menu, then click  to load the report.
7. In the **Delivery Operations** section, configure one or both of the following options:
 - **Publish**—(Selected by default) Publish the report at the scheduled time. For details on setting publishing options, see ["Publish Report Options" on page 203](#)
 - **Email**—Send the report as a link or an email attachment at the scheduled time. For details on setting email delivery options, see ["Email Delivery Settings" on page 210](#).
 - **Upload** — Upload the report to FTP or a Shared Folder . For details on how to send reports via FTP, see ["Uploading a Report to a Server or FTP Site" on page 207](#)

Tip: It isn't necessary to save the report before moving from one tab to another. Just remember to save the report before closing the page.

8. In the **Report Format** section, select a report format and delivery options.




Report Format ACROBAT PDF ☒ Smart Export

Delivery Options

General Page Settings

Pagination: Horizontal Breaks ☒ Deliver Zipped File

When choosing the report format for scheduled reports with several columns, change the paper size to Auto.




Report Format ACROBAT PDF ☒ Smart Export

Delivery Options

General Page Settings

Page

Orientation: ☒ Potrait ☐ Landscape 

Paper Size: Auto

Height: 11"

- Select a report format. See ["Report Formats for Viewing and Export" on page 196](#)
 - Select a delivery option. See ["Export Options" on page 200](#)
 - If you want an Excel, Word, or PDF file to be available in its native format, click **Smart Export**. See ["What is Smart Export?" below](#).
9. In the **Report Parameters** section, you can either accept the default parameters, or modify them here. For information on specifying report parameters, see ["Parameters" on page 273](#).
10. Click **Save**.

The report you added is scheduled, and now shows on the **Scheduled Reports** list.

What is Smart Export?

The Smart Export option is available for Scheduled Reports using MS Excel, Acrobat PDF, and MS Word formats. Reports are exported into their native formats, so that users can leverage the functionality of their respective tools. See ["Report Formats for Viewing and Export" on page 196](#)

- The grid information is exported as its equivalent table in Excel, Word and PDF.
- The matrix is exported as a Pivot table in Excel and as a table in Word and PDF.
- Report charts are exported as a chart in Excel, Word, and as an image in PDF.

Smart Export is enabled by default for scheduled reports in these three formats.

To enable Smart Export for a report:


1. From the Scheduled Reports page, edit an existing scheduled report, or click **Add** to start a new scheduled report. See ["Scheduling a Report" on page 178](#).
2. From the Report Format section, select either MS Excel, Acrobat PDF, or MS Word. The **Smart Export** checkbox becomes available.
 - **Checked** (default) — The report will be exported as a native file for its supported program.
 - **Unchecked** — The report will be a normal export, with charts exported as images.
3. Make sure all other information and changes have been made to the report.
4. Click **Save**.

Working with Scheduled Reports

Reports that are already scheduled are displayed on the Scheduled Reports page. You can enable or disable, edit, or delete scheduled reports from this page.

Note: Scheduled reports are enabled by default when they are created.



To edit a scheduled report:



1. Click **Schedule Reports** from the Reports menu.
2. Click  next to the scheduled report job you want to edit, or click on the report.
3. On the **Edit Job Report** page, modify the settings as needed.
See ["Scheduling a Report" on page 178](#) for details.

Note: The job name is not editable.


4. Click **Save**. Logger redirects you to the Scheduled Reports page.

To enable or disable a scheduled report:

1. Click **Schedule Reports** from the Reports menu.
2. **Disable**—Click the  to the right of the scheduled report job. The icon changes to , and the Next Run Time for the report displays **Disabled**

3. **Enable**—Click the  to the right of the scheduled report job. The icon changes to , and the Next Run Time displays.

To delete a scheduled report:

1. Click **Schedule Reports** from the Reports menu.
2. Click  to the right of the scheduled report job you want to remove.
3. Confirm the deletion.

Tip: Removing the report from Scheduled Reports list deletes the *scheduled job*, not the report itself nor any instances of its previously published output.

Scheduling Report Limitations

Micro Focus recommends that you schedule your reports whenever possible, so that reports that take more than an hour to generate will not time out, and will run during periods of light load.

Please see the following list of scheduling limitations and review the maximum amount of data handled based on report output format.

| Report Type | No. of Rows | No. of Columns | Report output Format | Approx. time taken to export | Export Options | File Size |
|---|-------------|----------------|----------------------|------------------------------|------------------------------|---|
| Smart Report(Created using RDBMS logger connection) | 1 million | 45 | MS-Excel | 28 mins 42 secs | Zipped=Yes | Zip file size = 96 MB Extracted File size=186MB |
| Smart Report(Created using RDBMS logger connection) | 3 million | 45 | Fast CSV (RAW Text) | 16 mins 42 secs | Zipped=Yes | Zip file size = 9.6 MB Extracted File size=1.07GB |
| Smart Report(Created using RDBMS logger connection) | 1.5 million | 45 | CSV | 55 mins 28 secs | Zipped=Yes | Zip file size = 48 MB Extracted File size=520MB |
| Smart Report(Created using RDBMS logger connection) | 100000 | 66 | Word | 19 min 19 secs | Zipped=Yes | Zip file size = 5.45 MB Extracted File size=26.5MB |
| Smart Report(Created using RDBMS logger connection) | 1.2 million | 45 | PDF | 47 mins 49 secs | Zipped=Yes Page width=34" | Zip file size = 33.5MB Extracted File size=986MB |

| Report Type | No. of Rows | No. of Columns | Report output Format | Approx. time taken to export | Export Options | File Size |
|---|-------------|----------------|----------------------|------------------------------|------------------------------|---|
| Smart Report(Created using RDBMS logger connection) | 1 million | 45 | TEXT | 52 mins 8 secs | Zipped=Yes | Zip file size =291MB Extracted File size=13.6GB |
| Smart Report(Created using RDBMS logger connection) | 4000 | 45 | XML | 52 mins 36 secs | Zipped=Yes | Zip file size =148KB Extracted File size=12MB |
| Smart Report (Logger Search Queries) | 1 million | 45 | MS-Excel | 13 mins | Zipped=Yes | Zip file size = 117MB Extracted File size=193MB |
| Smart Report (Logger Search Queries) | 1 million | 45 | Fast CSV (RAW Text) | 2 mins 54 secs | Zipped=Yes | Zip file size = 4.10MB Extracted File size=478MB |
| Smart Report (Logger Search Queries) | 1 million | 45 | CSV | 56 mins 46 secs | Zipped=Yes | Zip file size = 3.89MB Extracted File size=435MB |
| Smart Report (Logger Search Queries) | 100000 | 63 | Word | 15 mins 30 secs | Zipped=Yes Page width=24" | Zip file=10.2MB Extracted File size=25.4MB |
| Smart Report (Logger Search Queries) | 1 million | 58 | PDF | 31 mins 40 secs | Zipped=Yes | Zip file size =264MB Extracted File size=1.07GB |
| Smart Report (Logger Search Queries) | 1 million | 58 | TEXT | 58 mins 26 secs | Zipped=Yes | Zip file size = 319MB Extracted File size=18GB |
| Smart Report (Logger Search Queries) | 4000 | 58 | XML | 57 mins 36 secs | Zipped=Yes | Zip file size = 304KB Extracted File size=12.4MB |

Running Reports

You can run Logger reports from many locations, and choose the run option that works best for that report.

Tip: You can also run reports as part of the design process. This section deals with run-ready reports.

Understanding Run Report Options

The following table describes the available report run options. The viewer or list in which the report displays depends upon the report format and run action you choose.

Tip: Editable Ad hoc reports display by default in the Powerview designer. Smart reports display in the Smart designer.

Logger Report Run Options

| Action | Available From | Description |
|---------------------------------------|-------------------------------|--|
| Quick Run with Default Options | Explorer | Runs the report with the data filters specified in the report. You can add or modify the run-time parameters for time frame and constraints, such as Device Groups, Storage Groups, Devices, and Peers. See "Run-Time Filters, Criteria, and Parameters" on page 187 . |
| Run in Background | Explorer Report Parameters | Runs the report as a background process. You can view, export, or delete background reports from the Other Reports list on the Reports home page. See "Running Background Reports" on page 185 , and "Other Reports" on page 175 . |
| Run Report | Explorer | Runs the report using the last saved parameters. You can add or modify the run-time parameters, if necessary. See "Select Filter Criteria" on page 189 . |
| Run in Smart Format | Explorer | This option creates a Smart report from an Ad hoc parent report. Once a report is run in Smart format, it becomes a Smart report, opening by default in the Smart viewer and Smart designer tools. Published Smart reports can also be used as Smart Dashboard widgets. See "What is Smart Export?" on page 179 . |
| Run | Recent Reports | Runs the report using the last saved parameters. You can add or modify the run-time parameters, if necessary. See "Recent Reports" on page 171 . |
| Re-run | Recent Reports | Allows you to save new report parameters, view options, and filter criteria before running the report. Re-run opens the Report Parameters tab with values provided during the previous run, which you can continue using, or replace. Re-run also gives you options to preview the report, or run it as a background process. See "Recent Reports" on page 171 . |

Logger Report Run Options, continued

| Action | Available From | Description |
|---------------------|-------------------|---|
| Preview | Report Parameters | Displays a short sample of the report, including title and column headings. You can add or modify the run-time parameters, if necessary. See "Run-Time Filters, Criteria, and Parameters" on page 187 . |
| Run Now | Report Parameters | Runs the report immediately and displays in the appropriate viewer. See "Run-Time Filters, Criteria, and Parameters" on page 187 . |
| Refresh Data | Smart Viewer | Runs the report with existing filters and options. |

Best Practices for Running Reports

Logger is designed to process events while running reports, but event processing has priority. Running a complex report while the event processing system is under load will result in report timeout rather than dropped events.

To effectively manage demands for system resources, Micro Focus recommends using Scheduled Reports, so that reports run during periods of light load. If an ad hoc report must be run, run it when the system is not under load. See ["Scheduling a Report" on page 178](#).

Another option is to restrict large reports to run only in the background. See ["Restrict Long Reports to Run in the Background" on page 186](#).

If you are running a distributed report, also see the best practices discussed in ["Selecting Groups, Devices, and Peers" on page 190](#).

Smart Reports support up to 20k rows, for larger reports, see ["Restrict Long Reports to Run in the Background" on page 186](#).

Logger reports based on filters or saved searches should not include **Wildcards** in the fieldsets.

Running a Report

There are many ways and places to run reports, but Explorer will likely provide you the most selection of options. For full information, See ["Reports Explorer" on page 165](#).

To run a report from Explorer:

1. Click **Explorer** from the Reports menu.
2. Select a report. See ["Reports Explorer" on page 165](#).
3. Right-click the report. The action menu displays for that report. See ["Explorer Options and Context Menus" on page 169](#).
4. Select a run option for that report. See ["Understanding Run Report Options" on the previous page](#).

5. Enter any run-time filter or parameter criteria. See ["Run-Time Filters, Criteria, and Parameters" on page 187](#).
6. Click **Run**, **Run in Background**, or **Preview**. Logger then runs the report, and opens the report in the appropriate designer, where you can customize the report and create and edit charts to display the data. See ["Designing Custom Reports" on page 211](#).

Running, Viewing, and Publishing Reports

Reports are available under their respective categories. For more information about report categories, see ["Reports Explorer" on page 165](#).

You can run, view, and publish reports you create, as well as reports in categories for which the administrator has given you user access rights. You can run up to 5 Ad Hoc reports or up to 10 scheduled reports, concurrently.

Note: When scheduling reports, consider recurrence to avoid overlapping executions.

Running Background Reports

You can run a background report in **Report Status >Other Reports**.

Report Parameters

Device Type : All

Other Reports

Your request has been submitted.

Filters


Category Name [./CrossDevice] | Report Name [Login Event Audit] | Execution Type [(All)] | Status [(All)] | User [(All Organizations)/(All Users)]

| Sr.No. | Report Name | Action | Execution Type | Completion Status | Completion Date | |
|--------|---|--------|-------------------|-------------------|---------------------|-------------|
| 1 | <div><div></div>CrossDevice/Login Event Audit</div> | VIEW | Run in Background | Success | 03/02/2017 11:39:58 | <div></div> |

To run a background report from Explorer


1. From Explorer, navigate to a report you want to run.
2. Right-click the report name, and select **Run in Background**.
3. Configure any additional filters or report parameters.
4. Click **Run in Background**.

To run a background report from a filter or parameter page

1. From Recent Reports, select a report you want to run.
2. Click  to re-run the report.


3. Configure any additional filters or report parameters.
4. Click **Run in Background**.

To delete a background report

1. Click **Other Reports** on the Recent Reports tab. The Other Reports list displays.
2. Click the  to the right of the background report you want to delete.
3. Confirm the deletion.

Restrict Long Reports to Run in the Background

Admins can restrict long-running reports, so they can only run in the background.



The screenshot shows the 'Properties' window for the report 'Errors Detected in Anti-Virus Deployment'. The 'Look In' field shows the path '.../Anti-Virus'. The report is listed in a table with a red 'X' icon. The 'Properties' section includes fields for 'Report File', 'Report Name', 'Report ID', 'Description', 'Design Mode', 'Deployment Type', and 'Output Format'. The 'Advanced' tab is selected, showing the 'Restrict To Background' menu set to 'Enable'.

Look In: .../Anti-Virus

Refresh Show All Owners'

Errors Detected in Anti-Virus Deployment

Failed Anti-Virus Updates

Top Infected Systems

Update Summary

Virus Activity by Hour

Save Cancel

Properties

Report File: Browse

Report Name: Errors Detected in Anti-Virus Deployment

Report ID: 56EDA24C-82FE-6F73-BF83-27FCDFC27A97

Description: This report shows a summary of information on the anti-virus errors, including the Anti-Virus product information, host details, error information, and the number of errors.

Design Mode: ADHOC

Deployment Type: Custom

Default

Output Format: HTML

To restrict a report to run only in the background

1. Click **Report Categories** from the Administration section of the Reports menu.
2. Select the report you want to restrict.
3. From the Properties section, click **Advanced**. The report Advanced Properties menu displays.
4. From the Restrict To Background menu, click **Enable**.
5. Click **Set**. This closes the menu.
6. From the Manage Folders and Reports page, click **Save**.

Running Distributed Reports


A distributed report includes matching events from the specified peers of a Logger. You select the peers on which the report should run in the Peers list. If no peers are configured, the Peers list contains only the localhost IP address (127.0.0.1). However, if peers are configured, their IP addresses are listed.

Prerequisite

To run a distributed report, you must have configured one or more Peer devices.

To run a distributed report

1. From the Additional Filters menu, uncheck **Local Only**.
2. Select the Peers you want to include in your search from the Peers list.



Use ctrl-click to select or deselect items

3. Run the report.

Run-Time Filters, Criteria, and Parameters

Most reports give you the option to set appropriate run-time filters, select device and other search criteria, and parameters. This section explains how to use these customization tools to display the data you want as you want it.

You can define filters, or modify default filters if any are already built into the report. The filter expression is applied when the report runs, narrowing the focus of the report to the specified criteria.

For example, you could set the filter criteria for a report on Top Password Changes to report only on password changes related to specified user names or involving specified IP addresses. For details on how to create these filters (with Field, Criteria, and Value fields), see ["Filter" on page 230](#).

If you run the report without specifying any override run-time parameters here, the report is generated with the defaults specified at design time for this report. You can run a report in the background after specifying the Run Report parameters.

Note: Filter criteria defined at report run time applies only to this run of the report. Filters set in this way are not saved nor made available to other users. You can also set built-in, default filter criteria as a part of designing a report.

Additional Filters

When you run a report, you have the option to select additional run-time filters on time frame and constraints, such as Device Groups, Storage Groups, Devices, and Peers. If nothing is selected, all groups and devices are included.

Note: Peers are not included by default. They must be explicitly selected to include them. See ["Running Distributed Reports" on the previous page](#).

Additional Filters Report Parameters

| Option | Description |
|-------------------|--|
| Device Type | Some reports allow you to select which device types to include in the report. |
| Start | <p>Specify the starting point for the data gathering from the events database.</p> <p>By default, the start time is specified with a dynamic data expression (\$Now - 2h).</p> <p>You can modify the dynamic expression to specify a different dynamic start time, or disable Dynamic and use the calendar options to specify a fixed start time.</p> |
| End | <p>Specify the ending point for the data gathering that is some time after the starting point.</p> <p>Keep in mind that large time spans can mean large amounts of data, which can affect system performance.</p> <p>By default, the end time is specified with a dynamic data expression (\$Now).</p> <p>You can modify the dynamic expression to specify a different dynamic end time, or disable Dynamic and use the calendar options to specify a fixed end time.</p> |
| Search Time Field | Select the search time type: Logger Receipt Time or End Time (Event time). |
| Scan Limit | <p>Specify the number of events to scan.</p> <p>When you specify a scan limit, the number of events scanned for manually run reports is restricted to the specified limit. Doing so results in faster report generation and is beneficial in situations when you only want to process the latest N number of events in the specified time range instead of all the events stored in Logger.</p> <p>The scan limit is 100,000 by default. If you set the scan limit to 0 (zero), all events are scanned.</p> <p>Note: This setting does not apply to Scheduled reports.</p> |
| Device Groups | Select specific device groups on which to run the report query, if any. See "Selecting Groups, Devices, and Peers" on page 190 . |
| Storage Groups | Select specific storage groups on which to run the report query. See "Selecting Groups, Devices, and Peers" on page 190 . |
| Devices | Select specific devices on which to run the report query. See "Selecting Groups, Devices, and Peers" on page 190 . |

Additional Filters Report Parameters, continued


| Option | Description |
|--------|---|
| Peers | Select any peer Loggers (if peers are configured) on which to run the report query. See "Selecting Groups, Devices, and Peers" on the next page . |

Data Source Report Settings

When you choose the **Run Report** option for a report, you can choose a file format, specify pagination, and modify the data filter criteria for this run of the report. If you run the report without specifying any override run-time parameters here, the report is generated with the defaults specified at design time for this report.

The following table describes the **Report Settings** options.

Data Source Report Settings

| Option | Description |
|---|---|
| Template | Select the template to apply to this report. The templates pull-down menu shows supplied templates, and any custom templates you may have added. To include the start time, end time, scan limit, device group, storage group, and devices information (used to run a report) in a report, choose the BlankWithHeader template. See "Template Styles" on page 284 . |
| Report Format | Specify a file type or "format" option of the output. See "Report Formats for Viewing and Export" on page 196 . |
| View Options | Select from the available options for that report. See "View Options" on page 198 |
|  Filter tab | <p>Optional, Define filters or modify existing default filters, if any. See "Select Filter Criteria" below</p> <p>The filter expression is applied when the report runs, narrowing the focus of the report to the specified criteria.</p> <p>For example, for the report "Top Password Changes," you could set the filter criteria to display only password changes related to specified user names or specified IP addresses.</p> <p>For details on how to create these filters (with Field, Criteria, and Value fields), See "Filter" on page 230.</p> <div style="background-color: #f0f0f0; padding: 10px; margin-top: 10px;"> <p>Note: Filter criteria defined at report run time applies only to this run of the report. Filters set in this way are not saved nor made available to other users. You can also set built-in, default filter criteria as a part of designing a report.</p> </div> |

Select Filter Criteria

When you choose the **Run Report** link for a report, filter options are available to modify the data filter criteria for only this run of the report. You can define filters, or modify default filters if any are already built into the report. The filter expression is applied when the report runs, narrowing the focus of the report to the specified criteria.

For example, you could set the filter criteria for a report on Top Password Changes to report only on password changes related to specified user names or involving specified IP addresses. For details on how to

create these filters (with Field, Criteria, and Value fields), see ["Filter" on page 230](#).

If you run the report without specifying any override run-time parameters here, the report is generated with the defaults specified at design time for this report. You can run a report in the background after specifying the Run Report parameters.

Note: Filter criteria defined at report run time applies only to this run of the report. Filters set in this way are not saved nor made available to other users. You can also set built-in, default filter criteria as a part of designing a report.

Selecting Groups, Devices, and Peers

You can select which data sources within Device Groups, Storage Groups, Devices, or Peers to include in your report, as a part of setting the Additional Filters settings.

By default, events from all groups and devices are included, because nothing is selected. Select specific groups or devices to limit the data gathering to only those sources when the report is run.

Note: Peers must be explicitly selected to run a report query on them. If none of the peers are selected, the query will only run on the local Logger.

The selected items in the Device Groups, the Devices lists, and Peers are appended to the report query with an OR operator. They are appended to other selected items, such as Storage Groups, with an AND operator.

To select specific data sources:

1. Click an item to select it.
2. Use Ctrl-click to select or deselect multiple items.

To select all available data sources:

1. Deselect any selected data sources.

Viewing Reports

Once a report is run and in the Smart or Ad hoc Viewer, you can publish it for further use, add comments, email, upload, or export it in different output formats.


The options you have in the report viewer are limited to attaching comments and sending the report out somewhere. To modify and customize your report, see ["Designing Custom Reports" on page 211](#).

For information about modifying report results, such as adding logos, charts, and changing the display options, see [Creating a New Smart Report](#).

- [The Ad hoc Report Viewer](#)191
- [The Smart Report Viewer](#)193
- [Collaborating on Reports](#)194
- [Searching for IPv6 Addresses in Reports](#)195
- [Report Formats for Viewing and Export](#)196

The Ad hoc Report Viewer









When you view an Ad hoc HTML report (from Explorer, the Published Reports list, or the Other Reports list, for example), it displays in the Ad hoc Report viewer, where you can view the report, export it in different output formats, and other tasks, but you cannot modify the report attributes.







Tip: The Ad hoc Report viewer looks very much like the Powerview designer. The viewer does not display the Powerview designer icon  on the right side of the menu bar. To modify report attributes, see ["The Powerview Designer" on page 219](#), or ["Classic: The Ad hoc Report Designer" on page 224](#).

Ad hoc Viewer Menu Options

After running an ad hoc report, the following options are available from the Ad hoc Viewer menu bar.



| Icon | Description |
|---|---|
|  | Add a table of contents to a grouped report. See "Displaying a Table of Contents for a Grouped Report" on the next page . |
|  | View as Excel Spreadsheet. See "View Options" on page 198 . |
|  | View as PDF. See "View Options" on page 198 . |
|  | View as CSV file. See "View Options" on page 198 . |
|  | View as text file. See "View Options" on page 198 . |
|  | View as Microsoft Word document. See "View Options" on page 198 . |
|  | Export report. See "Exporting and Saving a Report" on page 206 . |
|  | Email report. See "Emailing a Report" on page 209 . |

| Icon | Description |
|---|--|
|  | Upload report to a server or an FTP site. See "Uploading a Report to a Server or FTP Site" on page 207 . |
|  | Report navigation tools. Click to page through the report, go to first or last page, or enter a page number. |
|  | Add comment. See "Adding a Comment to a Report" on page 194 . |
|  | View comments. See "Adding a Comment to a Report" on page 194 . |
|  | Refresh comments. Refresh the View Comments window. |
|  | Publish Report. See "Publishing Reports" on page 202 |

Displaying a Table of Contents for a Grouped Report


When information on the report is grouped (for example, by country, product, or department), you can display a table of contents (ToC) to help you investigate your data.

Reports can be grouped and ungrouped by column in the Powerview designer and Ad hoc Viewer. For more advanced grouping options, use the Ad hoc Report Designer **Group** tab. See ["Group" on page 232](#).

Note: The table of contents is for *viewing* grouped ad hoc reports. The ToC cannot be saved or exported as part of the report.

To display a table of contents for a grouped ad hoc report in Powerview:

1. Run an editable ad hoc report from Explorer, so it displays in the Powerview designer. See ["Working with Explorer" on page 166](#).
2. Open the Powerview data context menu and select the column name from the **Group** menu. See ["The Powerview Data Context Menu" on page 221](#).



3. To apply this change immediately, click **Apply** in the Actionboard, or wait until you have made all the changes you want to make.

4. Click the ToC icon () in the menu bar. The ToC displays.

| Table of Contents | |
|-------------------|--------------------------------|
| [-] | Most Common Events by S |
| [-] | CPU Usage |
| [-] | Disk bytes read |
| [-] | Disk bytes written |
| [-] | Individual Receiver EPS |
| [-] | Network Usage - Inbound |
| [-] | Network Usage - Outbound |
| [-] | Number of Apache Connec |
| [-] | Number of Searches Perfo |
| [-] | Overall Forwarder EPS |
| [-] | Overall Receiver EPS |
| [-] | Platform Memory Usage |
| [-] | Storage Group Space Usec |
| [-] | Successful login |

Most Common Events by Severity

Group By: Name: Ascending

Start Time: 05/23/17 11:21 PM

End Time: 05/24/17

Scan Limit: 100000

| | Count |
|---------------------------|-------|
| CPU Usage | |
| | 788 |
| Disk bytes read | |
| | 716 |
| Disk bytes written | |



5. To close the ToC, click the icon again, or click the **x**. To reverse the grouping, right-click the data again and select **Remove Grouping**

The Smart Report Viewer

In Explorer, when you select **Run in Smart Format** for an Ad hoc report, it displays in the Smart Report viewer, where you can where you can view the report, export it in different output formats, and other tasks, but you cannot modify the report attributes.

Tip: The Smart Report viewer can look similar to the Smart Report designer. The viewer does not display the Edit switch to the right of the Ad hoc Filters. To modify Smart report attributes, see ["The Smart Report Designer" on page 215](#).

If a Smart report includes a chart or other visualization, you can select a tab in the lower-left to see the various elements. The Smart Report viewer includes these menu or activity areas.

| Area | Options |
|---|---|
| Show/hide column menu | Right-click a column header to open a list of available columns. Select columns to display or hide. Note: Columns named globalEventId and eventId are aligned to the right. |
|  Adhoc Filters | Click to open an the Ad hoc Filters menu. See "Select Filter Criteria" on page 189 . |
|  Viewer menu | Click to open the menu. Select an option to refresh, export, publish, email, or upload the report. See "Smart Viewer Menu Options" on the next page . |
| View tabs | Toggle tabs between grid, charts, and other visualizations. |
| Page navigation | Click to page through the report, go to first or last page, or enter a page number. |

See also

- ["Smart Reports" on page 217](#)
- ["Creating a New Smart Report" on page 218](#)
- ["The Smart Report Designer" on page 215](#)
- ["Create a New Report from an Existing One" on page 213](#)
- ["Working with Logger Report Designers" on page 212](#)
- ["How do Smart Reports differ from Ad hoc and Studio Reports?" on page 160](#)

Smart Viewer Menu Options

The Smart Report Viewer provides the following options and actions.

| Menu Option | Description |
|---------------------|---|
| Refresh Data | Runs the report with existing filters and options. See "Understanding Run Report Options" on page 183 . |
| Export... | Opens the Export Options pop-up. See "Exporting and Saving a Report" on page 206 . |
| Publish... | Opens the Publish Report menu. See "Publishing a Report" on page 202 . |
| Email... | Opens the Email Report menu. See "Emailing a Report" on page 209 . |
| Upload... | Opens the Upload Options menu. See "Uploading a Report to a Server or FTP Site" on page 207 . |

Collaborating on Reports

Logger users can collaborate on a Published report by opening the report in HTML format to view and comment on it. Optionally, you can specify the users who can view the comments.




Tip: You must have Run and Publish access rights to a report to add comments.

Adding a Comment to a Report

You can view and add comments to a published report from any generated report page, including the report preview visible from Published Reports. You can also select which users can see a comment.

Note: For security reasons, comments cannot be deleted once added to a report.

To add a comment to a report:

1. From a report view, do one of the following:
 - From the  Ad hoc power viewer, click  from the toolbar.
 - From the Smart report viewer, select Publish... from the  Options menu.

The Publish menu dialog opens.

2. Click **Add Comment**. The Add Comment window opens.
3. Enter your comment in the text field.
4. Optionally, click the **Visible to:** drop-down menu to authorize specific users to view this comment, or leave the default access as **Everyone**. See ["Assigning Access Rights" on page 164](#). Click **Set**.
5. Click **Add Comment**. Your comment is saved with that report.
6. Click **Publish** to make your comment available to other report viewers.

Searching for IPv6 Addresses in Reports

You can use AdHoc filters to search fields that contain IPv6 addresses. To have these fields available in the AdHoc filters, you must build a query object that include the fields. You can then include the query in a report. To build this query, see ["Creating an IPv6 Search Query for Reports" on page 252](#).

The following fields can contain IPv6 addresses:

- deviceAddress
- agentAddress
- sourceAddress
- destinationAddress

IPv6 Address Format

If you use IPv6 addresses in your query object, the addresses **must** be in canonical format for the Logger to return results, for example:

```
SELECT from arc_deviceAddress, arc_agentAddress, arc_sourceAddress, arc_
destinationAddress

FROM events

WHERE arc_destinationAddress = "3ffe:b00::1:0:0:a"
```

(Valid alphanumeric characters are **0-9** and **a-f**. Upper case characters, such as A-F, are **not** valid)

The query above will not return any results if you use the non-canonical format, such as **3FFE:B00:0000:0000:0001:0:0:000A**.

For more information, see ["Creating an IPv6 Search Query for Reports" on page 252](#). For information on canonical format, refer to <https://tools.ietf.org/html/rfc5952>, section 4: A Recommendation for IPv6 Text Representation.










Report Formats for Viewing and Export

Every report includes a default viewing format. However, you can view or export in a number of popular formats. When you view a report, template and other formatting settings are available. Nevertheless, the template setting option is not longer available for the following formats: Comma separated, Fast CSV, Text, and Smart.

For a description of the view options available for each report, see ["View Options" on page 198](#). For a description of the export options available for each report, see ["Export Options" on page 200](#).

The following table lists the supported report formats. Not all reports support all options.

Report Rendering Formats

| Icon | Format | Description |
|---|-----------------|---|
|  | HTML | HyperText Markup Language, the default format for web viewing. These reports open in the HTML Report Viewer with navigation options. |
|  | PDF | Adobe's Page Description Format, a very portable print format, but not readily editable. These reports open in a PDF viewer. |
|  | MS EXCEL | Microsoft Excel XLS format. These spreadsheet reports can be opened and edited in MS Excel, and have customizable options, including Excel XLS templates, grids, and charts. |
|  | COMMA SEPARATED | Formatted comma-separated values (CSV). Template setting option is not available in this format. |
|  | FAST CSV | Template setting option is not available in this format. Downloads a CSV file, without template, grid, or chart. If you want to focus on the data, and don't need the formatting, this is the fastest option for very large reports. |
|  | TEXT | ASCII text format. Template setting option is not available in this format. |
|  | MS WORD | Microsoft Word DOC format. These reports can be opened and edited in MS Word. |
|  | iHTML | Single-page interactive HTML. These are fast-running Smart reports with a simple, non-paginated template, for fast web display of short reports. Smart reports are designed to quickly render reports when you want to see the data with minimum processing. Template setting option is not available in this format. |
|  | Smart | Multipage interactive HTML. These are fast-running reports with a simple, paginated template, for fast web display of longer reports. Smart reports are designed to quickly render reports when you want to see the data with minimum processing. Template setting option is not available in this format. |

Tip: The report formats available to you depend on the access rights associated with your user account. See ["Assigning Access Rights" on page 164](#).

About Report Pagination

If a report contains more columns than can be displayed horizontally using the default width specified in the report query, the report is paginated horizontally, such that additional columns are displayed on the following pages.

For example, if a report contains 45 columns and only 5 can be displayed at once, the report would be paginated such that Page 1 displays columns 1 through 5, Page 2 displays columns 6 through 10, and so on. Consequently, if the report contained more rows than can be displayed vertically, the second group of rows would be displayed starting at Page 10.

Logger currently limits the number of pages for horizontal pagination to ten. As a result, if a report requires more than ten pages to display all columns, complete report results may not display. To view all columns, adjust the columns manually in the Query Object Editor to fit on ten pages or less. See ["Working with Queries" on page 251](#).

Single-page reports are displayed within a scrolling window, as shown in the following example.

Most Common Events

02/16/2017 11:31 AM

Start Time:Thu Feb 16 09:28:34 PST 2017 End Time:Thu Feb 16 11:28:34 PST 2017
Scan Limit:100000

| Event Name | Count |
|-------------------------------------|----------------------|
| <input type="text"/> | <input type="text"/> |
| <u>Individual Receiver EPS</u> | <u>2242</u> |
| <u>Disk bytes read</u> | <u>118</u> |
| <u>Disk bytes written</u> | <u>118</u> |
| <u>Network Usage - Inbound</u> | <u>118</u> |
| <u>Network Usage - Outbound</u> | <u>118</u> |
| <u>Number of Searches Performed</u> | <u>118</u> |
| <u>Overall Forwarder EPS</u> | <u>118</u> |
| <u>Overall Receiver EPS</u> | <u>118</u> |
| 18 rows | |

Page 1 of 1

Tip: Use this option for short reports. For long reports, the full results may not be visible, or may be missing. Use the multiple page option for these reports.

View Options






When you select a report format, click **View Options** to see and specify relevant settings. Optionally, some formats allow you to apply a display template to the report. See ["Template Styles" on page 284](#). However, this option is not longer available for the following formats: Comma separated, Fast CSV, Text, and Smart.

List view format is consistent is all pages. Popup menu is automatically displayed horizontally when clicking the ellipsis icon in the report list.






Tip: Export options are similar, but not the same as View options. See ["Export Options" on page 200](#)

The following table lists the view options available to all reports. Defaults are **bolded**. For a description of each format option, see ["Report Formats for Viewing and Export" on page 196](#).

View Options—All Reports



| Report Format | Options | Settings |
|---|-------------------------------|---|
|  HTML | Template | Optional |
| | Pagination | Single Page Multiple Page Horizontal Breaks |
|  PDF | Template | Optional |
| | Pagination | Single Page Multiple Page Horizontal Breaks |
| | Download Zipped File | Y/ N |
|  MS EXCEL | Pagination | Single Page Multiple Page Horizontal Breaks |
| | Repeat Page Header and Footer | Y |
| | Download Zipped File | Y/ N |
|  COMMA SEPARATED | Separator | Predefined [Comma Tab] Custom [enter character] |
| | Enclosure | Predefined [QUOTES (" ")] Custom [enter character] |
| | Template XLS | Predefined |
| | Include | Grid Y /N Chart Y/ N Matrix Y/ N |
|  TEXT | Pagination | Single Page Multiple Page Horizontal Breaks |
| | Download Zipped File | Y/ N |

View Options—All Reports, continued

| Report Format | Options | Settings |
|---|-----------------------------|--|
|  MS WORD | Template | Optional |
| | Pagination | Multiple Page |
| | Download Zipped File | Y/ N |
|  Fast CSV | Separator | Predefined [Comma Tab] Custom [enter character] |
| | Enclosure | Predefined [QUOTES (" ")] Custom [enter character] |
| | Pagination | Single Page |
| | Download Zipped File | Y/ N |
|  EMAIL | Send Report As | Attachment Link Embedded |
| | Report Format | HTML Acrobat PDF COMMA SEPARATED MS EXCEL MS WORD XML TEXT. |
| | Pagination | Single Page Multiple Page Horizontal Breaks |
| | To, CC | (To—Required) Enter one or more valid email addresses, separated by commas or semicolons. CC is optional. |
| | Subject | Enter the email subject header. |
| | Message | Modify the provided email body message, or accept the default. You can include user parameters as well as system parameters in the message text. For example, if the report you are mailing has a parameter ReportDate then you can insert it as &lt;%ReportDate%> in your message text, which will be replaced by the report execution date at run time. |
|  PRINT | Print or download report as | PDF |
|  UPLOAD | Report format | HTML Acrobat PDF COMMA SEPARATED MS EXCEL MS WORD XML Fast CSV TEXT |
| | Pagination | Single Page Multiple Page Horizontal Breaks |
| | Upload Type | FTP Shared Folder |
| | Required Fields | Server Name, File Name |
| | Optional Fields | Port, User Name, Password, Folder Name |

The following table lists the view options exclusive to Smart reports. Defaults are **bolded**.

View Options—Smart Reports

| Report Format | Options | Settings |
|---|----------------------|--------------------------|
|  iHTML | Pagination | Single Page |
|  Smart | No available options | Basic paginated display. |

Tip: The report formats available to you depend on the access rights associated with your user account. See ["Assigning Access Rights" on page 164](#).

Export Options

When exporting a report, you must select any export options for the format type before rendering the report.

Tip: Some report formats have more options for viewing than for export. See ["View Options" on page 198](#).

Export Options

General

Format: **COMMA SEPARATED**

Separator: ☒ Predefined ☐ Custom
COMMA

Enclosure: ☒ Predefined ☐ Custom
QUOTES(" ")






Target XLS:

Include: ☒ Grid ☐ Chart ☐ Matrix
☐ Download Zipped File

Export Cancel

The following table lists the export options for each report format. Defaults are **bolded**.



Export Options—All Reports

| Report Format | Options | Settings |
|--|----------------------|--|
|  MS EXCEL | Download Zipped File | Y/ N |
|  PDF * | Download Zipped File | Y/ N |
| | Page Settings | Set page orientation, size, and margins |
|  COMMA SEPARATED | General | <ul style="list-style-type: none"> Separator: Predefined [Comma Tab] Custom [enter character] Enclosure: Predefined [QUOTES (" ")] Custom [enter character] Template: attach an .XLS template not available Include: Grid Y/N Chart Y/N Matrix Y/N Download Zipped File Y/N |
|  TEXT | Download Zipped File | Y/ N |
|  MS WORD* | Download Zipped File | Y/ N |
| | Page Settings | Set page orientation, size, and margins |

* **Tip:** When rendering supersized reports, Logger does not recommend to select PDF or MS Word as these are limited formats. Instead, select MS Excel, CSV, Fast CSV, or Text.

The following table lists the export options exclusive to Smart reports. Defaults are **bolded**.

Export Options—Smart Reports

| Report Format | Options | Settings |
|---|---------|----------------------|
|  iHTML | No | No available options |
|  Smart | No | No available options |

Tip: A **Smart Export** option is available for Scheduled Reports using MS Excel, Acrobat PDF, and MS Word formats. Reports are exported into their native formats, so that users can leverage the functionality of their respective tools. See ["What is Smart Export?" on page 179](#)

Printing Reports

Publishing Reports


You can publish a report after you run it, to save the output results for that run of the report for subsequent use. You can also schedule a report to publish after each schedule run. For more about scheduled reports, see ["Scheduled Reports" on page 177](#).

- [Publishing a Report](#)202
- [Publish Report Options](#)203
- [Working with Published Reports](#) 204


Publishing a Report

Publishing a report saves the generated output with the format and expiration date you specify. The process is the same for all reports, but the Publish menu opens from an icon or a menu, depending on the viewer.


To publish a Smart report


1. Run a report in Smart format. See ["Create a New Report from an Existing One" on page 213](#).
2. From the Smart report viewer, Click  to open the options menu.
3. From the menu, click **Publish**.... The Publish menu displays.
4. Specify the published report settings. See ["Publish Report Options" on the next page](#).
5. Optionally, add a comment to the report. See ["Adding a Comment to a Report" on page 194](#).
6. Click **Publish**.

To publish an ad hoc report:

1. From the Explorer, run a report in ad hoc format.
2. From the Ad hoc Report viewer, click the  **Publish Report** icon. The Publish menu displays.
3. Specify the published report settings. See ["Publish Report Options" on the next page](#).
4. Optionally, if you would like to attach a comment to the published report, click **Add Comment**. See ["Adding a Comment to a Report" on page 194](#).
5. Click **Publish**. When the report has generated, it appears in the Published Reports list on the Recent Reports page.

To delete a published report:

1. Click the Recent Reports tab.
2. Click the  icon to open the Published Reports widget.

3. Click the button to select a published report.
4. Click  to delete the selected report. Confirm the action.

Publish Report Options

The following settings are required for publishing a report. Optionally, you can add comments to a published report. See ["Adding a Comment to a Report" on page 194](#).

Publish

Report Format:

Options

Save In:

../CrossDevice

Report Name:

Access:

☒ Public

☐ Private

Expires On:

MM/dd/yyyy h:mm a

Note - The published report will be deleted on this date.

Add Comment

Publish

Cancel

Publish Report Options

| Setting | Description |
|---------------|---|
| Report Format | The output format for the report. The default format is HTML. See "Report Formats for Viewing and Export" on page 196 . |
| Save In | Save the report in the specified category (folder). If no category is specified, the published report will be saved in the category in which the original report resides. See "Reports Explorer" on page 165 . Note: You cannot save reports into the top-level category Root . If you have access rights, you can create a new category, or save to an existing category. |
| Report Name | Enter a name that will display in the Published Reports list. See "Published Reports" on page 172 |
| Access | Select an access value: <ul style="list-style-type: none">• Public makes this report available to everyone.• Private makes this report available to you only. |

Publish Report Options, continued

| Setting | Description |
|-------------------|--|
| Expires on | Date and time after which the report output is discarded (and, therefore, unavailable for viewing). If you want the report results to remain available indefinitely (do not expire), leave this field blank. Note: Published reports are stored on the Logger Report Server. ArcSight recommends that you set an expiry date, to free up server space. |



Working with Published Reports

You can render, save, and delete reports from the Published Reports widget, as well as view any comments attached to the report. How the report displays or generates within the widget depends on the file format you select:


- Report formats that can display within a browser display in a new tab.
- Report formats that must be viewed in another application open in a new window, where you can save, export, and upload the report.

If the list of Published Reports is long, you can filter the list by published name, date, source report, and other options.


To view a published report

1. From the Recent Reports tab, click  to open **Published Reports**.
2. Select a published report.
3. From the icon menu, click a view format. See ["View Options" on page 198](#). The report displays in the appropriate viewer. See ["Report Formats for Viewing and Export" on page 196](#).
4. Click **Apply**.
5. Click  in the upper-right to return to the Published Reports list.

To download a published report



1. From the Recent Reports tab, click  to open **Published Reports**.
2. Select a published report.
3. From the icon menu, click a file format such as PDF, CSV, Excel, Word, or Text. See ["View Options" on page 198](#).

A new tab opens and displays a message similar to the following:





4. Click on Open or Save option before closing this window or tab.
5. Enter any necessary information and click **OK**.


To view comments for a published report

1. From the Recent Reports tab, click  to open **Published Reports**.
2. Select a published report.
3. From the icon menu, click . The **Show Comment** window displays any comments made to that report.
4. When you are finished, click **Done**. See ["Adding a Comment to a Report" on page 194](#).

To delete a Published Report



1. From the Recent Reports tab, click  to open **Published Reports**.
2. Select a published report.
3. Click the  icon and confirm your request. The report instance is deleted from the Published Reports list.


To filter the Published Reports list

1. From the Recent Reports tab, click  to open **Published Reports**.
2. Click **Filter** to open the filter menu.
3. Enter your filter criteria.

Note: Access to these filter criteria depends upon your Logger Reports access rights policy, your role, and your individual access rights. Other permissions may be necessary. See ["Assigning Access Rights" on page 164](#).

| Filter Criteria | Description |
|-----------------|--|
| Published | Enter a text string with some or all of the published report name. |

| Filter Criteria | Description |
|------------------|--|
| Name Includes | |
| Updated Between | Enter a date range to restrict the update time for report results. Enter a date manually in MM/dd/yyyy format, or click  to open a calendar date picker. |
| Select Report | Click the  icon to open the Object Selector window. Select a report or a folder. |
| Select Owner | Select from among the report owners for which you have access rights. |
| Private Owned By | Select from among the private reports for which you have access rights. |
| Public Owned By | Select a public report owner from the list for which you have access rights. |

- Optionally, click  **(Root)** to open the category filter, and navigate to the published report you want to find.
- Click **Apply**. The filtered list displays.

Exporting and Uploading Reports



Once you generate a report, you can export it for use in other formats, or upload it to an FTP site or shared folder.

- [Exporting and Saving a Report](#)206
- [Uploading a Report to a Server or FTP Site](#)207

Exporting and Saving a Report


You can export a report to a file format of your choice and save it.

To export and save a report:

- While viewing a report, do one of the following actions:
 - From the Smart report viewer, click the  in the upper right to open the Viewer menu and click **Export**. See ["The Smart Report Viewer" on page 193](#).
 - From the Ad hoc report viewer, click  the Export icon to open the Export dialog. See ["The Ad hoc Report Viewer" on page 191](#).
- In the **Export Options** dialog, specify the Export Format and associated settings you want. See ["Export Options" on page 200](#).

Depending on the export format you choose, other settings are displayed as appropriate.

Tip: When rendering super-sized reports, Logger does not recommend to select PDF or MS Word as these are limited formats. Instead, select MS Excel, CSV, Fast CSV, or Text.



The screenshot shows the 'Export Options' dialog box with the 'General' tab selected. The 'Format' dropdown is set to 'COMMA SEPARATED'. The 'Separator' is set to 'Predefined' with a radio button, and the 'Comma' dropdown is set to 'COMMA'. The 'Enclosure' is set to 'Predefined' with a radio button, and the 'Quotes' dropdown is set to 'QUOTES(" ")'. The 'Target XLS' dropdown is empty. The 'Include' section has checkboxes for 'Grid' (checked), 'Chart', and 'Matrix'. There is also a checkbox for 'Download Zipped File'. At the bottom right, there are 'Export' and 'Cancel' buttons.



3. Click **Export**.

You can save the generated report as a file locally or elsewhere just as you would any other file.

Uploading a Report to a Server or FTP Site

You can upload reports to a server or file transfer protocol (FTP) site.

To upload a report:

1. While viewing a report, do one of the following actions:
 - From the Smart report viewer, click the  in the upper right to open the Viewer menu and click **Upload**. See ["The Smart Report Viewer" on page 193](#).
 - From the Ad hoc report viewer, click  Upload, or click directly on another output format. See ["The Ad hoc Report Viewer" on page 191](#).

The **Upload Options** menu opens.

2. Select the report format and upload options. See ["Report Formats for Viewing and Export" on](#)

[page 196.](#)

Tip: Upload options are similar to Export options, except that the default for uploading a Zipped file is **Yes**.

3. Select an upload type: **FTP** or **Shared Folder**.
 - If you select FTP, See ["FTP Upload Options" on the next page.](#)
 - If you select Shared Folder, see ["Shared Folder Upload Options" below.](#)
4. Enter the required and optional fields for the upload type.
5. Click **Upload**. A confirmation message displays
The report uploads to the folder and server you specified.

Shared Folder Upload Options

Enter the following fields when uploading a Logger report to a shared folder.

Report Format: ACROBAT PDF ▼ Options ▼

Upload Type: ☒ FTP ☐ Shared Folder

Secure ☐

Use PASV mode ☐

Server Name: Port:

User Name: Password:

Folder Name:

File Name:

Upload to Shared Folder Menu Fields

| Field | Description |
|-------------|---|
| Folder Name | (Required) Enter the folder path on the Shared Folder where the report should go. |
| File Name | (Required) Enter a file name for the report. |

FTP Upload Options

Enter the following fields when uploading a Logger report to a File Transfer Protocol (FTP) site.

Upload Options ✕

Report Format: HTML ▼ Options ▼

Upload Type: ☒ FTP ☐ Shared Folder

☒ Secure

☐ Use PASV mode

Server Name*: ftp.hpe.com Port:

User Name: LggLvr Password:

Folder Name: /opt/reports/

File Name*: Most Common Events Report

Upload

Cancel

Upload to FTP Menu Fields

| Field | Description |
|---------------|--|
| Secure | Use Secure Shell (SSH) FTP protocol to upload the file. |
| Use PASV mode | Use Passive FTP protocol to upload the file. |
| Server Name | (Required) Enter the hostname or IP address of the target server. |
| Port | Enter a port number, if required. |
| User Name | Enter the server user name to log into the target server. |
| Folder Name | Enter the folder path on the target server where the report should go. |
| File Name | (Required) Enter a file name for the report. |

Emailing a Report

You can send a report using email as either a Web link or an attachment.

Prerequisite

Before you can email a report, you must first set up SMTP for reports. Navigate to **System Admin > SMTP** and configure the SMTP settings.

To email a report:

1. From the Ad hoc report viewer, click the Email Report icon (✉) from the menu bar.
2. Specify the email delivery settings. See ["Email Delivery Settings" below](#).
3. Click **Email** to send the report.

Email Delivery Settings

Enter the following settings when setting up a generated email for a scheduled or other report. You may also need to specify other settings, including format, delivery options, and parameters.

Delivery Operations

☒ Email ☐ Publish

Send Report As ☐ Link ☐ Attachment ☒ Embedded

File Name ☐ Suffix Timestamp Format

To

Cc Bcc

Subject ☐ Suffix Timestamp Format

Message
Hello,

You have received this
automated email to let you know that report <%
MENU_NAME%> has been

Email Delivery Settings

| Setting | Description |
|-------------------------|--|
| Send Report As | <p>Choose one of these:</p> <ul style="list-style-type: none">• Link—Generates a link to the report in the body of the email.• Attachment—Sends the report as an attachment to the email.• Embedded—Sends the report in the body of the email. <p>Note: The formats allowed are HTML and Text.</p> |
| File Name | Enter a file name for the report. |
| Suffix Timestamp Format | (Optional) Check if you want a timestamp appended to the file name. Select the timestamp format from the drop-down menu. |

Email Delivery Settings, continued

| Setting | Description |
|-------------|---|
| To, Cc, Bcc | To —(Required) Enter one or more valid email addresses, separated by commas or semicolons. Cc and Bcc are optional. |
| Subject | Enter the email subject header. |
| Message | <p>Modify the provided email body message, or accept the default.</p> <p>Include place holder: <%SAVED_REPORT_LINK%>. Otherwise, message will be sent empty.</p> <p>You can include user parameters as well as system parameters in the message text. For example, if the report you are mailing has a parameter ReportDate, then you can insert it as <%ReportDate%> in your message text, which will be replaced by the report execution date at run time.</p> |

Designing Custom Reports

You can create new or customized reports using report objects such as custom queries, templates, and search parameters. This section explains how to use the report design tools to bring these objects together as a new report.

For information about building the report objects themselves, see ["Designing Queries, Parameters, and Templates" on page 250](#).

- [Powerview Designer and Classic Report Designer](#)211
- [Working with Logger Report Designers](#) 212
- [Create a New Report from an Existing One](#)213
- [The Smart Report Designer](#)215
- [The Powerview Designer](#)219
- [Classic: The Ad hoc Report Designer](#)224
- [Report Components](#)225
- [Creating an IPv6 Report](#)227
- [Private Reports](#)228
- [Customizing Report Elements](#) 228

Powerview Designer and Classic Report Designer

Any Ad hoc report can be modified in either the Powerview designer, or the Ad hoc Report Designer. Both tools have the same capabilities. However, the Powerview designer allows you to work right from the report viewer, seeing changes in real-time as you make them. Right-click within the report to access the option menus.

- **Powerview designer** — Work right from the report viewer, seeing changes in real-time as you make them. Right-click within the report to access the option menus. See ["The Powerview Designer" on page 219](#).
- **Ad hoc Report Designer** — Work from a toolkit environment, with different report elements available in tabs within the tool. See ["Classic: The Ad hoc Report Designer" on page 224](#).

Working with Logger Report Designers

Not sure how to get what report into what designer? Follow these steps.

Customize an Ad hoc report in the Powerview designer:

1. Click **Explorer** from the Reports menu to open Explorer.
2. Right-click the report you want to customize, to open the context menu. See ["Explorer Options and Context Menus" on page 169](#).
3. Select a run option **other** than "Run in Smart Format." See ["Understanding Run Report Options" on page 183](#).
4. Run the report to open the report in the Powerview designer. See ["The Powerview Designer" on page 219](#).
5. Optionally, right-click within the tabular results to open the context menu and click **Save Layout As**, if you want to preserve the original report.

Customize an Ad hoc or Smart report in the Smart designer:

1. Click **New Report** from the Design section of the Reports menu to open the Smart View page.
2. Click **Open Existing Report...** in the lower right to open the Open Report Layout menu.
3. Navigate to the report you want to customize and select it.
4. Click **Open**. The report runs, and opens in the Smart designer. See ["The Smart Report Designer" on page 215](#).

Tip: Saving an Ad hoc report in the Smart designer will convert it to a Smart report.

5. Optionally, click **Save As** from the bottom-right menu, if you want to preserve the original Ad hoc report.

Customize an Ad hoc or Studio report in the Ad hoc Report Designer:

From the Ad hoc Report Designer:

1. Click **New Report** from the Classic section of the Reports menu to open the Ad hoc designer. See ["Creating a New Classic Report" on page 226](#).
2. Click **Open** from the upper right menu to open the Open Report Layout menu.

3. Navigate to the report you want to customize and select it.
4. Click **Open** to open the report in the Ad hoc Report Designer. See ["Classic: The Ad hoc Report Designer" on page 224](#).
5. Optionally, click **Save As** from the upper-right menu, if you want to preserve the original report.

From Explorer:

1. Click **Explorer** from the Reports menu to open Explorer.
2. Right-click the report you want to customize, to open the context menu. See ["Explorer Options and Context Menus" on page 169](#).
3. Click **Customize** to open the report in the Ad hoc designer. See ["The Powerview Designer" on page 219](#).
4. Optionally, click **Save As** from the upper-right menu, if you want to preserve the original report.

See also

- ["Smart Reports" on page 217](#)
- ["Creating a New Smart Report" on page 218](#)
- ["The Smart Report Designer" on page 215](#)
- ["Create a New Report from an Existing One" below](#)
- ["The Smart Report Viewer" on page 193](#)
- ["How do Smart Reports differ from Ad hoc and Studio Reports?" on page 160](#)

Create a New Report from an Existing One

Since Logger ships with a variety of useful, pre-built reports for common security scenarios, you can use these not only to run as-is but also as templates for building new reports. A good way to get familiar with the process is to start with an existing report that has some of the features you want, save the original report under a new name, and then modify it. See ["How do Smart Reports differ from Ad hoc and Studio Reports?" on page 160](#).

Caution: Modifications to reports and other ArcSight-defined content may be overwritten without warning when the content is upgraded. Do not modify ArcSight-defined content directly.

Make modifications to a copy of any ArcSight-defined content as a general practice, and subsequent upgrades will not affect the modifications.

To create a new report based on an existing Logger report:

1. In the **Explorer**, browse to the report you want to use as a starting point.
2. Select and click **Customize Report** from the context menu.

Note: Some reports, such as Logger default reports or other custom reports, might not be

editable. If the **Customize Report** link is disabled, save a copy of the report and customize that one.

- Smart reports run and display in the Smart designer. See ["The Smart Report Designer" on the next page](#).
 - Ad hoc reports open directly in the Ad hoc Report Designer. See ["Classic: The Ad hoc Report Designer" on page 224](#).
3. Modify the report according to your needs. See ["Customizing Report Elements" on page 228](#).
 4. Save your new report.
 - From Smart Designer: In the bottom-right corner, click the ▼ next to **Save** to open the menu. Click **Save As**.
 - From Ad hoc Report Designer: Click **Save As** from the top right menu.

This displays the **Save Report Layout As** dialog for the selected report (and shows all reports stored in the same category as the one you selected).

5. In **Report Name**, enter a name for your report.

Icons: List, Search, Calendar, Refresh

Name

- ▲ (Root)
 - ▲ SANS Top 5
 - ▶ 5 - Suspicious or Unauthorized Network Traffic Patterns

Report Name: **Save** **Cancel** ^ Options

ID: ☒ System Generated

☒ Public ☐ Private

☒ Copy Access Rights

Description:

*=Read Only

6. Click **Options** (next to the Cancel button), and enter values for the following fields:

| Option | Description |
|---------------------------|--|
| ID | Enter a custom ID for the report, if desired. Alternatively, Select System Generated to automatically generate one (selected by default). |
| Public/Private | Select one. If public, everyone will have access to this report; if private, only you. |
| Copy Access Rights | When checked (the default) the report will inherit the access rights of the source report. |
| Description | Optionally, enter a description for the report. |


7. Click **Save**.
8. Click **OK** to confirm the save. Your new report is now available in the selected category folder.

See also


- ["Reporting" on page 156](#)
- ["Creating a New Smart Report" on page 218](#)
- ["The Smart Report Designer" below](#)
- ["The Smart Report Viewer" on page 193](#)
- ["Working with Logger Report Designers" on page 212](#)
- ["How do Smart Reports differ from Ad hoc and Studio Reports?" on page 160](#)

The Smart Report Designer


Smart View is a web-based, interactive interface designed to visualize and analyze large amounts of data. Use the Smart report designer to make your Smart reports retrieve, display, and look exactly the way you want them to.



1. Click **New Report** from the Design section of the Reports menu. The **Smart View** page opens in a new Report tab.



- If you double-click a report from the **Select Query Object** list, Logger runs the report, and opens it for editing in the Smart designer. From there, you can save and modify the report. To have the latest report version, right click and select the **refresh** option on each category. Additionally, the below menu will be displayed whenever you right click a query object. For information about modifying report results, such as adding logos, charts, and changing the display options, see [Creating a New Smart Report](#).



- If you click **Open Existing Report...** in the lower-right corner, you can select a copy of a report you have previously saved. Logger will run the report and display it in the Smart designer. From there, you can save and modify the report.
- If you click **Create Query Object...** in the lower-right corner, the Query page opens within Smart View. For more, see ["Queries" on page 250](#)

Open the Smart report designer:

See also

- [Smart Reports](#)
- [Creating a New Smart Report](#)
- [Create a New Report from an Existing One](#)
- [The Smart Report Viewer](#)
- [Working with Logger Report Designers](#)
- [How do Smart Reports differ from Ad hoc and Studio Reports?](#)

Smart Reports

You can create custom reports from existing ones, or build a new report from scratch.

New Report > opens in Smart View {Open Existing Report... | Create Query Object}

See also

- ["Creating a New Smart Report" on the next page](#)
- ["The Smart Report Designer" on page 215](#)
- ["Create a New Report from an Existing One" on page 213](#)
- ["The Smart Report Viewer" on page 193](#)
- ["Working with Logger Report Designers" on page 212](#)
- ["How do Smart Reports differ from Ad hoc and Studio Reports?" on page 160](#)

Creating a New Smart Report

To create a new Smart Report:

Click **New Report** from the Design section of the Reports menu. The **Smart View** page opens in a new Report tab.

- Select a report from the Select Query Object list. Logger runs the report, and opens it for editing in the Smart designer. From there, you can save and modify the report.
- If you click **Open** in the upper-right corner, you can select a copy of a report you have previously saved. Logger will run the report and display it in the Smart designer. From there, you can save and modify the report.

Note: Columns named **globalEventId** and **eventID** are aligned to the right.

If you click Create **Create Query Object** in the lower-left corner, the Query page opens within Smart View. For more, see [Queries](#)

See also

- [Smart Reports](#)
- [The Smart Report Designer](#)
- [Create a New Report from an Existing One](#)
- [The Smart Report Viewer](#)
- [Working with Logger Report Designers](#)
- [Create a New Report from an Existing One](#)
- [How do Smart Reports differ from Ad hoc and Studio Reports?](#)

Annotating Smart Report Charts

You can annotate (add explanation or comment) to report charts through the Description field in the Chart Properties menu. See ["Chart" on page 237](#) for more information on Chart properties.



Tip: In this release, only Smart report charts can be annotated in this way.

To annotate a Smart report

1. From Explorer, run a Smart report that includes a chart.
2. Make sure the report is in Edit Mode.



The Chart edit tools display.


3. Click  to open the Chart Properties window. See ["Chart" on page 237](#).
4. In the Settings tab, Miscellaneous section, Click  to open the Description menu.
5. From the Description menu, create your annotation and click **OK**.


Tip: Where you position the description, and how large it is, can affect the size of the chart visualization. If the chart is part of a Dashboard, consider adding a Rich Text widget to the layout, which can display the information without compressing the chart.

6. When you have finished your chart modifications, click **Apply**. The annotation displays in the chart.
7. When the chart looks as it should, remember to click **Save** or **Save As** (in the bottom-right) to save the report.

The Powerview Designer

When you run an editable Ad hoc report (from Explorer or Recent Reports, for example), the first ten columns and 200 rows of your report display in the Powerview designer. In addition to the same menu bar as the viewer, you can modify your report and add and edit charts.

Tip: The Powerview designer looks very much like the Ad hoc Report viewer. The Powerview designer displays the Powerview designer icon  on the right side of the menu bar.

In the Powerview designer, your home page includes your sample report data and any chart or matrix, with report format, configuration, and display options available through context menus. In contrast, the Ad hoc Report Designer uses the Data Source menu tab as its home page, and you must click the  Preview or Run button to see the report as it will display. You can choose which designer you prefer. See ["Classic: The Ad hoc Report Designer" on page 224](#).

Tip: Right-click within the report headers or report body to open the Powerview designer context menus. Mouse just above the chart to see the chart menu.

When a report with a chart opens in Powerview designer, the chart opens above the data grid. You won't see the chart menu until you move your mouse near the top of the chart. For a description of these menus, see ["The Powerview Chart Menu" on page 222](#).

The Powerview designer includes these menu activity areas:

| Area | Options | See |
|----------------------|---|--|
| Menu bar | Click an icon to publish, export, or page through the report, or add and view comments. Only the designer displays the Powerview icon on the far right. | "Ad hoc Viewer Menu Options" on page 191. |
| Heading context menu | Right-click a column header to open an option menu of available data editing tools. | "The Powerview Heading Context Menu" on the next page. |

| Area | Options | See |
|--------------------|---|---|
| Data context menu | Right-click within the data to open an option menu of report options such as Add Chart and Save Layout As. | *The Powerview Data Context Menu" on the next page. |
| Chart context menu | When a chart is present, hover towards the top of the chart to display the chart context menu. The menu remains hidden until it is moused-over. | *The Powerview Chart Menu" on page 222. |

The Powerview Heading Context Menu

When you right-click within the report headers, a context menu displays. The header menu deals mostly with modifying the report results display by column. In contrast, the data context menu deals more with global report options. See ["The Powerview Data Context Menu" on the next page.](#)

To change an option from the heading context menu:

1. Right-click over the data column you want to group by and select from the menu.
2. You will see the action ready for confirmation in the Action Board. To apply this change immediately, click **Apply** in the Actionboard, or wait until you have made all the changes you want to make.

Tip: If you don't want to apply multiple actions at once, you can click **Immediate Refresh** from the data context menu to apply your changes automatically.

The heading context menu contains the following options:

| Menu Option | Description |
|---------------|--|
| Show | Click Show and select any column that isn't visible, to display it. |
| Hide | Click Hide to remove the column you clicked on from the report output. Once applied, any hidden columns appear in the Show list. |
| Group | Group the data by the column you clicked from. |
| Totals | Select one of your available options. For example, Count and DistCount . |
| Sort | Click either Ascending or Descending to sort the data by that column. |
| Reset Width | Click to reset the selected column to its default width. |
| Other Options | The options on your context menu may vary with report type and query. For example, Count columns may have the option to Render as DataBar . |


The Powerview Data Context Menu

When you right-click within the report data, a context menu displays. The data menu deals with the more global report options. In contrast, the header context menu deals with report changes mostly at the column level. See ["The Powerview Heading Context Menu" on the previous page](#).

To change an option from the data context menu

1. Right-click anywhere in the report data and select from the context menu.


| Severity | Name |
|----------|--------------------------|
| <u>3</u> | Successful login |
| <u>3</u> | Session expired |
| <u>2</u> | Saved Search updated |
| <u>2</u> | Saved Search added |
| <u>1</u> | Individual Receiver EPS |
| <u>1</u> | Storage Group Space Used |
| <u>1</u> | Network Usage - Outbound |
| <u>1</u> | Network Usage - Inbound |



2. You will see the action ready for confirmation in the Action Board. To apply this change immediately, click **Apply** in the Actionboard, or wait until you have made all the changes you want to make.

Tip: If you don't want to apply multiple actions at once, you can click **Immediate Refresh** from the data context menu to apply your changes automatically.

The data context menu contains the following options:

| Menu Option | Description |
|---------------------|---|
| Group | <p>When you mouse over Group, a list of columns display. Select a column to group the data by the selected column.</p>  |
| Suppress Duplicates | Select this option to hide duplicate events in your report display. Once applied, the menu option changes to Show Duplicates . |
| Add Chart | Select this option to create a chart for the report. You can create more than one chart per report. See "Creating a Chart for an Ad hoc Report in Powerview" on the next page . |
| Template | Select Template to choose from a list of all available templates for your report. See "Template Styles" on page 284 . |
| Immediate Refresh | When you select Immediate Refresh mode, your selections are applied without using the Actionboard. This mode will stay in effect until you deselect it. |
| Preview Mode | Select Preview Mode to limit your report view (while you are working on it) to the first 200 records. Unselect it to view the entire report. |
| Save Layout As | <p>Select this option to save the report in its current form, rename, or save the report to a new location.</p> <p>Tip: Save your work often. If your Logger times out, you could lose your work.</p> |

The Powerview Chart Menu






When a report with a chart opens in Powerview designer, a default chart opens above the data grid. Logger uses the first character field as the X axis, and the first numeric field as the Y axis, and plots the chart. The Powerview designer gives you access to the most commonly used report options. For many more options, open the report in the Classic Ad hoc Report Designer. See ["Classic: The Ad hoc Report Designer" on page 224](#).

Tip: You won't see the chart menu until you move your mouse near the top of the chart.

To change an option from the chart context menu

1. Hover just above the chart to open the chart context menu.
2. Click the icons to configure your chart options.

The data context menu contains the following options:

| Menu Icon | Description |
|---|--|
|  | Change the chart type. Select between 2D and 3D images. Chart types include: Bar, column, pie, doughnut, line, area, curve, curve area, scatter, bubble radar, line radar, gauge, counter, tree map, packed circle, sunburst, funnel, and pyramid. |
|  | Change the data source. Click to select a report or query to use as the source of the chart. |
|  | Link or unlink the chart to either report fields or a matrix. The default is linked. Look for this icon  just above the report data. If it shows the check mark, your chart is linked to the report data. If the report data changes, the chart does, also. If there is no checkmark, the chart will not reflect any changes to the original report data. |
|  | Check or uncheck chart display settings. Setting options include: Show Legends, Show Point Labels, and Show Description. |

Note: Your changes update immediately, without needing to commit them on the Actionboard.

3. From the report data area, right-click to open the context menu and select **Save as** to save your report.

Creating a Chart for an Ad hoc Report in Powerview

When you run an editable Ad hoc report, you can add a chart to the report data in the Powerview designer.

To create a chart for an Ad hoc report in Powerview:

1. Run an editable Ad hoc report. The report opens in the Powerview designer. See ["Understanding Run Report Options" on page 183](#).
2. Right-click within the report data (not the headers) to open the Powerview data context menu. See ["The Powerview Data Context Menu" on page 221](#).
3. Select **Add Chart**. Please wait while Logger generates a default chart for your report from the first ten columns and 200 rows of your report display.
4. Hover above the chart to display the chart menu. Make any adjustments to the chart from the available menu options. See ["The Powerview Chart Menu" on the previous page](#).
5. Select **Save Layout As** from the Powerview data context menu to save the report.

This displays the **Save Report Layout As** dialog for the selected report (and shows all reports stored in the same category as the one you selected).

6. In **Report Name**, enter a name for your report.

Name

▲ (Root)

▲ SANS Top 5

▶ 5 - Suspicious or Unauthorized Network Traffic Patterns

Report Name **Save** **Cancel** ^ Options

ID ☒ System Generated

☒ Public ☐ Private

☒ Copy Access Rights

Description

*=Read Only


7. Click **Options** (next to the Cancel button), and enter values for the following fields:

| Option | Description |
|---------------------------|--|
| ID | Enter a custom ID for the report, if desired. Alternatively, Select System Generated to automatically generate one (selected by default). |
| Public/Private | Select one. If public, everyone will have access to this report; if private, only you. |
| Copy Access Rights | When checked (the default) the report will inherit the access rights of the source report. |
| Description | Optionally, enter a description for the report. |

8. Click **Save**.
9. Click **OK** to confirm the save. Your new report is now available in the selected category folder.

Classic: The Ad hoc Report Designer

When you click **New Report** from the Classic menu, or when you select **Customize Report** for an Ad hoc report in Explorer, you are redirected to the Ad hoc Report Designer.

In the Ad hoc Report Designer (ARD), you build your report using the Data Source menu tab as a home page. As you make your changes between tabs, you can click the  Preview button to see the report as it will display. You can use this designer to create and edit reports, if you prefer these classic tools to the Powerview designer. The tools and capabilities between the Powerview and ARD are the same; the differences lie in the user interface. See ["The Powerview Designer" on page 219](#).

To open the Ad hoc Report Designer:

1. Select **New Report** from the Classic Reports menu. The Ad hoc Report Designer opens in a new tab.








Toolbar Buttons

The toolbar includes these buttons.

- Click **Run** to test the current version of the report.
- Click **Preview** to preview the report before saving it.
- Click **Open** to open another report in the Report Designer.
- Click **Save** to save the report.
- Click **Save As** to save it under a different name.

Report Components

A report consists of different components, which can each affect the way the data displays in the report. Click a component tab at the top of the Designer page to open the component configuration page.

| Tab | Description |
|---|---|
| Data Source  | See "Data Source" on page 228 for more information. |
| Fields  | See "Fields" on page 229 for more information. |
| Filter  | See "Filter" on page 230 for more information. |
| Group  | See "Group" on page 232 for more information. |
| Totals  | See "Totals" on page 233 for more information. |
| Sort  | See "Sort" on page 234 for more information. |
| Highlight  | See "Highlight" on page 234 for more information. |

| Tab | Description |
|---|---|
| Matrix  | See "Matrix" on page 236 for more information. |
| Chart  | See "Chart" on page 237 for more information. |
| Expand All/ Collapse All  | Toggles the detail view. Once expanded, you can also toggle visibility of an individual component in the Designer by clicking the component's title bar. For example, to toggle visibility of the Highlighting component, click the Highlighting title bar (above the Create Matrix title bar). |

Creating a New Classic Report

To create a new Classic report:

- Under **Classic**, click the **New Report** link in the left panel. The Ad hoc Report Designer > Untitled Report page displays. See ["Classic: The Ad hoc Report Designer" on page 224](#).


Ad hoc Report Designer > **Untitled Report**

Run Preview Open Save Save As

Data Source Fields Filter Group Total Sort Highlight Matrix Chart Map

Data Source


Select Source

Query Object: (Root) 


Query Editor...


Report Settings




Report Title:






Report Format: HTML 

View Options

Template: Blank 

Report Contents: Detailed 

- From the  **Data Source** tab, either select a query from the repository menu, or click **Query Editor...** to create your own. See ["Queries" on page 250](#).
Enter basic report design information, such as title, template, and format, in the Report Settings section. See ["Data Source Design Settings" on page 228](#).
- Configure the report display fields from the  **Fields** tab. See ["Fields" on page 229](#).
- Enter any filter criteria from the  **Filter** tab. See ["Filter" on page 230](#).
- Enter any grouping criteria from the  **Group** tab. See ["Group" on page 232](#).

6. Enter any column totals criteria from the  Total tab. See ["Totals" on page 233](#).
7. Enter any sorting criteria from the  Sort tab. See ["Sort" on page 234](#).
8. Enter any highlight criteria from the  Highlight tab. See ["Highlight" on page 234](#).
9. Enter any matrix criteria from the  Matrix tab. See ["Matrix" on page 236](#).
10. Enter any charting criteria from the  Chart tab. See ["Chart" on page 237](#).
11. Click **Save** to save the new report.


Creating an IPv6 Report

Prerequisites

Before you can create a report displaying IPv6 events, you must first create the query to capture IPv6 information. See ["Creating an IPv6 Search Query for Reports" on page 252](#).


To create a report that incorporates an IPv6 query:

1. Navigate to **Reports | Classic > New Reports**.



Data Source


Select Source

Query Object: (Root) 


Query Editor...


Report Settings

Report Title: IPV6 Report

Report Format: HTML 

View Options

Template: Blank 

Report Contents: Detailed 

2. Open the **Fields** tab. Select the fields in the **Selected Fields** column that you want to appear in the report. Select all of the IPv6 address fields.
3. Save the report. It will now be available through the Explorer.

Tip: If you check under the filter tab, you should see the list of fields. The filter can be configured ahead of time to run by default and they are also available at runtime.

Private Reports

If you have access rights to view, run, and schedule all reports, you can create **private** reports. If you do not have permissions to edit a **public** report that you want to modify but you do have permissions to create private reports, then you can save the public report as a private one and edit the private report.

To set the default report access scope as Public or Private:


1. Go to in **ReportClient.properties** file.
2. Configure **DEFAULT_REPORT_SAVE_SCOPE** property as **public** or **private**. If no scope has been specified, the previous scope will be the default.
3. Restore services.

For more about publishing a report as public or private, see ["Publish Report Options" on page 203](#). For more about access rights for reports, see ["Assigning Access Rights" on page 164](#).

Customizing Report Elements

No matter which report designer you choose, the main report configuration elements are the same.

To access the report configuration pages from a designer:

- In the Smart designer, use the  Smart options menu.
- In the Powerview designer, right-click within the report.
- In the Ad hoc Report Designer, click the tab for the configuration element you want to modify.

Data Source

Every report is built on a base query. To select one for your report, under **Select Source** in **Query Object**, browse to a query to use.

For instructions on how to view a list of the default search fields, see ["Default Fields" on page 333](#). For information about custom schema fields added to the default schema, see ["Adding Fields to the Schema" on page 431](#).

You can edit the selected query by clicking **Query Editor**. (For information on building new queries, see ["Queries" on page 250](#).)

Data Source Design Settings

| Option | Description |
|--------------|---|
| Query Object | Navigate to a query, or click Query Editor... to create a new query. See "Queries" on page 250 . |

Data Source Design Settings, continued

| Option | Description |
|-----------------|---|
| Formula Fields | Add a formula expression that can use existing field(s). This formula field can be treated like any other field on grid, chart or matrix in the report. |
| Report Title | Give this report a title. |
| Template | Select the template to apply to this report. The templates pull-down menu shows supplied templates, and any custom templates you may have added. To include the start time, end time, scan limit, device group, storage group, and devices information (used to run a report) in a report, choose the "BlankWithHeader" template. See "Template Styles" on page 284 . |
| Report Format | Select the default format for the report. See "Report Formats for Viewing and Export" on page 196 . |
| Report Contents | Select whether report should detailed or summarized. Default is Detailed . |

Fields

Once you select a query to use in the report, the display fields it contains are shown in the **Available Fields** list. You can select which of these display fields you want to use in your report. You can edit the selected query by clicking on the **Query Editor** link. (For information on building new queries, see ["Queries" on page 250](#).)







Note: In addition to the fields in the WHERE clause of the query, the fields in the SELECT clause also need to be indexed to yield faster report generation. For more information about indexing fields, see ["Indexing" on page 146](#).

Enter a title for the report in the **Report Title** field, and then select whether the report contents should be Detailed or Summarized in the **Report Contents** field. The report title is displayed at the top of a report.

Select the query you want to use for the report from the drop-down list located on top of the Select Display fields section. The Available Fields list is populated with the fields defined in the selected query.

Select the fields to use in the report by moving fields from **Available Fields** into the **Selected Fields** list.

Note: You must move at least some available fields to the **Selected Fields** list, or the report will not run correctly

- Select a field in **Available Fields** and click  to move it into the **Selected Fields** list, or click  to add all fields.
- To deselect fields that you do not want in the report, select a field in the **Selected Fields** list and click  to move it back to the **Available Fields** list, or click  to deselect all fields.
- Use the move up  and move down  arrows to order the Selected Fields.

Tip: For information on how to create query objects for use in reports, see ["Queries" on page 250](#). All

available queries, including new queries you create, show up in the pull-down menu in the Select Display Fields section of the Ad hoc Report Designer.

Filter

Filter criteria are defined as part of a report design. When other users run the report, they receive the built-in filters by default. You can also set filter criteria and row limits on an ad hoc basis when you run a report. However, values set at run time are not built in to the report like those set at design time. Run-time parameters are only applicable to a particular report run and do not persist.



| | | Open | Field | Criteria | Use Field | Value | Close | Relation |
|---|---|------|-------|----------|--------------------------|-------|-------|----------|
| + | - | ▼ | ▼ | ▼ | <input type="checkbox"/> | | ▼ | ▼ |
| + | - | ▼ | ▼ | ▼ | <input type="checkbox"/> | | ▼ | ▼ |
| + | - | ▼ | ▼ | ▼ | <input type="checkbox"/> | | ▼ | ▼ |

If a report does include default filter criteria, users have the option to run the report with the defaults, or modify or remove the built-in filters at run time. For more information, see ["Run-Time Filters, Criteria, and Parameters" on page 187](#).

You can set filters on the results of the base query with logical expressions to narrow the focus of the report results. For example, you could set the filter criteria on a report on Top Password Changes to report only on password changes related to specified user names or involving specified IP addresses.


You can limit the number of rows in a report by defining a **Max. Rows** value, or require filtering on one or more fields of your choice using the **Mandatory** option.


Select Filter Criteria Options

| Option | Description |
|-----------------------------|---|
| Maximum Rows (Max. Rows) | <p>Specify the maximum number of rows in the report output. Results that push the number of rows beyond the Max. Rows limit you define will not be included in the report.</p> <ul style="list-style-type: none"> • Selecting set Max. Rows and also specifying a grouping under Set Grouping (as described in "Group" on the next page), may produce a different result than if you just specified Max. Rows without grouping. • Setting this field to 0 returns an unlimited number of rows. • Increasing the maximum rows for report may not always increase the number of rows returned by the report. If the query invoked by the report limits the number of rows returned, increasing the Max. Rows setting in the report has no affect. For example, if you edit the NIST IR Top 10 High Risk Events report and change the value in the Max. Rows column from 10 to 20, when the report is run report only 10 rows are returned. This is because the query invoked by the report is returning 10 rows. However, you can limit the number of rows returned by the report to a number less than the default value. For example, if the value of the Max. Rows field is changed from 10 to 5 for the NIST IR Top 10 High Risk Events report, this report returns 5 rows during run time. • You can increase the number of rows returned by editing the query and changing the number of rows returned by the query and change the number specified in the Max. Rows field of the report. |
| Field | <p>The Fields will be populated with event data fields specified in the base query. (Fields will generally equate to columns in reports.)</p> <ol style="list-style-type: none"> 1. Select a field on which to filter. 2. To add another field on which to filter, click  (Add Filter). 3. To remove a filter, click  (Remove Filter). <p>For instructions on how to view a list of the default search fields, see "Default Fields" on page 333. For information about custom schema fields added to the default schema, see "Adding Fields to the Schema" on page 431.</p> <p>Multiple filters with conditions set on different fields will be AND'ed together. Multiple filters with conditions set on the same field will be OR'ed together.</p> <p>For example, if you want to filter on events to return data based on a value/count (of rows or other) between 90 and 100, use the Between criteria to do this (for example, <Field> Between 90 and 100)</p> <p>Setting two filters on the same field with criteria "Above 90" and the other as "Below 90" would not give you the data you are looking for. Only one of these filters would be triggered.</p> <p>If the query you choose for this report has mandatory filtering, the "Select Filter Criteria" panel title and one or more fields are marked with a red asterisk. See details.</p> |
| Criteria | <p>Select a logical operator. (For example, Is, Is Not, Starts With, Ends With, Contains, and so forth.)</p> <div> <p>Tip: To make the query case-sensitive, select the Match Case option for your operator.</p> </div> |
| Value | Select a value to complete the conditional filter expression. |










Group

Grouping brings together related report data into logical groups based on particular fields. The data can be arranged in ascending or descending order, and can display the selected field value, or a summary value. You can create different groups to display information in different ways.

To configure report groups, select **Reports | New Report**, then click **New Report** from the Design menu. The **Ad hoc Report Designer** page displays. Click the Group tab () to open the **Select Grouping** menu.



The **Select Grouping** dialog box shows a configuration table for report groups. It includes a title bar with a group icon and a count of 0. The table has columns for Field, Order, Ranking Field, Ranking Function, and Show When. There are three rows for defining groups: 'Group By', 'Then By', and another 'Then By'.

| | Field | Order | Ranking Field | Ranking Function | Show When |
|--|----------------------|----------------------|----------------------|----------------------|---|
|   Group By | <input type="text"/> | <input type="text"/> | <input type="text"/> | <input type="text"/> |  |
|   Then By | <input type="text"/> | <input type="text"/> | <input type="text"/> | <input type="text"/> |  |
|   Then By | <input type="text"/> | <input type="text"/> | <input type="text"/> | <input type="text"/> |  |

Note: A report that has a group defined can only display up to 100,000 lines.

Example 1: Let's say you create a group that displays "Total Sales" in descending order (Z to A). The total sales of "East Region" is 1000 units, and total sales of "West Region" is 1900 units. In the report, the "West Region" group detail will appear before "East Region" group details.

Example 2: If the report uses a query that includes a Date field, you can group results by date. You could add additional statements to group by "User Name", "Source Address", "Destination Address", and so forth, depending on what other fields are available in the report query.

Note: Selecting set Max. Rows under **Select Filter Criteria** (as described in ["Filter" on page 230](#)) and also specifying grouping may produce a different result than if you just specified Max. Rows without grouping.



See the table ["Run-Time Filters, Criteria, and Parameters" on page 187](#) for more information about report settings.

To define a group:



1. From the **Group By** menu, select available options from the following menus to specify what event information should be groups, in what order, and under what conditions.

The **Group By** field is the primary field in the data group, organized by the ranking field, in ascending or descending order.

Select Group By Fields

| Option | Description |
|-----------------------------------|--|
| Field | <p>Select an option from the menu to make it the primary field in the report group. The Field menu is populated with event data fields specified in the base query.</p> <ul style="list-style-type: none"> To add another grouping field, click  (Add Field). To remove a group-by field, click  (Delete Field). |
| Order | <p>Select in what order you want the information to display.</p> <ul style="list-style-type: none"> Ascending (0, 1, 2... or A-Z) Descending (2, 1, 0... or Z-A) |
| Ranking Field Ranking Function | <p>Select a field to order by (Ranking Field) and the type of information you want the report to show (Ranking Function). Logger can group the data by date, number, and character.</p> <p>For example, if you select the query object "Login Errors by User," you can group the data by "User Name", in "Ascending" order, with "Error" as the ranking field, and "Count" as the ranking function.</p> <p>This allows you to see users with the highest number of errors listed at the top of the data group section of the report.</p> |
| Show When | Use this menu if you want information to display when more detailed criteria are met. |


- If you want to include secondary groups, populate the **Then By** fields. For example, if your report uses a query that reports on password changes and includes a "User Name" field, you might want to sub-group the results for each date by "User Name".







Use the  (Add Field) and  (Remove Field) buttons to add or remove **Then By** fields for sub-groups.

The report will generate records organized and grouped in the order you selected.

Tip: Alternatively, you can specify only a sort order (instead of groups). See also, ["Sort" on the next page](#).

Totals

 **Select Totals** 0

| | Field | Function | Level |
|---|----------------------|----------------------|----------------------|
|   | <input type="text"/> | <input type="text"/> | <input type="text"/> |
|   | <input type="text"/> | <input type="text"/> | <input type="text"/> |
|   | <input type="text"/> | <input type="text"/> | <input type="text"/> |

You can specify the summary (total) fields. You can apply a summary on any of the following levels:







- Report
- Page
- Group

To specify summary details:

1. From **Field**, select the field that will be processed to calculate summary information.
2. On the same row, from **Function**, select the summary function.
3. On the same row, from **Level**, select the level at which you want the summary.

Note: If a Total is applied to a field that is not already in the Selected Fields list, that field is automatically added to the Selected Fields list.

Sort

| | | |
|---|---------|----------------------|
|  Sort Order | | 0 |
| | Field | Criteria |
|   | Sort By | <input type="text"/> |
|   | Then By | <input type="text"/> |
|   | Then By | <input type="text"/> |

If you do not want grouped report results (as described in a ["Group" on page 232](#)), but you do expect sorted results, then specify a sort (instead of a grouping).

Note: A report that has a sort order defined can only display up to 100,000 lines.

You can have up to three levels of sorting.

To specify a sort order:

1. In **Field**, select the field on which you want to sort the report.
2. In **Criteria** (in the same row), select the sort criteria.
3. If desired, provide values in the "Then By" rows to specify more sorting criteria.

Highlight

A report can include multiple levels of highlighting for specified fields. Highlighted items can serve as visual alerts on generated reports when specified set conditions are satisfied.

To set up a highlight:

1. In **Highlight**, select the field that should be highlighted. Select **Entire Row** to highlight an entire record.
2. In **Using Style**, select the style to be applied to highlight it.
3. Select **Alert** checkbox to receive a visual alert on report viewer.
4. In **Field**, select the fields to evaluate for highlight (alert).
5. In **Level**, select the level at which the selected field should be evaluated:
 - DETAIL evaluates each row (record)
 - REPORT evaluates at the end of report
 - Respective groups evaluate at the end of each group
 - PAGE evaluates at the end of the page
6. When REPORT or PAGE is selected in Level, select a Function to be applied.
7. Select **Criteria** and specify its **Value**.
Click (Remove Condition) on the left of the criteria entry to delete an entry. Click (Add Condition) to add another entry.

Matrix

You might choose to include a matrix in your report, since it presents a summary of data. Make sure that the appropriate query object is selected (under **Select Display Fields**).



The screenshot shows the 'Create Matrix' interface. At the top is a 'Link Chart' dropdown. Below it are four panels: 'Available Fields' (with a search bar and list), 'Column Fields' (with columns: Field, Group By, Totals, Show When), 'Row Fields' (with columns: Field, Group By, Totals, Show When), and 'Summary Fields' (with columns: Field, Function, Highlight). Navigation buttons (left, right, up, down, and a reset button) are positioned between the panels.



To create a matrix:

1. To place a field in Row or Column, click the field and drag it to the **Row Fields** or **Column Fields** boxes.
2. To place a field as a cell (summary), click the field and drag into the **Summary Fields** box.
3. Select a **Function** from the pull-down menu provided for a field placed in **Summary Fields**.
4. Optionally, for numeric or date fields in columns or rows, specify a **Group By** function in the pull-down menu provided.
5. Optionally, for fields in columns or rows, check the **Totals** checkbox to view a row or column.

Select a field and click padding-right: 0px; to add that field to the matrix as one of the **Column Fields**.

Select a field in Column Fields and click  to remove it from the matrix.

Select a field and click  to add that field to the matrix as one of the **Row Fields**. Select a field in Row Fields and click  to remove it from the matrix.

Select a field and click  to add that field to the matrix as one of the **Summary Fields**. Select a field in Summary Fields and click  to remove it from the matrix.

To move a field up or down, select the field and click  (Move up) or  (Move down), to move the field in the respective direction.

To remove all settings and contents of the current matrix, click **Clear Matrix**.

Chart

You can add charts to your reports. The query object option selected by default is **Use Parent's** but you can also uncheck it and choose a new query from the drop-down menu. You can also apply changes while view the chart simultaneously on the left pane of the report.

Chart Settings

Query Object: ☒ Use Parent's Chart Type: **Bar** Link:

Available Fields

- Event Time
- Device
- Logger
- devGlobalID
- deviceVendor
- deviceProduct
- deviceVersion
- deviceEventClassId
- name
- agentType
- agentZoneResource
- agentZoneURI
- categoryDeviceGroup
- categoryBehavior
- destinationAddress
- destinationHostName

Value Fields (Y-Axes)

| Field | Function | Series Type | Trend | Infographics |
|--------------------|----------|-------------|-------|--------------|
| deviceEventClassId | Count | | | |

Title: Y-Axis Title Stack Type: Normal Base Value: 0 Threshold: ...

Group Fields (X-Axis)

| Field | Group By | Display Field | Pivot | Split |
|--------------|----------|---------------|-------------------------------------|----------------------------------|
| deviceVendor | | | <input type="checkbox"/> | <input checked="" type="radio"/> |
| agentZoneURI | | | <input checked="" type="checkbox"/> | <input type="radio"/> |

Title: X-Axis Title Label Angle: 45

Settings

- ☐ Show Point Labels
- ☒ Show Description
- ☒ Show Legends
- Legend Position: (Default)

Sorting

Sort Order: Split Order

Field:

Order:

Show (N):

Miscellaneous

Description:

Apply **Cancel**

To create a chart, specify values for the following:

| Setting | Description |
|------------|---|
| Title | Title of the chart. |
| Chart Type | Select a chart type from the drop-down list. |
| Link | Choose to link the chart to either report fields or a matrix. |

| Setting | Description |
|------------------|---|
| Available Fields | Available Fields are drawn from the report query. Using the ► button, assign these fields to Value Fields (Y-axes on the chart) or Group Fields. See "Assigning Fields" below. |
| Settings | <ul style="list-style-type: none"> • Show Title: if selected, the chart title displays. • Show Legends: if selected, the chart will show legends for each field. Use the dropdown to select where it needs to be displayed: left, right, top, or bottom. • Show Point Labels: if selected, a label is shown with the number of matches for a value of a field in a chart. • Align: Select an alignment for chart placement. • Level: Select a level from which to draw data for the chart: <ul style="list-style-type: none"> ◦ Report: Data will be plotted with data from entire report ◦ Page: Data will be plotted with data from the page where the chart is located) |
| Sort Order | Select a sort order for the chart. |

Assigning Fields

You can set value and sort fields for a chart.

To Set Value Fields (Y-Axis):

1. Click and drag the Field in **Series (Y-Axis)** box, or use the ► button (Add field) to add the selected field.
2. Select summary function for the field.
3. To select a different chart type, click the button on the right to open a box with chart types. Select the type you need. Follow steps 1 through 3 above for each attribute to be placed as series. To re-position fields, select a field and click ▲ (Move up) or ▼ (Move down) as needed.

Tip: To change the size of the chart labels, the user must set the Axis.maxHeight property in the bar.ict file

To Set Group Fields (X-Axis):

1. Click and drag the field in **Categories (X-Axis)** box, or use the ► button (Add field) to add the selected field.
2. Select the method to group (for Numeric or date type).
You can specify groups in numeric fields. For example, to have groups of 10, specify 10 in Groups box.
You can specify groups in date fields. From the drop-down box select from Day, Week (Sunday to Saturday), Month, Quarter (Jan-Mar, Apr - Jun, Jul - Sep, Oct - Dec), Year.

Tip: To remove fields from Value fields (Y-Axis) or Group Fields (X-Axis), drag them out of the respective box or use the ◀ button (Remove field) on selected fields.

To display one chart per field, go the field line and click **split**.

To remove all settings and contents of the current chart, click **Clear Chart**.

To specify the screen percentage space, use the **Max Height** value.


To establish the maximum number of characters for view in the chart label, use **Max Caracteres** value.

To save a chart as an image:

1. Right-click on the chart and choose the saving format.
2. Click Save.

Map

Your report can include a GIS (Geographic Information System) map based on your data. For a description of these fields, see ["Map Parameters" on the next page](#).

 **Create Map**

Map:

Area Field:

Area Attributes:

Heatmap Properties

Value Field:

Function:

Start Color:

End Color:

Map Parameters

A map includes the following parameters:

Map Parameters

| Parameter | Description and Values |
|----------------------------------|--|
| Map | Select the map name for initial loading of data. For example, if you want to depict a map of US states, then select "USA - Regions". |
| Area Field | This is the value used to group map data. Select an area based on the initial selection of value for Map. |
| Area Attributes | Click an area of the map to see an informational balloon. Set values for the following attributes in the balloon display. <ul style="list-style-type: none">• Prefix: the prefix caption value for the field• Field: the value of the field• Function: the aggregation summary for the field• Suffix: the suffix caption for the field• As Title: if selected, this line appears as a title bar in the balloon. |
| Heatmap Properties - Value Field | Select the value field by which the heatmap is calculated. |
| Function | Select the aggregation summary for the field by which the heatmap is calculated. |
| Start Color | Select a color representing the lowest value of the value field. |
| End Color | Select a color representing the highest value of the value field. All in-between colors will be assigned values automatically by an even distribution. |

Geolocation Lookup

Geographical Information System (GIS) lookup allows the user to search for a particular event based on its geo-location. Thanks to public IPS in source address column, Logger can track an event using GIS lookup.

Creating a GIS lookup connection

1. In **Design > Queries**, select the appropriate connection. **MySQLReportDB** option allows you to create the query, while **LoggerSearchQuery** selects an existent one.
2. Click **Design >Category**, select GIS filter. Click **Result** and then **OK**.
3. Drag the GIS lookup to the diagram and change the connection to **MaxMindLookup**.
4. Select a field in the **lookup fields**.
5. Type the **parameter** on each lookup field. As you type a word in the value field, the options will auto-populate or appear as drop down.
6. Type [/] on the **request path** field to eventually click get patterns so a new window will display in

which you can select the additional columns that will appear in the results page.

7. Click **get patterns** to search for all possible record patterns. Choose an specific field from the list to perform a search.

Specifying the Geographical role

Modify the following property value fields for this process:

- **Caption:** Name the **fields list** during the report design stage.
- **Hyperlink:** Add a link for a web page or cross- reference another report.
- **Group Label:** To create a new group, type the name as appropriate. Otherwise, select an existing group from the drop down list.
- **Hidden:** To make this field unable to be seen during the reporting process, check the correspondent box.
- **Geographic Role:** Select the corresponding geographical roles that are automatically populated:
 - Continent
 - Country
 - State
 - County
 - City
 - Latitude
 - Longitude
- **GIS Format:** Pick between **signed degrees format**, **degrees minutes**, and **degrees only**. This applies for both geographic role: **latitude** and **longitude**.
- **Width:** Define the report width from a range of 1 to 100.
- **Output format:** The format string is used to configure **Date and Number**. To select the format string at run time, select **Apply Locale Default** in the selector dialog.
- **Input format:** This format string decides the prompting format for the field value in **Ad hoc Filter** screen. This is useful when prompting date values in a desired format or to input IP Address format for number values.
- **Align:** Choose between left, right, center to align the values on the report.
- **User Time Zone:** Specify the appropriate time zone.
- **Render As:** If string field references to an image path, select render as image.
- **Width:** Define the image width.
- **Height:** Define the image height.
- **Source Type:** Pick between image path or URL.

Rendering a Map

After you have looked up the geographic fields and assigned roles corresponding to them on the Query Object screen, you can then render maps in Logger. In the results page, click the **+** button and then select **Add a Map**. The map page will be displayed.

The following map types are supported in Smart reports:

1. **Heat Map:** Shows heat/choropleth map on areas and perform business analysis based on color measure.
2. **Bubble Map:** Displays bubbles on geographic locations and perform business analysis based on color and size measures.
3. **Route Map:** Exhibits routes between different geographic locations and perform business analysis based on color and size measures.

Modify the following property value fields for this process:

| Property value fields | Description | Heat Map | Bubble Map | Route Map |
|-----------------------|---|--|--|--|
| Visualization Type | Defines the map type displayed. | Select heat as map type. | Select bubble as map type. | Select route as map type. |
| Map Layer | Defines the map view used. | Choose between standard or satellite map layer. | Choose between standard or satellite map layer. | Choose between standard or satellite map layer. |
| Additional Map Layers | Highlights the geographic data. | Select one from the list: Water Way Land Cover Transportation Building Labels | Select one from the list: Water Way Land Cover Transportation Building Labels | Select one from the list: Water Way Land Cover Transportation Building Labels |
| Source Field Type | Selects the field type for the source field to be plotted on map. | Not applicable. | Not applicable. | Choose either location or latitude-longitude. |
| Map | Specifies the map region. | Select from the list the map region for the heat map to be plotted. | Not applicable. | Not applicable. |
| GIS Field Type | Define the GIS field type to be plotted on map. | Not applicable. | Choose either location or latitude-longitude. | Not applicable. |

| Property value fields | Description | Heat Map | Bubble Map | Route Map |
|--------------------------|---|---|---|--|
| Field | Allows appropriate selection of fields or data grouping based on the query object level previously defined. | Select a field from available list. | Select a field from available list. | Select a field from available list. |
| Destination Field Type | Determines the destination field type to be plotted on map. | Not applicable. | Not applicable. | Choose either location or latitude-longitude. |
| Color Field | Determines the color field used. | Specify the bubble color. | Specify the bubble color. | Specify the route color in the map. |
| Function | Determines the aggregation summary function applied to the value field. | Select summary function. | Select summary function. | Select summary function. |
| Start Color | Depicts the lowest amount of events. | Select the lowest value color. | Select the lowest value color. | Select the lowest value color. |
| End Color | Depicts the highest amount of events. | Select the highest value color. | Select the highest value color. | Select the highest value color. |
| Size Field | Specifies the field to limit the size of the map type. | Select the field to govern the size of the bubble in map. | Select the field to govern the size of the bubble in map. | Select the field to govern the size of the route in map. |
| Area attributes | Assists in the content design displayed in the map. | Open the attributes dialog. | Open the attributes dialog. | Open the attributes dialog. |
| Area Attributes Prefix | Shows a prefix value for the field. | Type as appropriate. | Type as appropriate. | Type as appropriate. |
| Area Attributes Field | Displays a list value. | Select field from the list. | Select field from the list. | Select field from the list. |
| Area Attributes Function | Shows a an aggregation summary function applied on the field. | Select a summary function. | Select a summary function. | Select a summary function. |

| Property value fields | Description | Heat Map | Bubble Map | Route Map |
|--------------------------------|--|--|--|--|
| Area Attributes Suffix | Shows a suffix value for the field. | Type as appropriate. | Type as appropriate. | Type as appropriate. |
| Area Attributes As Title | Determines where the attribute line is displayed in the map. | To show attributes on the title bar, check the box. Otherwise, the line will appear on the canvas area of the balloon. | To show attributes on the title bar, check the box. Otherwise, the line will appear on the canvas area of the balloon. | To show attributes on the title bar, check the box. Otherwise, the line will appear on the canvas area of the balloon. |
| Area Attributes Preview | Shows a preview of content formation balloon. | Click in order to see the preview. | Click in order to see the preview. | Click in order to see the preview. |

Building Dashboards

A dashboard displays multiple pieces of information arranged on a single screen, so that it can be viewed and monitored at a glance. A dashboard can display reports as well as web content. It acts as an interface for business analysts and application administrators to analyze their systems in a comprehensive and personalized manner.

Dashboards use widgets, which are display modules that can display supported objects. You first create the widgets, then you can place and display them within the dashboard.

For example:

- You can add one or more reports to a dashboard, and configure reports to auto-refresh on a specified interval (for example, every hour). The dashboard will access the latest published reports results, in this case, every hour.
- If you have also scheduled the reports to run and publish every hour, your dashboard will show current results. This eliminates the need to manually run and view each report once per hour in order to retrieve the same information updates.

See also

- ["Creating a New Smart Dashboard " on page 248](#)
- ["Creating a New Classic Dashboard" on page 1](#)
- ["How do Smart Dashboards differ from Ad hoc Dashboards?" on the next page](#)
- ["Dashboard Migration Tool" on page 249](#)
- ["Dashboard Prerequisites" on page 246](#)
- ["Editing an Existing Dashboard" on page 1](#)

- "What Items Can a Dashboard Include?" on page 247
- "Selecting a Default Dashboard View for the Reports Home Page" on page 1
- "Viewing Dashboards in the Dashboard Viewer" below
- How do Smart Dashboards differ from Ad hoc Dashboards?245
- Viewing Dashboards in the Dashboard Viewer245
- Dashboard Prerequisites246
- What Items Can a Dashboard Include? 247
- Creating a New Smart Dashboard248
- Dashboard Migration Tool249

How do Smart Dashboards differ from Ad hoc Dashboards?

Ad hoc dashboards can display the same report query in multiple forms (using different chart types, for example), but there can only be one query per dashboard.

Smart dashboards support the display of two or more different report queries in the same dashboard.

For example

- A Smart dashboard displays two charts—one showing the Most Common Events, the other the Least Common Events. Each chart uses a different query.
- An Ad hoc dashboard displays two charts, but both use the Most Common Events query to display the information as a bar chart and a scatter chart.

Viewing Dashboards in the Dashboard Viewer

To open one or more dashboards as tabs in the Dashboard Viewer:

1. Click the **Dashboard Preferences** link on top of the Dashboard Viewer page.
2. In the Available Dashboards box, navigate to the dashboard that you want to display in a tab.
3. Click +. The dashboard name is displayed in the **Selected Dashboard** box.
4. Click **Save**.
5. Click the **Dashboard** link in the left panel to display the Dashboard Viewer. The dashboard you selected is displayed.

Note: The set or subset of dashboards shown under **Available Dashboard(s)** is based on your user group status and the selection status of Show All Owners' checkbox. A user with Administrative rights is able to see more or all dashboards than a user with fewer privileges. If you limit the view to only your dashboards, the list will not include dashboards designed by other users.

To access dashboards from all users (designers), select the **Show All Owners** checkbox.
To view only your dashboards, deselect this checkbox.

See also

- ["Creating a New Smart Dashboard " on page 248](#)
- ["Creating a New Classic Dashboard" on page 1](#)
- ["How do Smart Dashboards differ from Ad hoc Dashboards?" on the previous page](#)
- ["Dashboard Prerequisites" below](#)
- ["Dashboard Migration Tool" on page 249](#)
- ["Building Dashboards" on page 244](#)
- ["Editing an Existing Dashboard" on page 1](#)
- ["What Items Can a Dashboard Include?" on the next page](#)
- ["Selecting a Default Dashboard View for the Reports Home Page" on page 1](#)

Dashboard Prerequisites

Dashboards are built from widgets created from published reports, which are generated by running an existing report, or creating a new one. You must follow these high-level steps to create the objects that populate your dashboard.

High-level steps to create a dashboard

The process for configuring dashboards consists of these tasks:

1. Run a report (modify an existing one, or create a new one).
2. Add charts and modifications to the report.
3. Publish the report.
4. Create a new widget from that report.
5. Create a new dashboard.

Note: Users can only create private dashboards.

From the Smart Dashboard designer (Design > Dashboards):

- a. Optionally, repeat steps 1-4 (above) to create additional dashboard widgets.
- b. Click **Design > Dashboards**. A blank dashboard displays.
- c. Use the Elements menu to drag and drop your widgets and other dashboard objects, to the dashboard.

From the Ad hoc Dashboard designer (Classic > Dashboards):

- a. Click **Classic > Dashboards**. The Ad hoc Dashboard designer displays.
- b. Create one widget for every report or web link you want to display on the dashboard.
- c. Add the widgets to the dashboard.
- d. Optionally, you can configure the dashboard to display as a tab in the Dashboard Viewer. See ["Viewing Dashboards in the Dashboard Viewer" on page 245](#) for details.

See also

- ["Creating a New Smart Dashboard " on the next page](#)
- ["Creating a New Classic Dashboard" on page 1](#)
- ["How do Smart Dashboards differ from Ad hoc Dashboards?" on page 245](#)
- ["Dashboard Migration Tool" on page 249](#)
- ["Building Dashboards" on page 244](#)
- ["Editing an Existing Dashboard" on page 1](#)
- ["Building Dashboards" on page 244](#)
- ["What Items Can a Dashboard Include?" below](#)
- ["Selecting a Default Dashboard View for the Reports Home Page" on page 1](#)
- ["Viewing Dashboards in the Dashboard Viewer" on page 245](#)

What Items Can a Dashboard Include?

The following information is available for placement on a dashboard. However, each report or Web Link must be placed inside a widget and the widget in turn is placed into the dashboard. See ["Widgets" on page 1](#).

A dashboard can contain one or more widgets containing any of the following:

- **Published Reports:** The dashboard will show the latest published version of the report. See ["Publishing a Report" on page 202](#).

Note: Reports must be published in order for the report data to be accessible to users on the Dashboard View. If no published results are available for a report on a dashboard, the Dashboard View will display a message indicating this. When the report is published, a refresh of the Dashboard view will display the report.

- **External URL:** The dashboard will display any external URLs that allow you to link to them. Permission is through its HTTP Header Field X-Frame-Options setup. For example, you can add **www.bing.com** as your URL, but you cannot add **www.google.com**.

- **Rich Text:** You can explain or annotate your dashboard with a Rich Text box, that can contain formatted text, graphics, and other objects.

See also

- ["Creating a New Smart Dashboard " below](#)
- ["Creating a New Classic Dashboard" on page 1](#)
- ["How do Smart Dashboards differ from Ad hoc Dashboards?" on page 245](#)
- ["Dashboard Prerequisites" on page 246](#)
- ["Dashboard Migration Tool" on the next page](#)
- ["Building Dashboards" on page 244](#)
- ["Editing an Existing Dashboard" on page 1](#)
- ["Deleting a Dashboard" on page 1](#)
- ["Selecting a Default Dashboard View for the Reports Home Page" on page 1](#)
- ["Viewing Dashboards in the Dashboard Viewer" on page 245](#)



Creating a New Smart Dashboard


Pre- requisites:

Creating a Smart Dashboard requires an existing published report.



- For information on how to create a report, see ["Creating a New Smart Report" on page 218](#).
- For information on how to publish a report, see ["Publishing a Report" on page 202](#)

Procedure

1. From the Design section of the Reports menu, click **Dashboards**.
2. Enable the  **Edit Mode** option and click **Elements**
3. Locate your report on the dashboard elements menu and drag and drop it to the center of the screen. Logger adds the widgets.
4. Click **Save**.
5. To add slide shows, rich text editors, external URLs and categories, drag and drop them from the menu on the right. The widget menu can be displayed by clicking the  on the upper right corner.



- From External URL settings you can change the name of the URL, set the refreshing time and add a description.
- From rich text settings you can change the name of the widget, enter text, edit the format and insert images or tables.
- From report settings you can name your widget, change the report you want to use, select a job, set the refreshing time, add a description, and change viewer toolbar options and instance navigation.
- From slideshow settings you can modify the refreshing time.

6. To edit a Smart Dashboard, enable the  **Edit Mode** option.
7. To delete a Smart Dashboard, click **Remove** from the three dot  menu.
8. To add a new Smart Dashboard click **Add New Dashboard**.

Dashboard Migration Tool

Classic > Dashboard > Classic Designer page is no longer supported by Logger 7.0 causing the user to no longer create or edit classic dashboards. Instead, a message is displayed confirming this information. A dashboard page will store the 6.7.1 dashboard data thanks to one time execution of the Migration Tool available for users when upgrading from 6.7.1 to 7.0. In **Reports > Explorer > Root > Converted Classic Dashboard**, the user can look for saved dashboards in a private scope unlike the widgets which will be available to the public.

Designing Queries, Parameters, and Templates

You can create and modify report objects like queries, parameters, parameter value groups, and templates using familiar Logger Design tools.

- [Queries](#)250
- [Parameters](#)273
- [Parameter Value Groups](#)281
- [Template Styles](#)284

Queries

Query objects (which comprise queries bundled with additional metadata) are used as the basis for designing reports. Logger Reporting provides a set of pre-built queries, which are used as the basis for the System-defined Reports and Solutions Reports to address common security use cases.

You can browse or select query objects in Explorer. See ["Reports Explorer" on page 165](#). You can use a provided query object as is, as the basis for your own reports, or design new query objects on the Query Object List page. You can use existing query objects as a starting point for new ones.

Note: Some queries may require parameters. We recommend first designing all needed parameter objects before creating the query object that will use those parameter objects.

For information on developing parameter objects, see ["Parameters" on page 273](#).

For instructions on how to view a list of the default search fields, see ["Default Fields" on page 333](#). For information about custom schema fields added to the default schema, see ["Adding Fields to the Schema" on page 431](#).

Reports that directly invoke SQL queries can use the standard insubnet SQL function as follows:

insubnet("subnet string", address_column)

Caution: Modifications to reports and other ArcSight-defined content may be overwritten without warning when the content is upgraded. It is not good practice to modify ArcSight-defined content directly.

Make modifications to a copy of any ArcSight-defined content as a general practice, and subsequent upgrades will not affect the modifications.

This topic explains how to design new query objects (either from scratch or based on existing ones).

How Search and Report Queries Differ

This topic applies both to Classic Search and Search page

Even though a search and a report query both perform the same function (finding events that match specific conditions) the two queries are distinct in these ways:

- You use Logger's Query Object Editor to create a report query. See ["Queries" on the previous page](#).

Tip: Report queries and field name queries can use indexed fields to expedite the underlying search.

- You use the Logger's Search UI to create a search query. The query can be specified using plain English keywords, field names, or regular expressions. See ["Searching for Events" on page 108](#).


Overview of Query Design Elements

To create a new query object, you need to specify a query name, define a data transformation, and save it. The data source for Logger Report queries is always the Logger databases, so there is no need to specify this as part of the query object.

Optionally, you can specify formulas, set field properties, define transformations, define formatting, define field groups, provide hyperlinking, define lookup values, and build mandatory filtering into the query.

Working with Queries

To search for an existing query by name or other criterion:


1. In the Reports menu, under Design, click **Queries**.
2. On the toolbar, click **Open**.
3. Click **Search** .
4. In the criteria dialog, select the criteria for your search.
5. Click **Search**. All queries matching your criteria are returned.

Creating a Copy of an Existing Query

To use an existing query object as the basis for a new one:

1. From the **Explorer**, click on a category and select the name of the query that you want to copy from the query list.
2. Right-click to expand the context menu. See ["Explorer Options and Context Menus" on page 169](#).
3. Click **Copy Query Object**.

Explorer



4. In the list of categories, right-click the category name under which you want to place the copied query, and select **Paste**.

A temporary version of the new query object is created with the same contents as the original and the same name pre-fixed with "Copy of."

Creating an IPv6 Search Query for Reports

This topic applies only to Classic Search page

To create a search query for IPv6 addresses:

1. Create a query object:
 - a. From the Reports Design menu, click **Queries**. The Query Object Editor displays.
 - b. From the Properties tab > click **Design** in the SQL section. The SQL Designer displays.
 - c. From the **Edit** tab, enter a query which includes the list of fields.

An example query could be similar to the following:

```
select arc_deviceVendor, arc_agentAddress, arc_sourceAddress, arc_
destinationAddress FROM events
```

- d. Click **OK**. The fields display in the SQL section of the Query Object Editor.

2. Define each field as an IPv6 field. Refer to the following image for reference:
 - a. Click the **Format** icon. The Properties tab now displays the query fields.
 - b. From the **Fields** list, select a field.
 - c. Click the three dot icon next to **OutputFormat**.
 - d. In the Data Format pop-up, select **Network Id**, then **IP Address (IPv6)**.
 - e. Click **OK** to dismiss the pop-up.
3. When you are finished defining each of the IPv6 fields, enter a name for the query object and save the query.

Modifying a Query Object

Use the Query Object editor to modify existing queries.

Tip: We recommend that you not modify queries provided with Logger or add-on Solution packs. If you want to use a supplied query as a starting point for your own queries, copy them and edit the copies, as described in ["Creating a Copy of an Existing Query" on page 251](#).

To modify an existing query:

1. In the **Query Explorer**, click the category in the Query Objects column where you have stored the query and click the **Edit Query Details** button.
2. Edit the query as needed (see ["Working with Queries" on page 251](#)) and click **Save**.

Deleting a Query Object

You can remove custom queries, but not supplied queries provided with Logger or add-on Solution packs.

To remove a query:

In the **Query Explorer**, click the category in the Query Objects column where you have stored the query and click the **Delete** button.

Creating Reports from Filters and Saved Searches.

This topic applies only to Classic Search page

About

Users can create and save reports based on existing Logger filters and saved searches.

Procedure

From **Analyze > Classic Search**

1. Enter a search query
2. Choose or customize the fieldset and the time range from the drop-downs.
3. Click the **Save** icon.
4. Mark the Create Report checkbox and click **Save**.
5. A new category called **DefaultLoggerSearchReports** is created the first time you save a Logger search report.

When creating a report from **Analyze > Classic Search >**, users can uncheck the **Local Only** option (if available) and save it as a Logger peer search report.

If the user checks **Local Only** and generates the search, the report saves that option. Eventually, before the report execution, the user can load it and modify it.

Note: Report names should not contain characters different from: alphabet letters, numbers, dot, dash, @, space and underscore.

5. Double-click your report from **Reports > Explorer > Default Logger Search Reports**.
6. Select parameters and click **Apply**. For more information about parameters, see ["Parameters" on page 273](#).

Parameters can be modified for the execution.

The start date and end date offset values are loaded in Logger search reports based on saved searches.

The **Local Only** check is loaded with the value selected from a Logger search report created from the Logger search page.

Note: When a Logger Search report is executed, duplicate column names that comes from source are excluded in the customer report outcome.

Filter Data

Select Parameters

Adhoc Filters

Additional Filters

Start ☒ Dynamic

End ☒ Dynamic

Scan Limit

☒ Local Only

Click on the boxes to display available options

| Device Groups | Storage Groups |
|--|---|
| <input type="text" value="Select some Device Groups"/> | <input type="text" value="Select some Storage Groups"/> |
| Devices | Peers (To include peers, uncheck Local Only) |
| <input type="text" value="Select some Devices"/> | <input type="text" value="Select some Peers"/> |

Apply





Cancel







Create a New Query from Smart Designer

Create a new query using the Smart report designer:

- Click **New Report** from the Design section of the Reports menu. The Smart View design page opens in a new tab.
- Click **Create Query Object...** in the lower-right corner. The Query Object Design Editor opens (from Smart View).



- Select a query object, or elect to start a query from scratch. The default name is **QueryObject**. See ["Queries" on page 250](#).
- Configure the query object step information. See ["Steps" on page 258](#).
 - Click  to configure the Data Source step. See ["Data Source Step" on page 259](#).
 - Click  to configure the Join step. See ["Join Step" on page 261](#).
 - Click  to configure the Union step. See ["Union Step" on page 261](#).
 - Click  to configure the Filter step. See ["Filter Step" on page 262](#).

- e. Click  to configure the Sort step. See ["Sort Step" on page 262](#).
 - f. Click  to configure the Formula Fields step. See ["Formula Fields Step" on page 262](#).
 - g. Click  to configure the Dynamic Fields step. See ["Dynamic Fields Step" on page 263](#).
 - h. Click  to configure the External Task step. See ["External Task Step" on page 263](#).
 - i. Click  to configure the GIS Lookup. See ["Geolocation Lookup" on page 240](#).
 - j. Click  to configure the Format step. See ["Format Step" on page 264](#).
5. Click the **Parameter** tab to configure parameters for the query. See ["Parameters" on page 273](#).
 6. Optionally, click the **Parameter Value Groups** tab to configure parameter values for the query. See ["Parameter Value Groups" on page 281](#).
 7. **Save** the query, as necessary.
 8. When you are satisfied with your new query, click **Apply and Close**, in the upper-right.

Designing a New Query

About

A query object represents a data transformation, which comprises a set of steps (elements) to produce the final output. A step can be a data source, a sort, a filter, an output, or other element. You design a query interactively using the Query Object Editor.

Procedure

1. From the Design section of the Reports menu, click **Queries**.

The Query Object Editor opens.

The Query Object Editor is shown here. Highlighted are the **Steps** list and the **Transformation** workspace.

To create a transformation, you drag query elements (steps) from the **Steps** list to the **Transformation** workspace, linking them in the sequence in which they will be evaluated. Then, you specify properties for each Step.

Working with Steps

Here are some of the ways you can use Steps.

Add a Step to a query

1. Drag it from the list to the **Transformation** workspace.

Specify properties for a Step

1. Select the Step.
2. Click the **Properties** tab.
3. Enter values for the Step. See ["Steps" on the next page](#).

See the results of a Step after you've added it

1. Click the **Results** tab.

Link Steps to other Steps

1. In the **Transformation** workspace, select the Step.
2. Holding your mouse button down, drag and draw an arrow (link) to the linked Step.



3. To add a Step between two linked steps, drag and drop the step on the link.

Rename a Step

1. Right-click the Step, and choose **Rename Step** from the context menu.
2. Enter a new name for the Step.

Delete a link or a Step

1. Right-click the item, then choose **Delete Link** or **Delete Step**.

The Query Design Process

You design a query visually in the **Transformation** workspace.


To design a query:

1. In the navigation menu, under **Design**, click **Queries**. The Query Object Editor opens.
2. In **Name** field, specify a unique name for this query object.
3. In the **Transformation** workspace, drag and drop the required steps for the query from the **Steps** menu into the desired sequence. (By default, the **Transformation** window already includes a Data

Source and Format step.)

For example, to add a sort to the transformation, drag a Sort element from the **Step** list to the Transformation field and drop it on a link.

Then, in the **Properties** tab, select a field to sort by.



4. Optionally, in the toolbar click **Advanced**, then set any advanced properties for the query object.
5. Click **Save**.

Note: A blank (empty) query object is displayed when this page is opened, and the **Add New** button on the toolbar is disabled until the blank query object is saved. After saving, you can add a new query object by clicking **Add New**.

Steps

A **step** is an element of a transformation, used in the construction of query objects. To use a step, drag it from the **Steps** menu to the **Transformation** window. The behavior of a step depends on the properties you assign to it on the **Properties** tab. You can check the results of a step on the data on the step's **Result** tab.

The following steps are available for use in the Query Object Editor:

Steps

| Step | Description |
|----------------|---|
| Data Source | Brings data into the query object. You must have at least 1 data source. For more information, see "Data Source Step" below . |
| Join | Joins two inputs. For more information, see "Join Step" on page 261 . |
| Union | Appends one input to another. For more information, see "Union Step" on page 261 . |
| Filter | Applies pre-defined filters and sets lookup values. For more information, see "Filter Step" on page 262 . |
| Sort | Sets sorting criteria. For more information, see "Sort Step" on page 262 . |
| Formula Fields | Enables addition of calculated fields populated at runtime. For more information, see "Formula Fields Step" on page 262 . |
| Dynamic Fields | Add or remove fields to the query object at runtime. For more information, see "Dynamic Fields Step" on page 263 . |
| External Task | Call standard and custom 3rd party procedures. For more information, see "External Task Step" on page 263 . |
| Format | Lists all fields provided by the query object. Generally, the format step is the last one in the transformation workflow. For more information, see "Format Step" on page 264 . |

Data Source Step

A Data Source Step brings data into the query object from the Logger database or an existing query object. A query can have multiple Data Source Steps.

Properties

Result

Fields

ABC arc_deviceVendor

New Source

Existing QO

(Root)

Connection:

MySQLReportDB

SQL

Design

select arc_deviceVendor from events where lower(arc_deviceVendor) = 'arcsight'

Sorted

Field Properties

Data Type:

CHAR

Data Format:

Length:

100

Scale:

0

Locale:

Sort Priority:

Sort Criteria:

Qualified Name:

A data source step has the following properties:

Data Source Step Properties

| Property | Description |
|----------------------------|--|
| New Source/ Existing QO | Choose whether to use the Logger database or existing Query Object. |
| Connection | <p>Select either <i>parent</i> or the name of a connection.</p> <ul style="list-style-type: none"> • Parent: data is fetched from the connection specified at the Query Object level, or falls back to the default connection configured for the user. • Connection name: data is fetched only from the specified connection. |
| SQL | <p>A complete SQL statement designed with the SQL Designer. Only visible if the Logger database is the data source.</p> <p>The SQL Designer enables you to design SQL statements by dragging and dropping tables (on the Design tab) or by typing the complete SQL (Edit tab).</p> <p>When using the Query Editor, be sure to use the appropriate SQL syntax for your data type. For example, to call a string data type, you must enclose the string with single quotes, as in the query below.</p> <pre>select arc_deviceVendor from events where lower(arc_deviceVendor) = 'arcsight'</pre> |
| Sorted | If selected, the data is sorted. |
| Field Properties | The Field Properties sub-menu (when enabled) allows you to configure the properties of the selected field. See the "Field Properties Sub-menu" below for a description of these properties. |

Field Properties Sub-menu

| Property | Values | Comments |
|--------------------|--------------------------------|---|
| Data Type | CHAR, NUMBER, DATE, BINARY | Select the data type of the incoming data. |
| Data Format | Format String | Specify the format of the incoming data. This is useful only if the Date or IP Address type data are incoming in CHAR fields, but need to be converted to Date and Number types for further use. |
| Database Time Zone | Select Time zone from the list | <p>Specify the time zone in which the incoming date data is stored. This is useful only if date time data needs to be converted to other time zone data based on reporting requirement.</p> <p>For example when incoming GMT data should be converted to another time zone in the report, specify that the incoming data is GMT. The output format is generally specified in the Format Step or in user preferences.</p> |
| Length/Precision | Enter | Enter the length of field for Char data types, and the precision or length of field for the Number data type. |
| Scale | Enter | Enter the Scale or number of digits after the decimal point. |

| Property | Values | Comments |
|----------------|-----------------------|--|
| Locale | Select from menu | Select the language/ country in which the incoming date data is stored. |
| Sort Priority | Number 0- N | If the data is sorted on multiple fields, then specify the sort priority number of this field. Primary sort field should be the lowest number. |
| Sort Criteria | Ascending/ Descending | Specify sort as either ascending or descending order. |
| Qualified Name | Enter | This name helps by providing a field name for SQL clauses such as WHERE and ORDER BY. It can also be used to resolve field name ambiguity when the same field comes from different tables or expressions. |

Join Step

A Join Step joins two inputs. A Join Step has the following properties:

Join Step Properties

| Property | Description |
|-------------------|--|
| Select All Fields | If enabled, all fields from both sources will be available in the output of this step. If deselected, you can select which fields will be available in the output. |
| Join Type | Select from one of the following join types: <ul style="list-style-type: none"> • Inner Join • Left Outer • Right Outer • Full Outer |
| Join Conditions | Forms the Join Key. |

Union Step

A Union Step appends one input to another. A Union Step has the following properties:

Union Step Properties

| Property | Description |
|-----------------------|--|
| Union Type | Select either Sorted or Unsorted. |
| Remove Duplicate Rows | If selected, each row in the result will be distinct. |
| Column | Enter the name of a column. Click to rename the column. Click to add a column Click to delete the column. |

Filter Step

A Filter step will apply pre-defined filters and set lookup values. A Filter step has the following properties:

Filter Step Properties

| Property | Description |
|----------------|---|
| Ad hoc filters | To apply one or more ad hoc filters, under Select Filter Criteria , enter the Field Name, Criteria , and Value . Click + to add more filters or click X to delete one. |
| Lookup Values | If enabled, a list of lookup values is provided to the end user to easily choose values to apply a filter. |
| Mandatory | If enabled, then any reports using this Query Object must apply the filter on the selected field. |
| Hide | If enabled, the field will be hidden from the end user in the list of fields that can be filtered on. |

Sort Step

A Sort step sets sorting criteria. A Sort step has the following properties:

Sort Step Properties

| Property | Description |
|------------------|--|
| Field | Select a field from the list on which to sort. You can add multiple fields for the sort using Sort by and Then by lines. |
| Criteria | Sorting criteria, either ascending or descending order. |
| Case Insensitive | If enabled, then case is ignored for sorting. (ABC would be the same level as abc). |
| Hide | If enabled, the field not be seen by the end user in the list of fields that can be filtered on. |

Formula Fields Step

A Formula Fields step enables you to add calculated fields populated at run time. These calculated fields are generally based on existing fields.

To add a formula field, click **+**. Then specify values for the field as follows:

Formula Fields Properties

| Property | Description |
|-------------|---|
| Name | Name and caption of the field. |
| Return Type | Data type of the formula field (Number, Char, or Date). |

Formula Fields Properties, continued

| Property | Description |
|----------------------|---|
| Length/ Precision | <ul style="list-style-type: none">Length of field for Char data typePrecision or length of field for Number data type. |
| Scale | Scale or number of digits after decimal point. |
| Formula | <p>Formula, using JavaScript syntax. To create a formula, you can use field names and define variables.</p> <ul style="list-style-type: none">A formula can include an if construct as well as nested if and logical operators.To include more than one statement in a formula, use a semicolon (;) to separate them. <p>Example: For a formula field named TotalAmount,</p> <pre>var total ; if (unitprice < 10) {total = unitprice*quantity;} else {total = unitprice;} TotalAmount = total;</pre> |

Dynamic Fields Step

A Dynamic Fields step can add fields to, or remove fields from, a query object at runtime. Dynamic fields can be added by pivoting data from a single data source, or dynamically fetching metadata for field properties.

- **Dynamic Mapping** takes each field from the metadata result set and maps it to Query Object Field Properties. The primary mappings are **Field ID**, **Field Name**, **Caption**, and **Data Type**.
- **Pivoting** converts normalized, name-value paired data into flattened tabular data. The Pivot tab includes these fields.
 - **Pivot Columns:** specifies which column has field ID and which column has value.
 - **Select Grouping:** specifies grouping fields, which when grouped on, the normalized data converts to a flat table.

External Task Step

An external task step enabled you to call standard and custom third-party processes. Logger includes the following pre-configured external tasks:

- **Java Row Processor:** for processing of Java rows
- **R Job:** for R Analytics Server scripts (See the table "[R Job Parameters](#)" on the next page for the properties)
- **Hive Job:** for Hive scripts
- **Pig Job:** for Pig scripts
- **Custom Map Reduce Job:** for custom map reduce scripts

R Job Parameters

| Property | Description |
|---------------|---|
| Server IP | IP address of R server |
| Plot Type | If Format Type is an image format, select a plot type from the drop-down list |
| Format Type | Select a format type |
| Model File | Location of the R model file |
| No. of Images | If Format Type is an image format, enter the number of images in the output |
| Script | R script file name |
| Validate | Click to validate the R job |

Format Step

A Format Step is the last step in the workflow, and lists all fields provided by the Query Object. A Format Step includes these parameters:

Format Step Parameters

| Property | Description |
|--------------------------|---|
| Field | Original name of field. |
| Source | Step in which this field originated. |
| Caption | The end user will see the field by this name. |
| Hyperlink | Drilldown detail or hyperlink URL. |
| Group Label | To assign this field to an existing group, select the group name from the drop-down list. To create a new group, type the new group name. |
| Hidden | If selected, the field will be invisible to users for the reporting process. |
| GIS Enabled | The selected field must contain GIS classification data such as country names, state, or city names. A GIS Enabled field will appear in the selection list for the grouping option in the GIS Mapping dialog and the Area field and the Heat Map Properties > Value fields on the Create Map dialog. For more information, see "Map" on page 239 . |
| Format properties | |
| Width | The default width of this field when dragged onto a report. Valid values 1-100. |
| Output Format | Enter a format string. The field value will be formatted using the format string. Useful for date and number formatting. (If you need to decide the format string at runtime, select Apply Locale Default .) |

Format Step Parameters, continued

| Property | Description |
|----------------|--|
| Align | Field alignment (left, center, right) when assigned to a report. |
| Input Format | Enter a format string. The string determines the prompting format for the value of this field in Ad hoc filters. Useful in prompting date or IP values in the desired format. |
| User Time Zone | Time zone for the display of report data. The Report Server calculates the difference between Database Time Zone and User Time Zone, and does time conversion. To decide time zone at runtime, select <i>SYS_USER_TZ</i> . |

To define a Format Step:

1. From the **Fields** list, select the field for which you want to define an input format. (The selected field is bold.)
2. Select the appropriate format and provide necessary values for that format.

To designate a mandatory filtering field:

From the **Fields** list, select a field you want as a mandatory filtering field.

Click the **Mandatory** checkbox to the right of the Fields list.

Other fields can be selected or deselected using the **Mandatory** checkbox.

Query Object Advanced Properties

Advanced properties at the query object level control the behavior of the query object and reports generated using the query object.

Values specified on the Advanced Properties tab

| Property | Values | Comments |
|-----------------------------|------------------------------------|---|
| Audit Log | (Default)Enable Disable | You can switch audit logging on or off for reports generated using the Query Object, irrespective of global audit logging settings. |
| Run Priority | (Default) Low Medium High | Decides priority in the request queue of the Report Server. |
| Database Connection Timeout | User specified | Over-rides the same property value at connection or global level. |
| Data Source Fetch Size | User specified | Over-rides the same property value at connection or global level. |
| Max Rows | User specified | Maximum row restriction from this query object. Report level Max Rows value can further downsize but cannot up-size this value. |

Values specified on the Advanced Properties tab, continued

| | | |
|-------------------------------|--|--|
| Query Execution | (Default) Synchronous Asynchronous | Synchronous - thread waits after sending database request until data returns Asynchronous - Useful to free rendering thread when database is taking too long to process the data before it starts sending data in. Examples: Heavy sorting at database. Complex procedures processing data before sending data. |
| Restrict to Background | (None) Enable Disable | Enable - Reports using this Query Object shall be allowed by submitting to run in background only. Useful when query takes a long time. Disable - Run and Run in background both available. |
| Restrict to formats | (None) List of available formats | None = Reports using this query object can run in all supported formats. Selected Values = Reports using the query object can run only in the selected formats. For example, a report with millions of rows in the output may be ok only in XLS and raw text formats. |
| Default Memory Usage per Exec | User specified | Overrides the same property at connection or global level. |
| Report Server Chunk Timeout | User specified | Overrides the same property at connection or global level. |
| Sort Area Size per Exec | User specified | Decides memory limitations set for in-memory sorting of rows. Overrides the same property at connection or global level. |
| Sort Threads per Exec | User specified | Decides memory limitations set for in-memory sorting of threads. Overrides the same property at connection or global level. |
| Data Caching | (None) Enable Disable | Enable - Create Cache of result set for this Query Object to re-use for in-view and post-view operations of a report up to specific time. |
| Update Fields at Runtime | (None) Enable Disable | Enable - If database query returns new fields at run time this query object exposes all of them to the user on Ad hoc Wizard or Power Viewer. |

Defining Queries on the Designer

SQL Designer

SQL (Structured Query Language) is an ISO based standard programming language for retrieving and updating information in a database. Logger supports SQL queries, and provides an interactive, SQL Designer in which to define SQL statements

Procedure

To access the **SQL Designer** from the Reports | Queries Page.

1. Select **MySQLReportDB** connection and click **Design** . Entities and attributes for the selected entity are listed on the left side of the SQL Designer. The right side of the SQL Designer provides tabs showing information related to the selected statement.

Note: The Attributes list shows a few attributes that are internal to Logger. They should not be used in queries because the resulting report will not contain expected results. All attributes listed after **arc_sourceZoneResource** are internal, including **arc_eventTime**, **arc_deviceName**, **arc_rowId**, and **arc_others**.

SQL Designer Tabs

| Option | Description |
|---------|--|
| Design | Graphical SQL query designer. Use options on this tab to design relatively simpler queries using drag and drop method. |
| Edit | Shows the SQL statements. A query created on the Design Tab is represented as an SQL statement on this tab. You can also write or paste and SQL directly here. |
| Results | Displays rows received as a result of SQL execution. |

List of Database Objects

The SQL Designer shows the **Default Connection** to the database that provides the database objects list. Logger Reporting provides a single type of object or **entity**, which is an **events** table. When you click **events** (under Entities), event fields (attributes) are shown under **Attributes**.

Note: In a SQL query, the null value is not considered equal or not equal to anything, not even to other nulls. To consider nulls as not equal to a value, the **where** clause must contain the **NULL** condition.

Design Tab

You can design simple SQL queries on the **Design** tab using “drag-and-drop”.

To create a SQL query statement using the Design tab:

1. Under **Entities** on the left side of the editor, click **events** to select the “events” entity.
The list of event attributes is shown under Attributes.
2. Click and drag event attributes from the **Attributes** list on left side of the editor to the **Select** box on the right. The associated values are automatically displayed in the **From** clause.

Note: The Attributes list shows a few attributes that are internal to Logger. They should not be used in queries because the resulting report will not contain expected results. All attributes listed after **arc_sourceZoneResource** are internal, including **arc_eventTime**, **arc_deviceName**, **arc_rowId**, and **arc_others**.

3. Repeat these steps to select other attributes from different entities.




Tip: The **events** entity must be selected (under Entities on the top left) in order for the event attributes to show up under **Attributes**. If no attributes are displayed, make sure you have “events” selected in the Entities list on the left side of the SQL Designer.

Select

The Select box shows the attributes selected for a given entity.

Where

The Where area shows the “where” clause for the query.

- To add a row at the top, click  (Insert first condition) in the left-most cell of column header.
- To add a row below the current row, click  (Add a condition) in the row below which you want to add a row for condition. A row is inserted in the row below the respective row.
- To remove a condition, click  (Remove this condition) in the row for the condition you want to remove.
- To specify a where clause, form a condition by selecting **Operand1**, **Operand2** and **Operator**.
- To join conditions, create two conditions, and select a relation in the right-most column of the first condition (of the two being joined).
- To group conditions, specify opening brace and closing brace in the right row.

Group By

In the Group By clause you can provide grouping criteria for the SQL statement. To place an entity in Group By, click the entity in the Entity List and drag it in the box below Group By.

Having

To build a “Having” clause, use the same settings as described in the “Where” clause.

Note: Be sure to include appropriate summary function in “Select” clause so that it can be used in the

“Having” clause.

Order By

In the Order By clause you can provide sorting (ascending/ descending) criteria for the SQL statement. For a report with grouping, the “Order By” clause must have the columns in the same order as the respective sections in the Layout Editor.

Caution: An order-by report query that involves millions of events can fail to run and display the following error messages: **“The server is too busy, try again later”**.

Therefore, Micro Focus Recommends that you follow these best practices:

- Use the ‘scan limit’ parameter to limit the number of events that will be scanned.
- Rewrite the report query to group by name or group by time to reduce the granularity of events scanned.

Edit Tab

When you switch from the Design tab to **Edit** tab, the SQL in the Design tab is constructed and displayed as a complete SQL statement in the Edit tab. You can use the Edit tab to view and write more complex SQL statements that cannot be defined in the Design tab.

SQL Designer: Edit Tab

Relationship of Edit and Design Tabs

The SQL Designer manages the SQL statement being constructed to prevent a complex query (defined in the Edit tab) from being unintentionally overwritten with changes made subsequently on the Design tab.

If you first enter a complex query on the Edit tab, then click back to the Design tab and make changes there, then click the Edit tab again. A dialog prompts whether you want to overwrite the original statement on the Edit tab with the changes you made on the Design tab.

- If you click **OK**, your changes in the **Edit** tab are overwritten, because the SQL in the Design tab will be reconstructed.
- If you click **Cancel**, the SQL in the **Edit** tab remains intact and is used as the final SQL.

The SQL statement as reflected in the Edit tab will be used as the final SQL for compilation.

Result Tab

The **Result** tab shows query results based on the currently-specified SQL statements (shown in the Edit tab). If the SQL uses a parameter, you will be prompted to provide the values to view the query results.


SQL Designer : Result Tab

Logger Search Reports Designer

Logger Supports Logger filters and saved searches.

To access the **Logger Search Reports Designer** from the Reports | Queries Page.

1. Choose the Logger Search Query connection and click **Design**.



☒ New Source ☐ Existing QO (Root)

Connection: **LoggerSearchQuery**

Logger Search Query

Design

☐ Sorted

Field Properties

Data Type: **CHAR** Data Format: ...

Length: **100** Scale: **0** Locale:

Sort Priority: Sort Criteria:

Qualified Name:

Logger Search Reports Tabs

| Option | Description |
|-------------|---|
| Description | Use options on this tab to select the filter or the saved search. |
| Result | Displays rows received as a result of the filter or the saved search execution. |

2. Select the fieldset from the drop-down on the Logger Search Designer.

You may also select either a filter or a saved search for the report.

3. Click **Ok**.

Note: Time range selection is displayed for Saved Searches.

Data Science Engine Step at Query Object Level

Data Science Engine enables the users to perform predictive analysis by allowing adding additional variables and columns to reports for further scrutiny. Query object permits extracting the data from different databases and transform it to either load or use in reporting.

Caution: By default, Data Science is disabled (set as false). To enable this functionality, go to **logger.properties** file and set the value **reports.data.science.component.enable=true** in logger properties. Restart the ReportEngine and Web processes afterwards.

Adding Data Science Engine step

Data Science Engine step functionality behaves similar to other transformation steps within reports. It needs to be dragged and dropped (with a maximum of 2 inputs) from the left pane in the transformation area and create necessary links. Data Science Engine step can be incorporated before or after adding any other transformation step.

This functionality can be used not only for training but also in prediction data using both independent (fields that estimate the value of dependent values) and dependent variables when the following conditions are met:

- Specific data for training and prediction has been added. Otherwise, the same data will be used for the 2 processes.
- Training data is added if no trained model is available in the script.

Adding Data Science Engine script

User will write the data science scripts using Python. Logger suggests create these scripts similarly at a query object level to display training and prediction options only at the time of report execution.

Make sure you are familiar with these guidelines before writing and adding a data science engine script:

- Scripts must contain both training and prediction sections. Start the section using **#** followed by **<%name.section%>**.
- First line of the training and prediction script is intended to read the CSV while the last line is for writing.
- Previous step data should be referred as **StepName.data**.
- The created model is saved as **myModel1** by default. Do not rename the model as it is referenced while communicating with Python environment.

- Provide a training script, otherwise it will be assumed that a trained model is used.
- If the training model is used, a prediction script needs to be added. Once written and verified, click **ok** or **save**.

Running Reports

In this stage, the user can choose between prediction only or training and prediction analysis. To perform retraining based on results prior the actual prediction, select training and prediction option. Otherwise, use prediction only.

Tip: To save your choices as default, check the save values next run box.

Predictive Analysis

Predictive Analytics helps you to input your script directly at report level and bring out predictions on your data. Adding script at report level is most useful when your predictions are not forming new variables or columns in your data reports.

Creating predictive analysis

1. Turn on the edit mode to view option for Predictive Analytics. You can perform predictive analysis in Smart View Reports.
2. Modify the following property value fields for this process:
 - **Fields:** Choose the fields showing in the report. Clicking any field will give you the ability to write Data Science script for that field.
 - **Data Science Connection:** Pick the Data Science Engine needed to generate predictions.
 - **Prediction Script:** Write the script for the field(s) you choose.
 - **Prediction Data Source:** Provide the data and set the independent variables to create predictions on dependent variables.
 - **Auto:** Provide the prediction data point in numeric value.
 - **Data Source:** Specify the query object containing the pre-decided values. Add its correspondent script.
3. Once script is added, check for no errors. Click **Ok**.

What if Analysis

What-if analysis enables the user to perform predictions of different fields based on various business scenarios. This will help you to take planned future actions and make operational decisions based on the predictions you derive.

Creating what-if analysis

1. Select **Filters** option and select **What-if tab**.
2. Use the slider to define the percentage values of different independent variables or manually set them. The values can be positive or negative, which implies the quantity you are increasing or decreasing from the current value.
3. **Click Ok.**
4. Download the report in PDF format.

Parameters

Reports retrieve data by running pre-built query objects. If a query needs a value at report run time, it uses built-in, run-time parameters. At report run time, the user is prompted to provide values for run-time parameters as a prerequisite for running the report. The report is then generated based on the user-provided values for those parameters.

Parameters are stored on the server, and therefore can be used in one or more report and query objects.

Note: We recommend first designing all needed parameter objects before creating the query object that will use those parameter objects. (For information on creating queries, see ["Queries" on page 250](#).)

See also

- ["Creating New Parameters" on page 275](#)
- ["Parameter Object Editor" on the next page](#)
- ["Parameter Properties" on page 306](#)
- ["Parameter Value Groups" on page 281](#)
- ["Placing a System-defined Query or Parameter into a Category" on page 293](#)
- ["Configuring Parameter Value Groups" on page 281](#)
- ["Modifying a Parameter" on page 280](#)
- ["Deleting a Parameter" on page 280](#)

Parameter Properties

When you click on a parameter in the navigation tree of the iPackager page, the following property page opens. The **Parameter Object** box is pre-populated with the parameter object name that is found on the report server. You can change the name of the parameter object. If you change the name here, the parameter object is packaged with the new name, but its original name on the report server will not change.

See also

- ["Parameters" above](#)
- ["Creating New Parameters" on page 275](#)

- ["Parameter Object Editor" below](#)
- ["Parameter Value Groups" on page 281](#)
- ["Placing a System-defined Query or Parameter into a Category" on page 293](#)
- ["Configuring Parameter Value Groups" on page 281](#)
- ["Modifying a Parameter" on page 280](#)
- ["Deleting a Parameter" on page 280](#)

Parameter Object Editor

To view and work with Logger Report parameters, under **Design**, click **Parameters** in the Reports left pane or click **Explorer** and click on a category, select a parameter, and click the **Edit Parameter Details** button to open the Parameter Object Editor.

Parameter Object Editor

Name

ParameterObject

Caption

Data Type

CHAR

Size

30

Usage Format

Prompt Format

Default Prompt Value

☐ Use Input Source

☐ Mandatory

☒ Visible

☒ Enable

☐ Data Restriction

☐ Multi Select

☐ Search

☐ Tree View

☐ Link

Valid Character(s)

Allowed Characters

Range(s)

From

To

Input Type

☒ EditText

☐ Dropdown

☐ Option

☐ Slider

Dropdown Source

Values

☐ Pre Defined

☒ Dynamic

Source Statement

Verify

Display Column

Value Column

Display Parameter Name

☐

☐ Validations

☐ Range

Advanced

Invalid Character(s)

Invalid Characters

Range(s)

From

To

See also

- ["Parameters" on the previous page](#)
- ["Creating New Parameters" on the next page](#)
- ["Parameter Properties" on page 306](#)
- ["Parameter Value Groups" on page 281](#)
- ["Placing a System-defined Query or Parameter into a Category" on page 293](#)

- ["Configuring Parameter Value Groups" on page 281](#)
- ["Modifying a Parameter" on page 280](#)
- ["Deleting a Parameter" on page 280](#)

Creating New Parameters

To create a new parameter:

1. In the Parameter Object Editor, click the **Add New** button located at the top left.
2. Specify values for the new parameter. (Details are given in the topics below.)

Caution: The parameter name must be unique amongst all parameters in the system.

3. After providing all required values, click **Save**.
4. The parameter is added to the Parameters list.

Note: A blank (empty) parameter object is displayed when this page is opened, and the **Add New** button on the toolbar is disabled until the blank parameter object is saved. After saving, you can add a new parameter object by clicking **Add New**.

See also

- ["Parameters" on page 273](#)
- ["Parameter Object Editor" on the previous page](#)
- ["Parameter Properties" on page 306](#)
- ["Parameter Value Groups" on page 281](#)
- ["Placing a System-defined Query or Parameter into a Category" on page 293](#)
- ["Configuring Parameter Value Groups" on page 281](#)
- ["Modifying a Parameter" on page 280](#)
- ["Deleting a Parameter" on page 280](#)


Setting Parameter Name, Data Type, and Default Values

Specify the parameter unique ID, display name, data type, size, format, and default value as described in the table below.


Parameter Name, Data Type, and Default Values

| Option | Description |
|--------|--|
| Name | Provide a name to uniquely identify this parameter. This name should be unique amongst all parameters in the system. |
| Prompt | Parameter name displayed to the user at report run time. |

Parameter Name, Data Type, and Default Values, continued

| Option | Description |
|---------------|---|
| Data Type | <p>Specify type of value the user must provide at report run time:</p> <ul style="list-style-type: none"> • CHAR - Value may include alphabetical characters, numbers and special characters. • NUMBER - Value may include digits and decimal points • DATE - A date or part of a date, like day, month, or year • BOOLEAN (For more information, see "Setting up Boolean Parameters" on page 278.) |
| Size | <p>Specify number of characters or digits this parameter should accept.</p> <div> <p>Note: This is only applicable to CHAR and NUMBER data types, not for BOOLEAN or DATE parameters.</p> </div> |
| Format | <p>Select the appropriate format in which user should provide value for this parameter. Click  to open a Data Format dialog box. Based on the format you have selected, a format string is displayed in the entry box.</p> |
| Default Value | <p>Specify a default value that is appropriate in most cases to provide for this parameter at report run time.</p> <p>The default value will be automatically selected at report run time. The user can change the default value, if needed. If the user does not change it, the report will run using the default value you specify here for this parameter.</p> |

Default Value for Date Type Parameter

For a date type parameter, the **Default Value** field provides a pull-down menu and a calendar. Click the calendar icon  to provide an explicit date, or select one of these dynamic variable values from the pull-down menu:

- **CURRENT_DATE**
- **MONTH_START_DATE**
- **YEAR_START_DATE**

You can also set a default date that is *relative* to any of the above three dynamic variable dates.

For example, to set a default date as 3 days after **CURRENT_DATE**, specify **CURRENT_DATE + 3**.

To set a default date as 5 days before **MONTH_START_DATE**, specify **MONTH_START_DATE - 5**.

To provide a value that is relative to a dynamic variable, select one of the dynamic variables, then type a suffix to it in the Default Value field by adding **+** or **-** and the number.

At report run time, a parameter with a **Date** format will display with the default date set here.

Defining Input Type

The parameter **input type** describes the style of interface provided to users at report run time in which to enter a value for this parameter. Choose from **Text Box**, **Combo**, or **Option** as described below.

Note: In the Reports Designer, changing the parameter type TextBox to another type causes an error. If you need to change the parameter type to TextBox, do not edit an existing parameter, delete that parameter and add a new one.

Input Type

| Option | Description |
|----------|---|
| Text Box | Select Text Box input type if you want the user to type the value for the parameter. |
| Combo | Select Combo if you want the user to select one value or multiple values from a pull-down menu. Select the Multi Select checkbox so that user can select multiple values from the box. See "Setting Multiple Default Values" on page 279 to configure other settings for this option. |
| Option | Select Option if you want the user to select values represented as options. Select the Multi Select checkbox to have value options in the form of checkboxes. Keep the Multi Select checkbox deselected to have options in the form of radio buttons. |

Setting Multiple Default Values

If you selected **Combo** Input Type (see ["Defining Input Type" above](#)), you need to define the following settings in the Parameter editor:

- Maximum Selectable Values: Specify the maximum number of values that can be selected or provided for a parameter.
- Enclosed By: Specify the character to use to enclose the set of values. This will depend on the database.
- Separator: Specify the character to use to separate the two values. This will depend on the database.
- Select Default Values: Specify the number of default values to display at report run time. You can choose from the following:
 - a. Selected: Only values for the selected parameters are displayed.
 - b. All: Values for all parameters are displayed.
 - c. None: No default values are defined.

Setting up Boolean Parameters

Parameters that have a Boolean data type are represented to the user as checkboxes (the input type) and have only two states:

- Checked (chosen at run time)
- Unchecked (deselected at run time)

To set up a BOOLEAN parameter:

1. Select **Data Type** as **BOOLEAN**.
2. In the **Values** area, select an option:
 - a. **Checked**: Specify the value to be passed when the user selects this option at run time.
 - b. **Unchecked**: Specify the value to be passed when the user does not select this option at run time.

Setting Various Run Time Behaviors

You can specify a variety of options on how the parameter will look and act at report run time. These options are generally related to the input type, and further define acceptable user input values, whether the parameter will be displayed or hidden, which values can be searched, and so forth.


Parameter Options

| Option | Description |
|--------------------------|---|
| Mandatory | Select this checkbox if you want to require the user to specify a value for this parameter at report run time. |
| Visible | Select this checkbox if you want the parameter to be displayed on the input form at report run time. Keep this deselected if the value for this parameter is populated from another report or if you want the parameter to use the default value in all cases. |
| Restrict to List | This setting is applicable for parameters with Input Type of Combo . select the Restrict to List checkbox here to force user input of a parameter value from the available run-time options only. If Restrict to List is <i>not selected</i> in the parameter definition you create here, the user can specify a value or can select values from available options. |
| Pass Values Using Tables | This setting is applicable for Multi Select . Select this checkbox when you want to pass parameter values through a table. This is done especially when the number of values that can be passed (total number of bytes of selected values) as part of the SQL is more than allowed. |
| Enable | |
| Forced | Select this checkbox if you want to restrict parameter values to a pre-specified list of values. |

Setting the Data Source List

Specify values for **Check box**, **Combo**, and **Option** input type. Values can be predefined only.

To Set Predefined Values:

1. In the **Display Name** field, specify the value to be displayed to the user at run time.
2. In the **Value** field, specify the value to pass as a filter.
3. Click  (**Add**) to add the display name to the list.

(To delete an option from the list, select the value and click .)

4. Repeat these steps for each option.
5. Select the **Display Parameter Name** checkbox if you want to provide the user with the option of adding the parameter as a control on a report.

Once selected, the **Display Parameter Name** field is auto-filled with the parameter display name that can be selected for use on a report. The name displayed on the report is the one specified in the **Prompt** field.

Tip: The **Display Parameter Name** settings have no effect when the Parameter Object is used in an ad hoc report.

Setting Multiple Default Values

If you selected **Combo** Input Type (see ["Defining Input Type" on page 277](#)), you need to define the following settings in the Parameter editor:

- **Maximum Selectable Values:** Specify the maximum number of values that can be selected or provided for a parameter.
- **Enclosed By:** Specify the character to use to enclose the set of values. This will depend on the database.
- **Separator:** Specify the character to use to separate the two values. This will depend on the database.
- **Select Default Values:** Specify the number of default values to display at report run time. You can choose from the following:
 - a. **Selected:** Only values for the selected parameters are displayed.
 - b. **All:** Values for all parameters are displayed.
 - c. **None:** No default values are defined.

Modifying a Parameter

To modify a parameter:

1. On the **Reports** right panel menu, click **Parameter Explorer** to display the Parameter Object list.
2. Browse to the parameter you want to modify.
3. In the **Actions** menu, click **Edit Parameter Details**.
4. Edit the parameter as needed (using the settings described in ["Creating New Parameters" on page 275](#)) and click **Save**.

See also

- ["Parameters" on page 273](#)
- ["Creating New Parameters" on page 275](#)
- ["Parameter Object Editor" on page 274](#)
- ["Parameter Properties" on page 306](#)
- ["Parameter Value Groups" on the next page](#)
- ["Placing a System-defined Query or Parameter into a Category" on page 293](#)
- ["Configuring Parameter Value Groups" on the next page](#)
- ["Deleting a Parameter" below](#)

Note: Only custom parameters can be modified, not supplied parameters, since supplied parameters are required for use in system Reports and Solution pack add-ons.

Deleting a Parameter

To delete a parameter:

1. On the **Reports** left panel, click **Parameter Explorer** to display the Parameters Object list.
2. Browse to the parameter you want to modify.
3. In the **Actions** menu, click **Delete**.
4. Click **Yes** to confirm deletion.

Note: Only custom parameters can be removed, not supplied parameters, since supplied parameters are required for use in foundation Reports and Solution pack add-ons.

See also

- ["Parameters" on page 273](#)
- ["Creating New Parameters" on page 275](#)
- ["Parameter Object Editor" on page 274](#)

- ["Parameter Properties" on page 306](#)
- ["Parameter Value Groups" below](#)
- ["Placing a System-defined Query or Parameter into a Category" on page 293](#)
- ["Configuring Parameter Value Groups" below](#)
- ["Modifying a Parameter" on the previous page](#)

Parameter Value Groups

Some reports require multiple run-time values, like a country list, for example. Selecting a handful of country name from a long list can be difficult. To address this problem, Administrators can create parameter value groups, that allows a user to select a group that includes multiple parameters.

Examples of parameter value groups:

- Americas (countries in the North American sub-continent)
- Europe (countries in Europe)
- Asia (countries in Asia)
- Africa (countries in Africa).

At run time, when a user selects a group, values belonging to that group will appear as selected. User does not have to manually select each of the countries every time the user runs the report. This saves time, as well as reduces the chance of errors.

See also

- ["Parameters" on page 273](#)
- ["Creating New Parameters" on page 275](#)
- ["Parameter Object Editor" on page 274](#)
- ["Parameter Properties" on page 306](#)
- ["Placing a System-defined Query or Parameter into a Category" on page 293](#)
- ["Configuring Parameter Value Groups" below](#)
- ["Modifying a Parameter" on the previous page](#)
- ["Deleting a Parameter" on the previous page](#)

Configuring Parameter Value Groups

Some reports may require users to provide multiple run-time values that would be easier to select if they were grouped. For example, a report that requires a user to select more than one country name might be a good candidate for parameter value groups. Users might find it difficult to select a few country names from a single, long list of countries.

As an alternative, the query designer could create parameter value groups for the Americas, Europe, Asia, Africa, and so forth. Each parameter value group would contain lists of countries belonging to those continents or areas. At report run time, when the user selects a group, values belonging to the group are pre-selected. Users do not have to manually select countries in parameter groups for every report run. Selections are saved from one report run to the next.

Using parameter value groups as a part of your query design strategy can save users time and reduce error at report run time.

To view and work with Logger Report parameter value groups, under **Design**, click **Parameter Value Groups** on the Reports left panel.



Parameter Value Groups

The following table describes the options on the **Parameter Value Groups** page.




Parameter Value Groups





| Option | Description |
|--------------------------------------|---|
| Name | Lists all the parameter objects. |
| Available Values | Lists available values for the selected parameter. |
| Value Groups | Lists groups created and the values selected within a group. An icon is displayed on the left of a Private group. |
| Show All Owners | If selected, displays groups created by all users. |
| Option buttons: Private Public | Select Private to list the groups you have set for you only. Select Public if you wish to list the groups you have set for everyone. |

To create a group:

1. Click  (Add Group) next to the **Value Groups** box. A group is created and listed under Value Groups with a default name (based on the currently selected parameter in Parameters list).
2. In the Value Groups list, edit the new group name as needed. (Double-click the name to edit it, if it is not already in edit mode.) Double-click the name again to set it, or click outside the box.
3. Add the values you want in the group by selecting a value in **Available Values** list and clicking  (Add value to selected group) button. The selected value is added to the selected group in the Value Groups list.
4. Repeat the previous step for each value you want to add to the group.

If a value that you want to add to a group is not listed in Available Values list, specify the value in **Additional Value** field (under Available Values) press Return key. The custom value is added to the currently selected group.




Select an Available Value and click  to add all the values to the selected group in Value Groups, click  to remove the selected value from Value Groups, and click  to remove all the values from Value Groups box.

Select a group and click up  and down  arrows to move the selected group up or down. Select a value and click up  and down  arrows to move the selected value up or down (within the group).

5. Click **Save**.

Note: If the name of a group is changed by a user, the values under that group will be removed from the **Selected Values** group of that user's preferences.

To create a tree view parameter:

1. Click the leaf node and click the right arrow  button.
 - To select all values in a branch (only for a multi-select parameter), click the branch and click the  button.
 - To make changes in name of a group, double-click the group name to make it editable. Specify a new name and click outside the box.
 - To delete a group, click  in the title of group you want to delete, and then click the **Save** button to save the changes.

See also

- ["Parameters" on page 273](#)
- ["Creating New Parameters" on page 275](#)
- ["Parameter Object Editor" on page 274](#)
- ["Parameter Properties" on page 306](#)
- ["Parameter Value Groups" on page 281](#)

- ["Placing a System-defined Query or Parameter into a Category" on page 293](#)
- ["Modifying a Parameter" on page 280](#)
- ["Deleting a Parameter" on page 280](#)

Template Styles

Logger reports use a style file (**.sty**) to generate report output in a specified format. The style file defines the look and feel, arrangement, and orientation of the report output.

You can modify any of the style files from the Logger Reports Template Styles page or you can define a new style to suit your needs.

Note: A report layout file (**.irl**) defines factors like paper size, static controls, and headers and footers to include in a report. You can define your own layout files. See ["Defining a New Template" on the next page](#) for more information.

See also

- ["Working with Logger Report Templates" below](#)
- ["Defining a New Template" on the next page.](#)
- ["Template Properties" on page 306](#)

Working with Logger Report Templates

Before creating a new template, you may want to check whether there is an existing one that meets your needs.

To search for an existing template

1. Do one of the following:
 - Select **Starts With** — Enter the first few letters of the template name in the text box above the list of existing templates.
 - Select **Contains** — Enter a word or part of a word that the template name contains in the text box above the list of existing templates.

To view and work with Logger Report template styles


1. Click **Template Styles** on the Reports menu.
2. Select an existing template, or create a new layout. See ["Defining a New Template" on the next page.](#)
3. Make modifications as needed.
4. Click **Preview** to display the template with sample data.
5. Click **Save** to save the layout. Your template will now display in the Templates list.

See also

- ["Defining a New Template" below.](#)
- ["Template Properties" on page 306](#)
- ["Template Styles" on the previous page](#)

Defining a New Template

To define a new template

1. Under Design, click **Template Styles** on the Reports left menu bar.
2. Click the  icon in the right panel.
3. Define the Items and Item Properties for the template.
4. Optionally, if you want to define or change the report layout file, click **Edit Layout**. See ["To include a header or footer in a report" below.](#)
5. Click **Save**.

To include a header or footer in a report

1. From the top of the templates page, click **Edit Layout**.
2. Click **Report Header** to include a header or **Page Footer** to include a footer.
3. Click **Insert > Layout Control**.
4. Select an option from the sub-menu and fill in the required information.

See also

- ["Working with Logger Report Templates" on the previous page](#)
- ["Template Properties" on page 306](#)
- ["Template Styles" on the previous page](#)

Reports Administration

This section explains the administration processes for configuring and managing Logger Reports.

Creating a Reports User Group

If multiple users need similar Report access rights, user groups can make administering those rights easier. Create a user group for each set of permissions, and then simply add the user to the appropriate groups. For more information, see ["Users/Groups" on page 495.](#)

To create a new User Group and give it Logger Reports Rights:

1. Click **System Admin** in the menu bar.
2. Click **User Management** in the Users/Groups section on the left panel.
3. Click the **Groups** tab, and click **Add**.
4. Type in a Name for the group and add a description.
5. Select **Logger Reports** from the Group Type drop down menu.
6. Click the arrow to display the list of Logger Reports Rights.
7. Click **Clear All** to remove all permissions.
8. Click the box next to each permission you want to give the user group.
For example, if you wanted to give the rights to view, run, and schedule reports from Foundation > Intrusion Monitoring > Attackers, put a mark in the box next to each of the following access rights:

Report folder [Attackers]: view, run, and schedule reports
Report folder [Foundation]: view, run, and schedule reports
Report folder [Intrusion Monitoring]: view, run, and schedule reports
9. Click **Save and Edit Membership**.
10. Click **Add** in the **Edit Group Membership** dialog.
11. Put a mark in the box for the user you want to add to the group, and click **OK**.
12. Log in as a member of the group you created and test whether you can perform the desired functions.
For the example, the user should be able to view, run, and schedule the Attackers reports only.

Managing Reports of Deleted Users

Because reports are often used by more than just one individual, Logger reports are not deleted when the report owner is inactivated as a Logger user. Keep in mind the following information:

- Scheduled reports continue to run after the user is deleted.
- An Administrator can delete or modify an inactive user's Public and Scheduled reports.
- Private reports are not visible to other users, including Administrators. Ask users to delete or convert Private reports to Public before they are inactivated.

Report Server Configuration

Logger Reporting provides a default configuration for the report server. If you do not modify the report server, reports will run with the default settings.

Report Configuration

To view or modify the report server configuration:

1. Click **Reports** in the navigation bar.
2. Click **Report Configuration** in the Administration section of the Reports menu. The **Report Configuration** dialog displays.
3. When you have finished entering the report configuration settings, click **Save**.

The following table describes the report configuration settings.

Report Configuration

| Option | Description |
|---|--|
| Database Connection Timeout (seconds) | <p>Time in seconds after which the database connection will be closed, if not used for that many seconds.</p> <p>Valid values include any integer greater than zero.</p> <p>Default: 14400</p> <p>Example: If DATABASE_CONNECTION_TIMEOUT is set to 50, the report server will close the connection to a database if there is no communication between the report server and database server for 50 seconds.</p> <p>For more information, see "Adjusting Timeout Values for Long-Running Reports" on page 164.</p> |
| Data Source Fetch Size (rows per fetch) | <p>Specifies the number of records to be fetched from the data source at one time (in one "read").</p> <p>A valid value is any positive integer.</p> <p>Default: 50</p> <p>Example: DATA_SOURCE_FETCH_SIZE=50</p> |
| Log Level | <p>Sets the level of criticality to be considered for logging.</p> <p>Valid values are DEBUG, INFO, WARN, ERROR, FATAL.</p> <p>Default: ERROR</p> <p>Example: LOG_LEVEL=ERROR</p> |
| Job Error Mail To | <p>Email address to receive job error messages, when generated. To include multiple addresses, separate them by commas.</p> |
| Scheduler Job Dispatch Threads | <p>Specify the number of scheduled reports that can be executed simultaneously. A maximum of 25 is licensed. Restart is required.</p> |

Report Configuration, continued

| Option | Description |
|-------------------------------|---|
| Host URL | Host URL (URL to the Logger application) sent as part of Logger Reporting Emails. Syntax: HOST_URL=[Host URL](String) Default: https://<logger_hostname>/logger/report Example: HOST_URL=https://loggerA.xyz.com/logger/report |
| Sign Document | Enable or disable the digital signing of reports. Options are Enable and Disable. Default is Disable . An administrator with correct permissions can browse and upload signature files. This can be done at global, organization or user level. When the Sign Document property is enabled, then these signatures are applied to the documents. See "Certificates" on page 398 . |
| Sign Document Formats | Currently, PDF is the only supported format for signatures. |
| Sign Document Operations | Enter what types of report operations should have a signature applied. Options are View, Email, Publish, Upload, Print, or All. Default is ALL . |
| Sign Document on Page | Choose on which page the signature should appear. Options are First and Last. Default is Last . |
| Sign Document Location Corner | Choose on which page corner the signature should appear. Options are Right Top, Right Bottom, Left Top, Left Bottom. Default is Left Bottom . |
| Maximum concurrent reports | Specify the maximum amount of reports that can be run concurrently. Logger can support a maximum of 25 concurrent reports. Yet, it has been set 5 by default. Make sure to restart the process after updating this field. |

Investigate Connection

To configure Vertica SSL, follow the steps listed in Chapter 8: Configuring Vertica SSL of the [ArcSight Investigate Deployment Guide](#).

Before adding or modifying the Vertica connection, generate the p12 for Java using the following command: **openssl pkcs12 -export -in client.crt -inkey client.key -out client.p12**. Then, include the **ca.crt certificate** in the Java truststore and the **client.p12** in the Java Keystore using the Logger **keytool_util.sh** script. After this process is completed, you can follow the steps described below.

Adding / Modifying Vertica DB connection

1. Click **Reports** in the navigation bar.
2. Click **ReportConfiguration** in the Administration section of the Reports menu. Click the **Investigate**

Connection tab.

3. Fill out the following mandatory fields with the appropriate information.
 - Connection Name: Name to identify the connection.
 - Host IP: IP or Logger hostname
 - Port: Default is 5433
 - Database: Default is Investigate
 - User name: User name for the specific connection
 - Password: Password for the specified connection
4. Fill out the following optional fields with the appropriate information. Properties with default values are mandatory to be filled.
 - a. Advanced Connection Settings
 - Max Rows
 - Schema
 - Initial Connection: Default is 5
 - Incremental Size: Default is 5
 - Resubmit Time: Default is 30 seconds
 - Max connections: Default is 30
 - White List: Default is Investigation.events
 - SSL: By default is checked.
 - b. JDBC Settings. It contains specific JDBC properties set to JDBC url.
5. Test or Save the changes.
 - Test: It checks the connection status.
 - Save: It creates a new connection named InvestigateDB. If it already exists a Vertica connection with the same name, the UI field values will be populated in the correspondent fields. To update the properties, change the values as needed and click save.

Report Categories

Reports, queries, and parameters can be organized and stored under categories for ease of access. You can create your own categories or edit existing category properties.

To open the Report Categories page

1. Click **Report Categories** from the Administration section of the Reports menu.

Look In: (Root)

Default Logger Search Reports (selected)
Default Reports
Device Monitoring
Foundation
Logger Administration
SANS Top 5
Test

Save Cancel Delete Cascade

Properties
☒ Public ☐ Private ☐ Hidden
Category Menu Name: Default Logger Search Reports
Category ID: Default_Logger_Search_Reports

Objects in each category can be accessed through the Reports Explorer. See ["Reports Explorer" on page 165](#) and ["Restrict Long Reports to Run in the Background" on page 186](#).

System-defined Categories

The several categories, based on common areas of usage, come with your system. The **Default Reports** category is for user-created reports. The other categories come with predefined reports ready for your use. For a complete list of reports in each category, access the category in the Report Explorer.

- Default Reports: User-generated reports are placed in this category.
- Device Monitoring: This category includes the following subcategories.
 - Anti-Virus: Use this category to store reports, queries, parameters, dashboards, and dashboard widgets that provide information on anti-virus activity, such as the anti-virus update status, virus activity by hour, and top infected systems.
 - CrossDevice: These reports provide information on functions that apply to multiple kinds of devices, such as failed login attempts, bandwidth usage by hosts, and accounts created by user.
 - Database: The report in this category provides information on database errors and warnings.
 - Firewall: These reports provide information on firewall activity, such as denied connections by port, address, and hour.
 - Identity Management: This report provides information on the number of connections per user as reported by the Identity Management devices in your network.
 - IDS-IPS: These reports provides information on activity involving Intrusion Detection Systems (IDS) and Intrusion Prevention Systems (IPS), such as alert count by device, port, severity, top alert destinations, worm-infected systems, and related metrics.

- Network: These reports provide information on activity involving network infrastructure, including interface status, device errors, and SNMP authentication failures.
- Operating System: These reports provide information on activity involving operating systems, such as login errors per user, user and user group creation, and modification events.
- VPN: These reports provide information on activity involving VPN connections, including authentication errors, connection information such as counts, accepted and denied by address, and related metrics.

Tip: More reports may be available for download as report packages on the Micro Focus Customer Support site (SSO). (For information about deploying report packages, see ["Deploying a Report Bundle" on page 307.](#))

- Foundation: This category includes the following subcategories.
 - Configuration Monitoring: Logger provides reports that address configuration monitoring.
 - Intrusion Monitoring Reports: Logger provides reports that address intrusion monitoring. For example, reports are provided to track password changes, firewall configuration events, firewall traffic, top attackers traversing firewalls, and so forth.
 - Intrusion Monitoring Reports: Logger provides reports that address intrusion monitoring. For example, reports are provided to track password changes, firewall configuration events, firewall traffic, top attackers traversing firewalls, and so forth.
 - Netflow Monitoring: Netflow Monitoring reports IP traffic information.
 - Network Monitoring Reports: Network Monitoring reports describe activities on Virtual Private Networks.
- Logger Administration: This category includes Logger Administration tasks such as Daily Byte Count.
- SANS Top 5 Reports

Logger provides reports that address the SANS Top 5 log reports scenarios, all pre-built and available to run on-demand or schedule for a specified frequency.

The SANS Institute is a cooperative training, certification, and research organization with a focus on developing solutions for securing information against a variety of potential threats. SANS facilitates and supports a collaborative effort of a large number of security practitioners in various industries and sectors around the world to share experience, solutions, and resources related to information security.

Note: SANS stands for “SysAdmin, Audit, Network, Security”. More information is available on their Web site at www.sans.org

The SANS Top 5 represents the current set of most critical log reports for a wide cross-section of the security community, and should be reviewed on a regular basis. This quote from the SANS Web site describes the strategy and focus of the SANS Top 5 Essential Log Reports:

“The goal is to include reports that have the highest likelihood of identifying suspect activity, while generating the lowest number of false positive report entries. The log reports may not always clearly

indicate the extent of an intrusion, but will at least give sufficient information to the appropriate administrator that suspect activity has been detected and requires further investigation.”

The SANS Top 5 log reports cover the following five scenarios:

- 1 - Attempts to gain access through existing accounts
- 2 - Failed file or resource access attempts
- 3 - Unauthorized changes to users, groups and services
- 4 - Systems most vulnerable to attack
- 5 - Suspicious or unauthorized network traffic patterns

For a complete description of the SANS Top 5 log reports, see www.sans.org/resources/top5_logreports.pdf or look for associated topics in SANS resources on their Web site.

The Logger SANS Top 5 Reports offered to address these threat scenarios are:

- SANS Top 5 - 1 Number of Failed Logins
- SANS Top 5 - 1 Top Users with Failed Logins
- SANS Top 5 - 2 Failed Resource Access by Users and Drilldown
- SANS Top 5 - 2 Failed Resource Access Events and Drilldown
- SANS Top 5 - 3 Password Changes
- SANS Top 5 - 3 User Account Creations, Deletions, and Modifications
- SANS Top 5 - 4 Vulnerability Scanner Logs by Host or by Vulnerability
- SANS Top 5 - 5 Alerts from IDS
- SANS Top 5 - 5 IDS Signature Destinations and Source
- SANS Top 5 - 5 Top 10 Talkers
- SANS Top 5 - 5 Top 10 Types of Traffic
- SANS Top 5 - 5 Top Destination and Target IPs
- SANS Top 5 - 1 Number of Failed Logins
- SANS Top 5 - 1 Top Users with Failed Logins
- SANS Top 5 - 2 Failed Resource Access by Users and Drilldown
- SANS Top 5 - 2 Failed Resource Access Events and Drilldown
- SANS Top 5 - 3 Password Changes
- SANS Top 5 - 3 User Account Creations, Deletions, and Modifications
- SANS Top 5 - 4 Vulnerability Scanner Logs by Host or by Vulnerability
- SANS Top 5 - 5 Alerts from IDS
- SANS Top 5 - 5 IDS Signature Destinations and Source
- SANS Top 5 - 5 Top 10 Talkers

- SANS Top 5 - 5 Top 10 Types of Traffic
- SANS Top 5 - 5 Top Destination and Target IPs
>Solution Reports

Any solution packages installed on the Logger are listed in separate report groups. Solution packages address specific compliance requirements or scenarios and are installed separately. Solutions Reports are available as add-on packages to Logger for specific compliance requirements or scenarios.

Note: You must log into Logger and open the Reports page at least once before installing any Solutions package.

The available solution packages include:

- ITGov (ISO 27002 & NIST 800-53 based reports)
- Payment Card Industry, (PCI based reports)
- SOX (Sarbanes-Oxley compliance reports)

For information on deploying Solutions Packages, see ["Deploying a Report Bundle" on page 307](#). Once deployed, these solution reports are listed in categories under the Solution Reports report group. To access these reports (once deployed), click **Reports | Solutions Reports |<report category name>** on the left menu, where <report category name> is the solution name, for example: **Payment Card Industry**.

For more information on report categories, including how to edit them, see ["Report Categories" on page 289](#).

Placing a System-defined Query or Parameter into a Category

You can place a pre-defined query or parameter into a category. Use the cut/paste feature to do so because cutting and pasting will preserve its ID.

To cut and paste a query or parameter:

1. Click **Explorer** in the Reports menu. Explorer displays.
2. Navigate to and select the pre-defined query or parameter you want to move.
3. Right-click **Cut Query Object** or **Cut Parameter Object** from the context menu.
4. Click the category name under which you would like to place this query or parameter.

Note: You cannot save a report in the root category. Save it in one of the existing subcategories, or create a new category.

5. Right-click again and click **Paste**.

Tip: Do not **copy** and paste a query or parameter to place it in a category. Doing so will give the query or parameter a new ID and render it unusable to reports or other existing objects that are using it. Use **cut** and paste, instead.

You can schedule any report to run once at a later date or on a specified frequency (such as daily or weekly). Monthly reports cannot be scheduled currently. For more on this, see ["Scheduled Reports" on page 177](#).

You can run, publish, and save the results of any type of report. For information on these common reporting tasks available on all reports, see ["Running Reports" on page 183](#) and ["Published Reports" on page 172](#).)

See also

- ["Parameters" on page 273](#)
- ["Creating New Parameters" on page 275](#)
- ["Parameter Object Editor" on page 274](#)
- ["Parameter Properties" on page 306](#)
- ["Parameter Value Groups" on page 281](#)
- ["Configuring Parameter Value Groups" on page 281](#)
- ["Modifying a Parameter" on page 280](#)
- ["Deleting a Parameter" on page 280](#)


Adding a New Category

In addition to using the existing report categories, you can create additional categories to meet your business needs.

To add a custom category:

1. Click **Report Categories** in the **Administration** section in the left pane.


The Deploy Reports and Categories displays the available categories. A toolbar across the top of the page displays buttons for the available actions.

2. Click **Add New Category** .
3. Define the properties for the new category and click the **Save** button.

| Property | Used for... |
|--------------------|---|
| Public | Setting this as Public makes the category available to everyone |
| Private | Setting this as Private make the category available to you only |
| Hidden | Select the Hidden checkbox to hide the display of this category in the Report Explorer. It will still be displayed in other Explorers. |
| Category Menu Name | Name of the Category |

| Property | Used for... |
|------------------|---|
| Category ID | Category ID should be unique across all the categories. By default, the Category ID is auto-generated by the system. To specify the Category ID manually, deselect the System Generated checkbox and specify the category ID. |
| System Generated | To specify the Category ID manually, deselect the System Generated checkbox and specify the category ID. |
| Delete Cascade | You can delete a category only if it is empty. To delete a category including its contents, check the Delete Cascade checkbox. |

Note: Once set, Category ID and scope (Public / Private options) cannot be changed.

4. You can optionally add a report to the category. To do so, double-click any category to open it and click the **Add New Report**  button. Define the following properties in the Properties box:

| Property | Used for... |
|------------------|--|
| Public | Setting this as Public makes the report available to everyone |
| Private | Setting this as Private make the report available to you only |
| Hidden | Check the Hidden checkbox, if you do not want to display this report in any of the dialogs and pages (except in the Report Explorer). Mark a report as hidden to stop users from directly accessing it. |
| Report File | An existing data file from which a report is generated. |
| Report Name | The Report Name has to be unique within a category |
| Report ID | A unique ID for the report that is auto-generated by the system by default when you run and publish the report. To manually enter an ID of your choice, deselect the System Generated checkbox and enter an ID in the Report ID field. |
| Design Mode | Text in Design Mode indicates if the report was designed using Studio (Web Studio or Desktop Studio) or ad hoc Report Wizard. |
| Deployment Type | A report deployed as Read Only cannot be modified and uploaded with same name. A report deployed as Custom can be modified and uploaded with the same name. |
| Output Format | Output Formats in which this report can be generated. Formats not selected here will not be available for this report. |
| System Generated | To specify a Report ID manually, deselect the System Generated checkbox and specify the Report ID. |

Deleting a Category

To delete a custom category:

1. Click **Report Categories** in the **Administration** section in the left pane.
The Deploy Reports and Categories display the available categories. A toolbar across the top of the page displays buttons for the available actions.
2. Select the category that needs to be removed.

3. Click .

Note: Before eliminating the category, make sure it contains no reports. Otherwise, an error message will appear.

4. Refresh the page in order to allow sync with Report Explorer.

Job Execution Status

About


The status of your scheduled reports can be displayed from this option.

Procedure

To open the Job Execution Status Page, go to **Reports > Administration > Job Execution Status**

Execution status of all the reports executed through scheduling or reports that ran in background can be viewed on Job Execution Status page. This page also lists reports that are currently executing and reports that are coming up for execution.

Jobs Execution Status



Data is displayed as Line chart and table.

By default, data of jobs having execution date 7 days in past is displayed. For example, if today is June 8 2018, data of jobs having execution date between June 1, 2018 and June 8, 2018 will be displayed.

Chart

Chart depicts jobs execution status in line chart (by date) for Completed jobs, Succeeded Jobs, Failed Jobs and Upcoming Jobs. If date range applied in filter is 3 days or less, chart will display hourly data. When you apply filter, the chart will change accordingly.

To view the point value, click corresponding line and hover on the point. A callout will be displayed showing the point value. To disable the value popup, click corresponding line again. When you click the data point, job detail pertaining to the clicked point will appear in a popup window.

The chart tab is collapsible. Click chart title to hide the chart tab. Click the title again to open chart tab.

List of Jobs

For each job, the following details are listed:

- Job Name
- Report Name
- Frequency
- Owner
- Scheduled Time
- Execution Time

- Last Run Status
- Re-Run

Frequency value of one-time jobs will be displayed as blank.

The Filters area

When the page opens, Filters tab remains collapsed. Click the tab-header to expand it. The tab-header also displays current filter settings. By default, it displays first 500 jobs (no filter for report name, Owner). List of jobs can be filtered by:

- **Entity Type:** Select a report/Query. Select a folder to select all the reports/queries in it. Click to open object selector to make selection.
- **Job Name:** Name of job.
- **Job Run Time:** Select (All) to view all jobs, select Completed to list jobs that are completed (successful as well as failure), Scheduled to list the jobs that are currently executing and select Pending to list jobs that are yet to be executed.
- **Status:** Select Success, Failure or All to include only successful jobs, failed jobs or all jobs respectively.
- **Date From and To:** Dates between which the jobs were executed / to be executed.
- **Job Type:** Select the job type. (All), to include all type of jobs; Now, Once, Recurring to include respective types; Background to include jobs run in background, Post Approval to include the jobs that executed reports supposed to undergo approval process.
- **Frequency:** Available when selected Job Type is Recurring, select among Daily, weekly, monthly or All.
- **Select Owner:** User who is owner of the job.
- In **Private Owned By**, select None to not view any private jobs, select Selected User to view selected user's private jobs, select Selected Org to view private jobs of users belonging to the selected organization (in Select Owner) and ALL to view private jobs owned by all the users.
- In **Public Owned By**, select None to not view any public jobs, select Selected User to view selected user's public jobs, select Selected Org to view public jobs of users belonging to the selected organization (in Select Owner) and ALL to view public jobs owned by all the users.
- **Show (selecting the number):** Select Top 100 to view first 100 jobs from the filtered list, select Top 500, Top 1000 and Top 4000 to view first 500, 1000 and 4000 jobs respectively.

Tip: Click a date to show jobs for that day in a pop-up.

Note: Jobs are listed in the ascending order of the time of execution.

Filtering the list

Provide filter criteria and click the **Apply** button. **List** of jobs having jobs that meet the filter criteria will be listed and will be plotted on chart.

Backup and Restore Report Content

You can back up, restore, and disseminate report content and configuration information, using iPackager to create a CAB file, and Deploy Report Bundler to deploy it. For more information, see ["iPackager Utility" below](#), and ["Deploying a Report Bundle" on page 307](#).

iPackager Utility

The iPackager utility enables you to package reports and report objects residing in Logger. This package can be later imported to a different Logger installation. If you own multiple Loggers, you can use the packages to configure reporting features on them. This method eliminates the need to configure reporting features for each Logger.

Note: The iPackager utility requires administrator privileges.

To access the iPackager utility:

1. Click **Reports** from the top navigation bar. The Reports home page displays.
2. Click **Administration** from the Reports menu. The Administration menu opens.
3. Click **iPackager** at the bottom of the menu. The iPackager page displays.

How iPackager Works

You first create a configuration (**.conf**) file, in which you can collect (import) the references for all the entity objects that you want to include in the package. You can save the configuration file and edit it at any time. Once you are satisfied with the contents of the **.conf** file, you can build the package into a **CAB** file. Data can be imported from multiple report servers and packaged in a single **CAB**.

Note: You can open only one **.conf** file in iPackager at a time.

Tip: When iPackager opens a **.conf** file, it checks for the availability of the objects already imported in the **.conf** file. If any of the objects already imported are not found on the report server, it is indicated on the tree view. The CAB file cannot be built until the missing object is replaced, or the object is removed from the **.conf** file.

iPackager Actions

The following actions can be performed from within the iPackager:

| Action | Description |
|-----------|--|
| Add New | Creates a new configuration (.conf) file. |
| Open | Opens an existing .conf file in iPackager. |
| Delete | Deletes the selected .conf file. |
| Save | Saves the currently open .conf file. |
| Save As | Saves the .conf file that is currently open under a new name. |
| Build CAB | Initiates the process of building a CAB file. |
| Cancel | Cancels the operation. |
| Upload | Uploads the .conf file to a web server. |
| Download | Downloads the .conf file from a web server to the browser's default download folder. |

Selecting Entities

You can select entity objects with different levels of granularity:

- 1** To select all the entities within a repository, click the check box for the entity type. The Selection Summary pane displays "All entities inside <repository name> are selected."
- 2** To select a subset of a repository, open (►) the entity type and select an entity sub-type from the open list. The Select Entities pane displays available entity objects. After you've made your selection, the Selection Summary page displays the number and type of entities you select.
- 3** To select all the entities from the report server, click "Select All Data From Report Server" at the bottom of the Entity Type pane. The Selection Summary pane displays "All data from report server is selected." Click "Deselect Complete Data" to revert the selection.

Opening a Configuration File

To open an existing .conf file in iPackager:

1. Click **Open** in the iPackager toolbar. The Open Configuration File dialog opens.
2. Select an available configuration file.
3. Click **Open**.

Selecting Entity Objects

You can select entity objects with different levels of granularity:

- 1** To select all the entities within a repository, click the check box for the entity type. The Selection Summary pane displays "All entities inside <repository name> are selected."
- 2** To select a subset of a repository, open (▶) the entity type and select an entity sub-type from the open list. The Select Entities pane displays available entity objects. After you've made your selection, the Selection Summary page displays the number and type of entities you select.
- 3** To select all the entities from the report server, click "Select All Data From Report Server" at the bottom of the Entity Type pane. The Selection Summary pane displays "All data from report server is selected." Click "Deselect Complete Data" to revert the selection.

Adding Entity Objects to a Configuration File

You can import entity object references from a report server into a **.conf** file.

Note: Only references to the entities will be imported. The actual components will be imported during the creation of the CAB file.

To add entity object references to a .conf file:

1. Select the entity objects you want to import. See ["Selecting Entity Objects" above](#).
2. Click **Save** or **Save As** to open the Save Configuration File dialog box.
3. Enter a name for the configuration file.
4. Click **Save**. If successful, a confirmation message displays at the top of the page.

Note: The **Add New** button is now available, which clears the entity selection panes for a new configuration file.

Report Category Filters

A Search Group filter can be optionally assigned to each report category. Assigning a Search Group filter to a report category means that all the reports in the category will only process events returned by this filter.

To assign a search group filter to a report category:

1. Create the filter that you would like to apply to every report in a given category. See ["Filters" on page 311](#) for the details of creating a filter of type Search Group.
2. Open the **Reports** page.
3. In the menu, under **Administration**, click **Report Category Filters**.

4. Select the desired filter for each category.

To accelerate the search, the query type is listed next to the Search Group filter name in the list page. List is displayed in alphabetical order.

Note: For Unified Queries: Duplicate Storage Groups and Search Groups are not supported. The user is unable to create reports with duplicate parameters. Therefore, if the same condition added previously as filter is selected, a warning message is displayed. On the other hand, with the exception of MySQL reports, the peers option is currently disabled.

Note: Report category filter in a Logger Search Report will override the Search Group Filter. If the category of the Logger Search Report does not have a filter, the system will apply the filter in the Search Group Filter.

5. Click **Save**.

To remove a search group filter from a report category:

1. Open the **Reports** page. In the menu, under Administration, click **Report Category Filters**.
2. In the pull-down menu associated with the report category from which you want to remove the filter, select **None**.
3. Click **Save**.

Deleting Entity Objects from a Configuration File

To delete an entity object within a .conf file:


1. Open the **.conf** file in iPackager.
2. Open the repository that contains the entity object.
3. Deselect the check box for the object.
4. Click **Save**.

Modifying Entity Object Properties

You can modify the properties for entity objects in an open **.conf** file.

To modify an entity object property:

1. Click **Open** to open an existing **.conf** file.
2. Select the entity types to open the object you would like to modify.
3. From the Select Entity pane, right-click the object and click **Properties** from the popup menu.



The Properties dialog box displays for the object. Each object displays its own default properties.

A screenshot of the 'Report Properties' dialog box. It has a title bar with a close button. The dialog contains several fields: 'Category Name' with the value 'Configuration Monitoring', 'Report' with 'Accounts Deleted by User', and 'Version' with '0.00'. There is a 'Deployment Type' dropdown menu currently set to 'Editable'. Below these is a section titled 'Deployment Options' which contains two groups of checkboxes. The first group, 'if Exists', has 'Overwrite' checked and 'Delete' unchecked. The second group, 'if Not Exists', has 'Add' checked. At the bottom right are 'Update' and 'Cancel' buttons.

Object names are pre-populated with the object name from the report server. You can change the name of the object. If you change the name here, the object is packaged with the new name, but its original name on the report server will not change.

In addition, all objects have some variation of the following Deployment Options:


- If Exists:
 - Overwrite — While importing, if the component is found in the package, replace the one in package with the one on the report server.
 - Delete — While importing, if the component is found in the package, delete it.
 - Cascade Delete (Category folders only) — Delete the category folder, even if it contains reports.
- If Not Exists:
 - Add — While importing, if the component is not found in the package, add it to the package.

Category Properties

While creating a CAB file in iPackager, you can change the name for a selected Category. If you change the name here, the category is packaged with the new name, but its original name on the report server will not change.

Change a Category name in iPackager

1. From the Navigation tree in iPackager, select a Category you want to re-name.
2. Right-click and select **Properties**. The Category Properties dialog opens.



The image shows a 'Category Properties' dialog box with a close button (X) in the top right corner. It contains two text input fields: 'Parent Category:' which is empty, and 'Category:' which contains the text 'Default Logger Search F'. Below these fields is a section titled 'Deployment Options'. Under this section, there are two groups of options. The first group is labeled 'if Exists:' and contains three radio buttons: 'Overwrite' (which is selected), 'Delete', and 'Cascade Delete'. The second group is labeled 'if Not Exists:' and contains one radio button: 'Add' (which is selected). At the bottom right of the dialog are two buttons: a blue 'Update' button and a black-outlined 'Cancel' button.

3. Change the properties as needed.
4. Click **Update**. The new Category name displays in the iPackager.

Report Properties

When you click on a report in the navigation tree of the iPackager page, the following property page opens.

Category Properties

×

Parent Category:

Category:

Deployment Options

if Exists: ☒ Overwrite
☐ Delete
☐ Cascade Delete

if Not Exists: ☒ Add

The **Report** box is pre-populated with the report name found on the report server. You can change the name of the report. If you change the name here, the report is packaged with the new name, but its original name on the report server will not change.

Query Properties

When you click on a query in the navigation tree of the iPackager page, the following property page opens.

Query Object Properties

×

Category Name:

Query Object:

Deployment Options

if Exists: ☒ Overwrite
☐ Delete

if Not Exists: ☒ Add

The **Query Object** box is pre-populated with the query object name found on the report server. You can change the name of the query object. If you change the name here, the query object is packaged with the new name, but its original name on the report server will not change.

Parameter Properties


When you click on a parameter in the navigation tree of the iPackager page, the following property page opens. The **Parameter Object** box is pre-populated with the parameter object name that is found on the report server. You can change the name of the parameter object. If you change the name here, the parameter object is packaged with the new name, but its original name on the report server will not change.

See also

- ["Parameters" on page 273](#)
- ["Creating New Parameters" on page 275](#)
- ["Parameter Object Editor" on page 274](#)
- ["Parameter Value Groups" on page 281](#)
- ["Placing a System-defined Query or Parameter into a Category" on page 293](#)
- ["Configuring Parameter Value Groups" on page 281](#)
- ["Modifying a Parameter" on page 280](#)
- ["Deleting a Parameter" on page 280](#)

Template Properties

When you click on a template in the navigation tree of the iPackager page, the following property page opens.



Template Properties x

File Name:

Deployment Options

if Exists: ☒ Overwrite
☐ Delete

if Not Exists: ☒ Add

See also

- ["Working with Logger Report Templates" on page 284](#)
- ["Defining a New Template" on page 285.](#)
- ["Template Styles" on page 284](#)

Building the CAB File

When you issue command to build the CAB file, the actual objects specified in the references in your open .conf file are actually picked up from the respective locations and a CAB file is built. This CAB file will contain all the objects.

If any of the information saved in the **.conf** file is not available at the right source while building the CAB, then you will see an error message and the CAB building process stops. You will need to fix any errors before rebuilding the CAB file.

To build the CAB file:

1. Click **Build CAB**.
2. On the **Build Properties** dialog, enter a name for the file. Make sure the filename only contains alphanumeric and dash characters. Otherwise, you cannot deploy the file afterwards.
3. Optionally, enter information in the **Author**, **Company**, **Version**, and **Comment** fields.
4. Click **Build and Download**. The Build Status window displays the status. To halt the process, click **Cancel Build**.
5. When the CAB file is complete, follow the prompts to view the objects included in the file.

Deploying a Report Bundle

You might obtain additional sets of reports from ArcSight to address new security scenarios, add packaged solutions, or enhance your current coverage with updated reports. You can use the **Deploy Report Bundle** page to load and deploy packages of new reports onto your Logger system.

To deploy a report CAB file:

On the **Reports** page left panel menu, click the **Deploy Report Bundle** link to start.

A report package (or CAB file) can contain many types of reporting resources, including:

- Categories and reports
- Organization information
- Portal properties and server properties
- Parameter objects
- Query objects
- Ad hoc report templates
- Printer settings
- Database connections

To upload and deploy a report package:

1. In the entry box provided under Step 1, specify the reports package file name and with its full path. Click **Browse** to locate the file.
2. Click **Upload**. The content is uploaded and information is displayed about the included categories and report objects.
3. To create a deployment process log, select the **Create Log File** option.
4. Click **Deploy** to continue with the deployment process, or click **Cancel** to discontinue. A log file will be created if the **Create Log File** checkbox was selected.

Status information is displayed about the objects in the package being deployed. A legend is displayed just below the **Deploy** button. Information about each of the components in the package is displayed in respective tabs.

Note: Overwrite behaviors are determined when the package was created.

For example, protocol on whether or not an object in the deployed package will overwrite an existing object on the system, and under what circumstances, is determined at package creation time. Therefore, these settings on package deployment are not available to you at deploy time. See ["iPackager Utility" on page 299](#).

5. Click **Download Log**

The content of the deployed reports package is available on the respective Logger Reports pages. Solution Reports will be listed under **Solution Reports** on the left panel menu. For more information about these types of reports, see ["System-defined Categories" on page 290](#).

To customize the cab information:

When deploying a CAB file from a source Logger to a target Logger, if the categories being imported do not have identical names and IDs on both Loggers, the deployment may fail.

To customize the information during deployment and look for any failures, Go to **ReportClient.properties** file and update these values:

- Enable the events. By default, this value is false
- Configure the class path as appropriate.

Should you encounter this issue, rename the conflicting category in the target Logger or the source Logger (you will need to recreate the CAB file if you do this on the source Logger) such that the category has a unique name or ID. Then, redeploy the CAB file.

Note: If a CAB file is created for Logger Search Reports, users may need to relink the filter or the saved search once the report object is in the Destination Logger.

Deleting an iPackager Configuration File

To delete a **.conf** file:

1. Open the **.conf** file in iPackager.
2. Click **Delete**.
3. On the warning dialog, click **Yes** to confirm the deletion.

Chapter 5: Configuration

The following topics describe how to create and manage receivers, forwarders, devices, device groups, SmartConnectors, and filters. Receivers, devices, and other resources created by one user are visible to all other users, although subject to user group privileges. Resources are shared by all sessions.

| | |
|--|-----|
| • Search | 310 |
| • Data | 342 |
| • Storage | 404 |
| • Scheduled Tasks | 417 |
| • Advanced Configuration | 420 |

You can access these configuration options in the Logger UI from the Configuration dropdown menu or by starting to type the feature name in the Take Me To... text box and clicking it in the dropdown list.

Search

The options in the **Configuration | Search** category enable you to manage how search works on your Logger.

| | |
|---|-----|
| • Filters | 311 |
| • Search Group Filters | 314 |
| • Saved Searches | 315 |
| • Scheduled Searches/Alerts | 317 |
| • Saved Search Files | 326 |
| • Search Indexes | 326 |
| • Guidelines for Field-Based Indexing | 327 |
| • Global Search Options | 328 |
| • Managing Fieldsets | 333 |
| • Default Fields | 333 |
| • Custom Fields | 335 |
| • Running Searches | 335 |
| • Lookup Files | 336 |
| • Import Geolocation Files | 342 |

Filters

You can create search filters to save specific queries so that you can easily use them again. Filters are similar to saved searches. However, filters save the query only, while saved searches save the time range information in addition to the query.

Your system comes with a set of predefined search filters. For more information about these filters, see ["System Filters/Predefined Filters" on page 140](#). You can add new filters and edit the existing ones from the Filters page.

The following categories of filters are displayed on the Filters page.

- **Shared:** Shared search filters are user-created and are visible to all users. Once created, any user can use a shared search filter to search for events.
- **Search Group:** Search group filters provide an access control mechanism to limit the events that users in a particular user group can see. Search group filters can also be used to limit the events processed by a category of reports (see ["Report Category Filters" on page 301](#)). The query for these filters can contain either a regular expression or one level of unified query. For more information, see ["Search Group Filters" on page 314](#).


You must have admin-level privileges to create or edit search group filters. See ["Users/Groups" on page 495](#) for more information on Logger user rights and how to administer them.

- **System:** A set of pre-defined filters, known as system filters, come with your system. For more information about system filters, see ["System Filters/Predefined Filters" on page 140](#).

Search filters can have one of two different types of query:

- **Unified Query:** Unified Query (Unified) search queries specify keywords and fields.
- **Regular Expression:** Regular Expression (Regex Query) search queries specify a regular expression. Regular expression based search filters are useful for creating real time alerts, which accept only regex queries.
- The Search Group Filters manage the association of User Groups with Search Group Filters. Search Group Filters can be used to restrict events in the following two ways: Unified or Regex queries.

To create a filter



1. From the navigation bar Configuration menu, select **Filters** to open the Filter page.
2. Click **Add**. The Add Filter page displays.
3. Enter a name for the new filter in the Name field. Filter names are case-sensitive.
4. Select the category from the type drop down:
 - For Shared Filter: Select whether is Unified or Regex. Click next
 - For Search Group filter: select search group filter. Click next.

Note: If you create a Search Group filter, make sure that you associate it to a user group, as described in ["Search Group Filters" on page 314](#).

5. If Search Group Filter is the category, select the type: **Unified** or **Regex Query** from the type drop down.

Once you select the type, the following message will be displayed: ***The search group will be automatically updated in the database. Do you want to continue?*** If click cancel, the current category remains selected.

6. Enter the query for the new filter.

- For Unified queries:

Type a query. Logger's Search Helper enables you to quickly build a query expression by automatically providing suggestions, possible matches, and applicable operators. See ["Search Helper" on page 104](#) for more information. Duplicate Storage Groups and Search Groups are not supported. The user is unable to create reports with duplicate parameters.

OR

Click **Advanced Search** to use the Search Builder Tool to create the query. For details about using the Search Builder Tool, see ["Using the Advanced Search Builder" on page 98](#).


When adding a filter in Device Groups or Storage Groups, Logger displays a confirmation message

as this action limits future searches for both search and report.


- For Regex queries: Enter the regular expression in the Query text box.

7. Click **Save**.

To create a filter by copying an existing one:

1. From the navigation bar Configuration menu, select **Filters** to open the Filter page.
2. Locate the filter that you want to copy from the list of filters. Click the Copy icon ().
A new filter with the name "Copy of <filtername>" is created.
3. Change the name of the filter and edit the query for the new filter if necessary.
4. Click **Save**.

To edit a filter:

1. From the navigation bar Configuration menu, select **Filters** to open the Filter page.
2. Find the filter that you want to edit and click the Edit icon () on that row.
3. Change the information accordingly based on the query type:
4. Click **Save**.


Note: Logger does not support right click functions. If any of the options is selected, an invalid page is opened or saved. Make sure to edit the search group filter by double clicking the filter name or click the correspondent edit button.

Peer /Pipeline Operator:

It applies for Regex /Unified filter only. The query textbox in the search group category does not allow either [_peer] or [!] to use pipeline expressions.

If you use the advanced option, the Auto suggest for Unified Queries filters has been limited to level 1; complex expressions are not supported. "Peer" option was removed and it is no longer available in the edit section. If you attempt to add this keywords, the following message displays: "The peerLogger keyword is not allowed for Unified Search Group filters".

To delete a filter:

1. From the navigation bar Configuration menu, select **Filters** to open the Filter page.
2. Find the filter that you want to delete and click the Delete icon () on that row.
3. Confirm the delete.

Search Group Filters

The Search Group Filters manage the association of User Groups with Search Group Filters. Search Group Filters can be used to restrict events in the following two ways:

- **Restrict the events processed by a Report Category:** A Search Group Filter can be associated directly with a Report Category. This association provides a way to restrict the events processed by all the reports in a Report Category.

When a Search Group filter is used to restrict the events processed by a Report Category, you do not need to configure the Search Group in the Search Group Filters page as described below. After adding a filter of type "Search Group", you can go directly to the Reports Category Filters page under the Reports menu and select the filter for the Report Category. For more information, see ["Report Category Filters" on page 301](#).


When the user executes a Logger Search report with a filter that belongs to the report category, it will override the Search Group Filter. If the category of the Logger Search Report does not have a filter, the system will apply the filter in the Search Group Filter.

- **Restrict the events visible by members of a user group:** A Search Group Filter can be associated with a user group (of type Logger Search). This association means that all members of the user group only see events that match the Search Group Filter. User groups (described in more detail later in this chapter) provide a way of assigning privileges to a specified set of users.

Search Group Filters

You may assign a search filter to a search group that will be appended to all searches performed by users in that search group.

To create a new search group filter, you must first go to the [Filters](#) page and add a new filter of type Search Group.

| Name | Filter | Description | |
|---|--------|--|---|
| Default Logger Search Group | NONE | The default search group allows both local and distributed searches. |  |


Tip: The User Group of type Default Logger Search Group is listed in the Name column and the associated filter is listed in the middle column.

Users who belong to a User Group that does not have a Search Group Filter will see all events.

To add, edit, or delete Search Group Filters, see ["Filters" on page 311](#). To add, edit, or delete User Groups, see ["Users/Groups" on page 495](#) for more information on Logger user rights and how to administer the. Only users that are members of a Logger Rights group can assign Search Group Filters.

To associate a Search Group Filter with a User Group:

1. If the User Group that you want to associate with the Search Group Filter does not exist, create a new User Group of type Search Group. For instructions, see ["Users/Groups" on page 495](#).

2. If the Search Group Filter you want to associate with the User Group does not exist, create a filter of type Search Group. For instructions, see ["To create a filter" on page 312](#). When creating the filter, from the **Type** pull-down menu select the **Search Group** option.
3. From the navigation bar Configuration menu, select **Search Group Filters**.
4. Select the User Group in the Search Group Filters table. Click the Edit icon ().
To accelerate the search, the query type is listed next to the Search Group filter name in the list page.
5. Select a filter from the pulldown list. (Only Search Group type filters are listed.)
6. Click **Save**.

Saved Searches

A saved search, like a search filter, recalls a specific query. However, in addition to the query, a saved search saves the time range and the field set to display in the search results. Saving the time range supports scheduled searches and reports. You can schedule a Saved Search to run at a specific interval. A scheduled Saved Search can be also configured to generate an alert. For more information, see ["Scheduled Searches/Alerts" on page 317](#).

The Saved Searches page displays all Saved Searches and supports adding, editing, and deleting Saved Searches. You can add a saved search here or directly from the Search page.

Saved Search Page

For information on how to save a search from the Search page, see ["Saving Queries, Creating Saved Searches and Saved Filters." on page 138](#).

For information on how to use the saved searches created on this page, see ["Searching with Saved Queries" on page 144](#).

To add a Saved Search:

Add Saved Search

Name

Search Time Field

Logger Receipt Time

Start time

11/28/2019

19:11:22

☐ Dynamic

End time

11/29/2019

19:11:22

☐ Dynamic

Query

Advanced

Filters

Configuration - Configuration Changes (Unified)
Events - Event Counts by Destination
Events - Event Counts by Source
Events - High and Very High Severity Events (Unified)
Firewall - Deny
Firewall - Drop
Firewall - Permit
Intrusion - Malicious Code (Unified)
Logins - All Logins (Unified)
Logins - Failed Logins

Use ctrl-click to select or deselect items

Local search

☒

Save

Cancel

1. Open the **Configuration | Search** menu and click **Saved Searches**.
2. Click **Add** and enter the following parameters:

| Parameter | Description |
|--------------------|--|
| Name | A name for this Saved Search. This name will be used for exported output files, with the Saved Search date and time appended. |
| Start Time | Absolute date and time of earliest possible event. Alternatively, check Dynamic to specify the start time relative to the time when the Saved Search job is run. |
| End Time | Absolute or Dynamic date and time of latest possible event, as described above. |
| Search Time Fields | Select the search time type: Logger Receipt Time or End Time (Event time). |
| Query Terms | Enter the query in the text field or select one or more Filters from the list below the text field. When you type a query, Logger's Search Helper enables you to quickly build a query expression by automatically providing suggestions, possible matches, and applicable operators. See "Search Helper" on page 104 for more information. |
| Local Search | Check this box to limit the Saved Search to the local Logger box. If the Local Search box is left unchecked, the Saved Search will include all Peer Loggers as well as the local Logger. |

3. Click **Save** to add the new Saved Search, or **Cancel** to quit.

To edit a Saved Search:

1. Open the **Configuration | Search** menu and click **Saved Searches**.
2. Find the Saved Search that you want to edit and click the Edit icon (✎) on that row.
3. Change the information in the form and click **Save**.

To delete a Saved Search:

1. Open the **Configuration | Search** menu and click **Saved Searches**.
2. Find the Saved Search that you want to delete and click the Delete icon (✕) on that row.
3. Confirm the delete.

Scheduled Searches/Alerts

You can schedule a Saved Search to run at a specific interval. A scheduled Saved Search can be configured to generate an alert. The results of a scheduled search are written to a file, as described in ["Saved Search Files" on page 326](#). The results of a scheduled Alert are sent to a specified destination.

The Scheduled Searches/Alerts page displays a list of currently scheduled Saved Searches and Alerts. From here you can add a new Scheduled Search or Alert and manage existing ones. For more information about scheduled Saved Search Alerts, see ["Saved Search Alerts" on page 323](#).

Note: Before you schedule a Saved Search Alert, you must have created at least one Saved Search. Saved searches used in Alerts cannot contain aggregation operators such as chart or top.

To add a new Scheduled Search or Alert:

You can add a new Scheduled Search or Alert from the Configuration menu or directly from the search results page.



- To set up a Scheduled Search Alert from the search results page (**Analyze > Classic Search**), see ["Creating Saved Search Alerts \(Scheduled Alerts\)" on page 323](#).
- To set up a Scheduled Search from the search results page (**Analyze > Classic Search**), follow the instruction in ["Saving Queries, Creating Saved Searches and Saved Filters." on page 138](#), set the Type to **Scheduled Search** and select the **Schedule it** option.
- To set up a Scheduled Search or Alert from the configuration menu (**Configuration | Search > Scheduled Searches/Alerts**), see ["Adding a Scheduled Search or Scheduled Alert" on the next page](#).

To see list of the existing Scheduled Searches and Alerts:


Open the **Configuration | Search** menu and click **Scheduled Searches/Alerts**.

A list of the current Scheduled Searches and Alerts is displayed.



To edit a existing Scheduled Search or Alert:

1. Open the **Configuration | Search** menu and click **Scheduled Searches/Alerts**.
2. Locate the Scheduled Search/Alert that you want to edit and click the Edit icon () on that row.
3. Click the Edit icon () and update the parameters as needed. For details about the settings, see ["To set up a Scheduled Search or Alert from the Scheduled Searches/Alerts page:" on the next page.](#)
4. Click **Save** to update the Scheduled Search/Alert or **Cancel** to abandon your changes.

To remove a Scheduled Search or Alert:

1. Open the **Configuration | Search** menu and click **Scheduled Searches/Alerts**.
2. Identify the Scheduled Search/Alert that you want to remove, and click the Remove icon () on that row.
3. Click **OK** to confirm the removal, or click **Cancel** to keep the Scheduled Search/Alert.

To enable or disable a Scheduled Search or Alert

1. Open the **Configuration | Search** menu and click **Scheduled Searches/Alerts**.
2. Identify the Scheduled Search/Alert that you want to enable.
3. Click the associated icon ( or ) to enable or disable the alert.

To view triggered Alerts:

See ["Viewing Alerts" on page 149.](#)

Adding a Scheduled Search or Scheduled Alert

You can schedule a Saved Search or an Alert to run at any time. Before you schedule a Saved Search or Alert to run, you must have created or saved at least one Saved Search. See ["Saving Queries, Creating Saved Searches and Saved Filters." on page 138.](#)

You can add a new Scheduled Search or Alert from the Configuration menu or directly from the search results page.

- To set up a Scheduled Search Alert from the search results page (**Analyze > Classic Search**), see ["Creating Saved Search Alerts \(Scheduled Alerts\)" on page 323.](#)
- To set up a Scheduled Search from the search results page (**Analyze > Classic Search**), follow the instruction in ["Saving Queries, Creating Saved Searches and Saved Filters." on page 138,](#) set the Type to **Scheduled Search** and select the **Schedule it** option.

To set up a Scheduled Search or Alert from the Scheduled Searches/Alerts page:

1. Open the Configuration | Search menu and click **Scheduled Searches/Alerts**.
2. Click **Add**. A screen like the following is displayed.

The screenshot shows a web form for configuring a scheduled search or alert. The form is divided into several sections:

- Name:** A text input field.
- Schedule:** A dropdown menu set to "Every day", and a "Hour of day" dropdown menu next to a text input field labeled "Hours (24 hour format)".
- Job type:** A dropdown menu set to "Search".
- Saved Searches:** A list box containing the following items: "All Forwarders", "All Receivers", "Configuration Changes by Product", "Failed Logins by Product", "Failed Logins by User", "FieldQueryUtilsSavedSearch", "Firewall Drops by Source", "Individual Forwarders", "Individual Receivers", and "Malicious Code Activity". Below the list is the instruction "Use ctrl-click to select or deselect items".
- Search Result Export Options:**
 - Export Options:** A radio button labeled "Save to Logger" is selected.
 - File format:** A dropdown menu set to "CSV".
 - Export directory name:** A text input field.
 - Fields:** A checkbox labeled "All fields" is checked.
 - Include Event Total:** An unchecked checkbox.
 - Include only CEF events:** An unchecked checkbox.
 - Delete files after:** A text input field followed by the word "days".
- Buttons:** A blue "Save" button and a black "Cancel" button.

3. Enter the following parameters:

| Parameter | Description |
|----------------|--|
| Name | A name for this Scheduled Search. |
| Schedule | Set when and how often you want the report to run. For details about these options, see "Scheduling Date and Time Options" on page 145 . |
| Job Type | Select Search to schedule a Saved Search. Select Alert to schedule a Saved Search Alert. |
| Saved Searches | <p>Select from the list of saved searches. If none of the saved searches suits your needs, click the Saved Searches page to define a new search. Then come back to this page to schedule it. For more information about defining a Saved Search query, see "Saved Searches" on page 315.</p> <p>You can use Ctrl+click to select and remove items from the list.</p> <div>Note: When multiple saved searches are specified in one scheduled search job, the resulting file contains the number of hits for each saved search and not the actual events.</div> <div>Note: You can only select one Saved Search for each Alert you configure.</div> <div>Note: Aggregation operators such as chart and top cannot be included in the search query for Scheduled Alerts. Saved searches that contain aggregation operators are not displayed in the selection list after you specify searches you have created are not displayed in the selection list for Saved Search Alerts.</div> |

4. If you selected the job type Search, specify the Search Result Export Options

Search Job Options

| Parameter | Description |
|-----------------------|---|
| Export Options | <p>For the Logger Appliance:</p> <p>Select from one of these options:</p> <ul style="list-style-type: none"> Export to remote location: The file is written to an NFS mount, a CIFS mount, or a SAN system location that you specify. Save to Logger: The file is saved to the Logger's onboard disk. If the file is saved locally, you can use the Saved Search Files ("Saved Search Files" on page 326) feature to access those files. <p>For Software Logger, the only available option is "Save to Logger," which is preselected for you.</p> <p>Tip: The Logger Appliance supports mounting through the user interface. Software Logger uses its filesystem, which can contain remote locations mounted through the operating system.</p> |
| File Format | <p>Select a format for the exported search results.</p> <ul style="list-style-type: none"> CSV, for comma-separated values file. PDF, for a report-style file that contains search results as charts and in tables. You must specify a title for the report in the Title field. If the search query contains an operator that creates charts such as chart, top, and so on, charts are included in the PDF file. In that case, you can also set the Chart Type and Chart Result Limit fields. These fields are described later in this table. |
| Remote Location | <p>This field is only available on the Logger Appliance. Use the dropdown to select an existing Remote File System location. If there are none, a link to the Remote File System location page is displayed.</p> |
| Export Directory Name | <p>For the Logger Appliance, select the directory where the search results will be exported from the pull-down menu.</p> <p>For Software Logger, enter the directory path in this field, which can be a path to a local directory or to a mount point on the machine on which Software Logger is installed.</p> <p>By default, all saved searches are stored in /opt/arcsight/logger/userdata/logger/user/logger/data/savedsearch.</p> <p>Tip: To group your searches in folders, indicate a subdirectory in which to store them.</p> <p>If a directory of the specified name does not exist, it is created. If a directory of the specified name exists and the Overwrite box is not checked, an error is generated. If the Overwrite box is checked, the existing directory contents are overwritten.</p> |
| Title | <p>(Optional) Enter a title to appear at top of the PDF file. If no title is specified, the default "Untitled" is used.</p> <p>Tip: This field becomes available when you select the PDF output format.</p> |
| Fields | <p>A list of event fields that will be included in the exported file. By default, all listed fields are included.</p> <p>Deselect All Fields to the view and edit the list of fields. Click Clear to remove the listed fields.</p> |

Search Job Options, continued

| Parameter | Description |
|--------------------------------------|--|
| Chart Type (for PDF only) | Type of chart to include in the PDF file. You can select from: Column, Bar, Donut, Area, Line, Stacked Column, Stacked Bar. Note: This option overrides the Chart Type displayed on the Search Results screen. (If the search query includes an operator that creates a chart, this field is meaningful; otherwise, it is ignored.) |
| Chart Result Limit (for PDF only) | The maximum number of unique values to include on the chart. The default is 10. (If the search query includes an operator that creates a chart, this field is meaningful; otherwise, it is ignored.) If the configured Chart Result Limit is less than the number of unique values for a query, the top values equal to the Chart Result Limit are plotted. That is, if the Chart Result Limit is 5 and 7 unique values are found, the top 5 values will be plotted. |
| Include Event Total | Check this box to include an event count with the Saved Search, or a total when more than one Saved Search is specified. |
| Include only CEF Events | Check this box to include only Common Event Format (CEF) events. Uncheck the box to include all events in the output. For more information about CEF, refer to the document "ArcSight CEF." For a downloadable a copy of this guide, search for "ArcSight Common Event Format (CEF) Guide" in the Micro Focus Security Community . |
| Delete Files After | Specify how many days to keep the saved search results. |

- If you selected the job type Alert, specify the Alert Options

Alert Job Options

| Parameter | Description |
|---|---|
| Match count | Number of events that should be matched in Threshold number of seconds for an alert to be triggered. |
| Threshold (sec) | Number of seconds within which the "Match count" events should be matched for an alert to be triggered. |
| Notification destinations are optional. If none is specified, a notification is not sent. | |
| Email address(es) | (Optional) A comma-separated list of email addresses to which the alert will be sent |
| SNMP destination | (Optional) An SNMP destination to which the alert will be sent. For more information, see "SNMP Destinations" on page 392 . |
| Syslog destination | (Optional) A syslog server address to which the alert will be sent. For more information, see "Syslog Destinations" on page 393 . |
| ESM Destination | (Optional) An ArcSight Manager address to which the alert will be sent. For more information, see "Sending Notifications to ESM Destinations" on page 394 . |

- Click **Save** to add the new Scheduled Search/Alert, or Cancel to quit.

7. Once a Scheduled Search is created, enable it as described in ["To enable or disable a Scheduled Search or Alert" on page 318](#).

Saved Search Alerts

This section describes Saved Search Alerts. Saved Search Alerts are based on the search queries that you have saved on Logger. For detailed information about Saved Search queries, see ["Saved Searches" on page 315](#).

Note: For information on Real Time Alerts, see ["Real Time Alerts" on page 383](#). For information on alerts in general, see ["Logger Alert Types" on page 388](#).

For each Saved Search Alert, you configure a match count, threshold, destination, and a schedule at which the alert will be triggered (if specified number of matches occurs within the specified threshold). If the new Alert will send notifications to an email, SNMP, or Syslog Destination, set up the destination before creating the Alert.

See ["Static Routes" on page 461](#), ["Receiving Alert Notifications" on page 390](#), and ["Setting Up Alert Notifications" on page 391](#) for more information. Audit events for alerts are only written to the Internal Storage Group and not forwarded to ESM Destinations by default. If you need to forward these audit events to ESM, please contact customer support for assistance.

Note: This change only applies to audit events generated for alerts; other audit events are can be sent to ESM Destinations.

Note: To ensure system performance, a maximum of 200 alerts are allowed per saved search alert job. Therefore, if a saved search alert job triggers more than 200 alerts, only the first 200 alerts are sent out for that job iteration; the rest are not sent. Additionally, the job is aborted so it does not trigger more alerts for that iteration and the status for that job is marked "Failed" in the Finished Tasks page (**Configuration | Scheduled Tasks > Finished Tasks**). The job runs as scheduled at the next scheduled interval and alerts are sent out until the maximum limit is reached.

This limit does not exist on the real-time alerts.

Creating Saved Search Alerts (Scheduled Alerts)

This section describes how to schedule Saved Searches to run as Scheduled Alerts. For information on creating Real Time Alerts, see ["Creating Real Time Alerts" on page 386](#). For a description of the types of alerts, see ["Logger Alert Types" on page 388](#).


You can schedule a Saved Search to run at any time. Before you schedule a Saved Search Alert, you must have created at least one Saved Search.

Note: Saved searches used in Alerts cannot contain aggregation operators such as chart or top. See ["Saving Queries, Creating Saved Searches and Saved Filters." on page 138](#) for more information.

You can add a new Scheduled Search or Alert from the Configuration menu or directly from the search results page.

- To set up a Scheduled Search Alert from the search results page (**Analyze > Classic Search**), see ["Creating Saved Search Alerts \(Scheduled Alerts\)" on the previous page](#).
- To set up a Scheduled Search from the search results page (**Analyze > Classic Search**), follow the instruction in ["Saving Queries, Creating Saved Searches and Saved Filters." on page 138](#), set the Type to **Scheduled Search** and select the **Schedule it** option.
- To set up a Scheduled Search or Alert from the configuration menu (**Configuration | Search > Scheduled Searches/Alerts**), see ["Adding a Scheduled Search or Scheduled Alert" on page 318](#).

To set up a Saved Search Alert from the search results page:

1. Run a search, as described in ["Searching for Events" on page 108](#).
2. Click the Save icon () and enter the following settings.

| Parameter | Description |
|-------------|--|
| Name | A name for the query you are saving. |
| Save as | To enable the Scheduling option, select Saved Search. |
| Schedule it | Click to schedule now or leave blank to schedule later. |
| Type | Select whether you want to schedule a Search or an Alert. Scheduled searches run on a predetermined schedule and export results to a pre-specified location. Scheduled alerts run a search on a predetermined schedule but only generate an alert if the specified number of events within the specified threshold is found. Select Scheduled Alert to create an Alert. |

3. Click **Save**.

If you checked the "Schedule it" setting in the previous step, you are prompted to choose if you want to edit the schedule. If you click **OK**, the Edit Scheduled Search page is displayed, as shown in the next step. If you click **Cancel**, the search is saved but it is not scheduled to run.

4. The Edit Scheduled Search/Alert page enables you to define a schedule for the saved search job and alert options. Select the desired options, and click **Save**. For details about the parameters, see ["Alert Job Options" on page 322](#).

Add Scheduled Search/Alert

✖ You must specify at least one number between 0 and 23.

| | | | |
|----------------|----------------------------|--|------------------------|
| Name | SavedSearchLogger.job | | |
| Schedule | Every day ▼ | | |
| | Hour of day ▼ | | Hours (24 hour format) |
| Job type | Alert ▼ | | |
| Saved Searches | FieldQueryUtilsSavedSearch | | |

Alert Options

| | |
|--------------------|--------|
| Match count | 4 |
| Threshold (sec) | 60 |
| Email address(es) | |
| SNMP destination | NONE ▼ |
| Syslog destination | NONE ▼ |
| ESM destination | NONE ▼ |

Save **Cancel**

5. After creating the Scheduled Alert, enable it as described in ["To enable or disable a Scheduled Search or Alert" on page 318](#).

Saved Search Files

Access Saved Search results that were saved to Logger with the Saved Search Files command. Saved Search Files can be retrieved (streamed to the browser) or deleted. Click Refresh to update the list of files.

Saved Search Files page

| Scheduled Searches/Alerts | | | | | |
|---------------------------------------|------------------|----------------|---------------|-----------------|---|
| Add | | | | | |
| Task | Type | Schedule | Next Run Time | Destinations | |
| SavedSearchLogger.job | Scheduled search | Daily at 12:00 | Disabled | Saved to Logger | Edit Delete Refresh |

Access the saved search results:

1. Open the **Configuration | Search** menu and click **Saved Search Files**. The files containing the search results are displayed.
2. To download and open a file, click a link in the Name column or click the **Retrieve** icon in the row.

Search Indexes

You can add fields to the field-based index at any time. However, **once a field has been added to the index, you cannot remove it.**

Prerequisites

Users must be assigned to the following User Groups to access this feature:

- Default Logger Rights Group
- Default System Admin Group

See ["Setting Logger User Permissions" on page 510](#) for more information.

Caution Before adding any fields to the index, make sure you are familiar with the information in ["Guidelines for Field-Based Indexing" on the next page](#).

To add fields to the field-based index:

1. Open the **Configuration | Search** menu and click **Search Indexes**.
2. Select the fields from the Indexable Fields list.

To add indexed fields, select one or more fields below

Indexable fields

agentAddress

agentHostName

agentNtDomain

agentZoneURI

customerName

destinationDnsDomain

destinationMacAddress

destinationTranslatedAddress

destinationUserPrivileges

deviceCustomDate1

deviceCustomDate1Label

deviceCustomDate2

deviceCustomDate2Label

deviceCustomNumber1Label

deviceCustomNumber2Label

deviceCustomNumber3Label

Use ctrl-click to select or deselect items

Indexed fields

deviceVendor

deviceProduct

deviceVersion

deviceEventClassId

name

agentSeverity

agentType

applicationProtocol

baseEventCount

bytesIn

Full text indexing is enabled

Apply Changes

Select Recommended Fields

3. To select multiple fields, hold down the Ctrl key down and click the fields.
4. Click **Apply Changes**.

Guidelines for Field-Based Indexing

Make sure you are familiar with these guidelines before you index any fields:

- Events are indexed by the fields in the “Indexed fields” list (on the Search Indexes page) and the default event metadata fields—event time, Logger event, and device address.
- You can index up to 123 fields on Logger. This number includes the custom schema fields you may have added to your Logger.

- Once a field has been added to the index, it cannot be undone.
- Only users belonging to a System Admin Group can add fields to index.
- After you add a field to the index, Logger might not immediately start indexing on that field. Therefore, allow some time between adding a field and using it in the search query. If Logger is in the process of indexing on a field and you use that field to run a search query, the search performance for that operation will be slower than expected.
- If an event field contains data of unexpected type (for example, a string when an integer is expected), the data is ignored. Therefore, search for that data value will not yield any results. For example, if the port field contains a value 8080A (alphanumeric) instead of 8080 (numeric), the alphanumeric value is ignored.
- For faster report generation, ALL fields of a report (including the fields being displayed in the report) need to be indexed. That is, in addition to the fields in the WHERE clause of the query, the fields in the SELECT clause also need to be indexed.
- For optimal search performance, make sure that event fields on ALL peers are indexed for the time range specified in a query. If an event field is indexed on a Logger but not on its peers for a specific time range, a distributed search will run slower on the Loggers. However, it will run at optimal speed on the local Logger. Therefore, the search performance in such a setup will be slow.
- Logger supports indexing of the **requestUrl** field. This field returns website addresses from the World Wide Web. Indexing **requestUrl** will return results faster, but will also significantly increase the size of your search results, which may impact your search storage capacity.

Global Search Options

The Edit Search Options page allows Administrators to configure global search settings for field, full-text, regular expression, and concurrent search options, as well as search display, and field summary options.

To adjust these options, open the **Configuration | Search** menu and click **Search Options**.

Tip: The search options on this page support internationalization (i18n) choices.

Prerequisites

Users must be assigned to the following User Groups to access this feature:

- Default Logger Rights Group
- Default System Admin Group

See ["Setting Logger User Permissions" on page 510](#) for more information.

Setting Global Search Options

The Edit Search Options page allows you to configure global search settings for Logger.

To view or modify Logger global search settings:

1. From the navigation bar, click **Search Options** from the **Configuration | Search** menu. The Edit Search Options page opens.
2. View or modify the settings according to ["Search Option Parameters"](#) below.
3. Click **Save** to retain the changes.

Note: Some of these options will require you to reboot your Logger Appliance or restart your Software Logger.

Search Option Parameters

These parameters configure advanced global search options on the Edit Search Options page. To adjust these options, click **Search Options** from the **Configuration | Search** menu.

Field Search Options

| Option | Description |
|--|---|
| Case sensitive | <p>Default: Yes</p> <p>Controls whether to differentiate between upper- and lower-case characters during a search. When this option is set to No, searching for "login" will find "login," "Login," and "LOGIN".</p> <p>Setting this option to No may affect query performance.</p> <p>Changing the case-sensitivity only applies to the local Logger. Peer Loggers will continue to use their own settings.</p> <p>Full-text search (keyword search) is case insensitive. You cannot change its case sensitivity.</p> <p>Note: You must reboot the Logger Appliance/restart the Software Logger for this change to take effect.</p> |
| Include NULL field value in NOT operator results | <p>Default: No</p> <p>Setting this option to Yes causes queries using the NOT operator to return events where the field value matches the filter criteria or is NULL.</p> <p>The default, No, causes queries using the NOT operator to only return events where the field value matches the filter criteria.</p> <p>Note: You must reboot the Logger Appliance/restart the Software Logger for this change to take effect.</p> |

For more information about field searches, see ["Field-Based Search"](#) on page 80.

Full-text Search Options

| | |
|--------------------------|--|
| Use primary delimiters | <p>Default: Yes</p> <p>Controls whether primary delimiters are applied to an event to tokenize it for indexing.</p> <p>A primary delimiter tokenizes an event for indexing. For example, an event "john doe the first" is tokenized into "john" "doe" "the" "first" using the "space" primary delimiter.</p> <p>The primary delimiters are: space, tab, newline, comma, semi-colon, () [] { } “ *</p> |
| Use secondary delimiters | <p>Default: No</p> <p>Controls whether secondary delimiters are applied to an event to further tokenize a token created by a primary delimiter thus enabling searches that can match a part of a primary token.</p> <p>For example, you can search for "microfocus.com" in http://www.microfocus.com.</p> <p>The secondary delimiters are: period, = : / \ @ - ? # & _ > <</p> |

For more information about full-text searches, see ["Keyword Search \(Full-text Search\)" on page 79](#).

Regular Expression Search Options

| | |
|------------------------------|---|
| Case sensitive | <p>Default: No</p> <p>See "Case sensitive" on the previous page.</p> <p>Note: You must reboot the Logger Appliance/restart the Software Logger for this change to take effect.</p> |
| Unicode case sensitive | <p>Default: No</p> <p>Controls whether events in languages other than English should be compared in a case-sensitive way.</p> <p>Caution: Micro Focus strongly recommends that you do not change this option.</p> <p>Note: You must reboot the Logger Appliance/restart the Software Logger for this change to take effect.</p> |
| Check for canonical equality | <p>Default: No</p> <p>Controls whether events in languages other than English should be compared using locale-specific algorithms.</p> <p>Caution: Micro Focus strongly recommends that you do not change this option.</p> <p>Note: You must reboot the Logger Appliance/restart the Software Logger for this change to take effect.</p> |

For more information about regular expression searches, see ["Regex Helper Tool" on page 103](#).

Search Display Options

| | |
|---|--|
| Populate rawEvent field for syslog events | <p>Default: No</p> <p>Controls whether raw events are displayed in a formatted column called rawEvent using the Raw Event field set. This option applies to syslog events only. If you want to view the raw events associated with CEF events, you do not need to configure this setting. Instead, configure the connector that is sending events to Logger to populate the rawEvent field with the raw event.</p> <p>Note: Even though the rawEvent column displays the raw event, this column is not added to the Logger database and is not indexed. Therefore, you can only run a keyword (full-text) or regular expression search on the event.</p> |
| Show Source and SourceType fields | <p>Default: No</p> <p>Controls whether the Source and SourceType fields are included in the Field Summary and query results. You must reboot the Logger Appliance/restart the Software Logger for this change to take effect.</p> <p>Note: Setting this option to Yes can impact query performance.</p> |

For more information about raw events, see ["Raw Event" Fieldset](#) on page 90. For more information about field summary and query searches, see ["Source Types"](#) on page 367.

Concurrent Search Options

| | |
|-----------------------------|--|
| Expiry time (min) | <p>Default: 10 Range: 1–60</p> <p>Controls how long a completed search remains available in Logger memory before expiring.</p> <ul style="list-style-type: none">• This option controls both single and concurrent search expiry times.• Clicking the Session ID opens the search results in a new tab and resets the expiry time. Using the pagination link (moving through the display pages) for a search also resets the expiry time. |
| Maximum concurrent searches | <p>Default: 0 (unlimited searches) Range: 1–1000</p> <p>Controls how many concurrent searches this Logger can run, including dashboards and Saved searches.</p> <p>Note: If the number of searches is changed from default to another number, the server process must be restarted to implement the change.</p> |

For more information about concurrent searches, see ["Concurrent Searches"](#) on page 112.

Search Hit Limits

| | |
|------------------------|--|
| Max hits of Search UI | <p>Default: 1 000 000 Range: 1–10 000 000</p> <p>Controls the maximum limit of hit results in Logger Search UI.</p> <ul style="list-style-type: none">• Since Logger had a limit of 1 000 000 in previous versions, this value has been set as default. <p>Note: If the number is changed from default to another number, Logger appliance or Software Logger process must be reboot/ restarted to implement the change.</p> |
| Max hits of Search API | <p>Default: 1 000 000 Range: 1–10 000 000</p> <p>Controls the maximum limit of hit results using the API.</p> <p>Since Logger had a limit of 1 000 000 in previous versions, this value has been set as default.</p> <p>Note: If the number is changed from default to another number, Logger appliance or Software Logger process must be reboot/ restarted to implement the change.</p> |

For more information about concurrent searches, see ["Search Hit Limits " on page 112](#)

Field Summary Options

| | |
|-------------------|---|
| Use field summary | <p>Default: Yes</p> <p>Controls the whether the Field Summary panel is included in the search results by default. Regardless of the default, you can change the setting on-the-fly by using the Fields Summary checkbox on the Search screen.</p> |
| Discover fields | <p>Default: No</p> <p>Controls whether the Field Summary feature automatically detects non-CEF fields in raw events. Regardless of the default, you can change the setting on-the-fly by using the Discover Fields checkbox on the Search screen.</p> <p>This field is hidden if Use Field Summary is set to No.</p> |

For more information about the field summary panel, see ["The Field Summary Panel" on page 130](#). For more information about discovering fields, see ["Discovering Fields in Raw Event Data" on page 132](#).

Managing Fieldsets

You can view the predefined fieldsets and the ones you have created on the Fieldsets page (**Configuration | Search > Fieldsets**).

| Fieldsets | | |
|--------------------------------|--------|---|
| Name | Type | Fields |
| Network, Routers, and Switches | System | Event Time, deviceVendor, deviceProduct, name, deviceEventClassId, sourceAddress, sourceHostName, sourcePort, destinationAddress, destinationHostName, destinationPort, transportProtocol, deviceAction, deviceSeverity, deviceAddress, deviceHostName, deviceCustomNumber2Label, deviceCustomNumber2, deviceCustomString2Label, deviceCustomString2, deviceCustomString3Label, deviceCustomString3, deviceCustomString5Label, deviceCustomString5, deviceCustomString6Label, deviceCustomString6, categoryDeviceGroup, categoryBehavior, categoryObject, categoryOutcome, categorySignificance, *user, Raw Message |
| NIDS | System | Event Time, deviceVendor, deviceProduct, name, deviceEventClassId, sourceAddress, sourceHostName, sourcePort, destinationAddress, destinationHostName, destinationPort, fileName, deviceCustomString2Label, deviceCustomString2, deviceCustomString3Label, deviceCustomString3, deviceCustomString4Label, deviceCustomString4, deviceCustomString5Label, deviceCustomString5, deviceCustomNumber1Label, deviceCustomNumber1, deviceAddress, deviceHostName, deviceSeverity, categoryDeviceGroup, categoryBehavior, categoryObject, categoryOutcome, categorySignificance, *user, Raw Message |
| VPN | System | Event Time, deviceVendor, deviceProduct, name, deviceEventClassId, message, deviceAction, sourceAddress, sourceTranslatedAddress, sourceHostName, destinationAddress, destinationHostName, transportProtocol, deviceAddress, deviceHostName, deviceSeverity, sourceUserName, destinationUserName, deviceCustomNumber1Label, deviceCustomNumber1, deviceCustomNumber2Label, deviceCustomNumber2, deviceCustomNumber3Label, deviceCustomNumber3, deviceCustomString1Label, deviceCustomString1, deviceCustomString2Label, deviceCustomString2, deviceCustomString3Label, deviceCustomString3, deviceCustomString4Label, deviceCustomString4, deviceCustomString5Label, deviceCustomString5, deviceCustomString6Label, deviceCustomString6, bytesIn, bytesOut, deviceInboundInterface, deviceOutboundInterface, categoryDeviceGroup, categoryBehavior, categoryObject, categoryOutcome, categorySignificance, *user, Raw Message |

In this list of fieldsets, ***user** indicates user-created fields. An asterisk (*) at the end of the list of fields indicates that more fields are included than are listed.

If you have “Edit, save, and remove fieldsets” privileges, you can delete your custom fieldsets from this screen.

Note: You can only delete the field sets you create, and not the predefined ones available on Logger.

To delete a custom field set:

1. Open the **Configuration | Search** menu and click **Fieldsets**.
2. Identify the field set you want to delete and click the Delete icon (✕).
3. Confirm the deletion.

Default Fields

The Logger schema comes with a set of predefined fields. Some of these fields are already indexed for improved search speed and efficiency. You can add custom fields to Logger's schema and index them for field-based search. A field-based search can only use fields in the schema.

Note: The size of each field in the schema is predetermined. If the string you are searching for is longer than the field-length, you should use a **STARTSWITH** rather than an **=** search, and include no more than the number of characters in the field size. For more information, see “Field-based Search” on page 1.

The Default Fields page (**Configuration | Search > Default Fields**) displays the predefined fields included in the schema. It includes the Display Name, Type, Length, and Field Name for each default field. To view information on existing custom fields, see ["Custom Fields" on the next page](#).

Prerequisites













Users must be assigned to the following User Groups to access this feature:

- Default Logger Rights Group
- Default System Admin Group

See ["Setting Logger User Permissions" on page 510](#) for more information.

To view the default schema fields:

1. From the Configuration menu under Search, click **Default Fields**.

| Display Name | Type | Length | Field Name | Indexed |
|--|------|--------|----------------------|---------|
| agentAddress | TEXT | 46 | agt | - |
| agentHostName | TEXT | 1023 | ahost | - |
| agentNtDomain | TEXT | 255 | agentNtDomain | - |
|  agentSeverity | TEXT | - | agentSeverity | Indexed |
|  agentType | TEXT | 63 | at | Indexed |
| agentZone | TEXT | 200 | agentZone | - |
| agentZoneName | TEXT | 50 | agentZoneName | - |
| agentZoneResource | TEXT | 100 | agentZoneResource | - |
| agentZoneURI | TEXT | 2048 | agentZoneURI | - |
|  applicationProtocol | TEXT | 40 | app | Indexed |
|  baseEventCount | LONG | - | cnt | Indexed |
|  bytesIn | LONG | - | in | Indexed |
|  bytesOut | LONG | - | out | Indexed |
|  categoryBehavior | TEXT | 1023 | categoryBehavior | Indexed |
|  categoryDeviceGroup | TEXT | 1023 | categoryDeviceGroup | Indexed |
|  categoryObject | TEXT | 1023 | categoryObject | Indexed |
|  categoryOutcome | TEXT | 1023 | categoryOutcome | Indexed |
|  categorySignificance | TEXT | 1023 | categorySignificance | Indexed |
|  categoryTechnique | TEXT | 1023 | categoryTechnique | Indexed |

2. The Default Fields page displays the default schema fields. You can sort the fields by clicking the column headers.

Logger displays the Index status of each field in two ways:

- The **Indexed** column shows indexed and superindexed fields.
- The **Display Name** field includes a light green icon (■) for indexed fields, and a dark green icon (■) for superindexed fields. Non-indexed fields have no icon.

Custom Fields

You can view the custom fields that have been added to the Logger schema under Configuration | Search > **Custom Fields**.

| Custom Fields | | | | | | |
|---------------|--------|--------|--------------|-------------------|---------|-----------------------------|
| Display Name | Type | Length | Field Name | Actual Field Name | Creator | Created |
| DoubleField1 | DOUBLE | - | DoubleField1 | ad.DoubleField1.r | admin | Jul 12, 2016 9:36:11 AM PDT |
| Peer_Field | TEXT | 25 | MytextField | ad.MytextField | admin | Jul 12, 2016 9:35:40 AM PDT |

This page lists all custom schema fields that have been saved. You can view the alphabetical list of fields, but cannot edit or delete them. For detailed information about custom fields, see ["Adding Fields to the Schema" on page 431](#).

Running Searches

During the time that a search is running or has not yet expired or been deleted, you can see the details of the search query (but not the search results) from the Running Searches page.

The running searches page displays the following search types:

- A manual search on local or peer Logger (**Analyze > Classic Search**). See ["Running a Search" on page 108](#).
- A scheduled search (**Configuration | Search > Scheduled Searches/Alerts**). See ["Scheduled Searches/Alerts" on page 317](#).
- A saved search alert (**Configuration | Search > Saved Searches**). See ["Saved Searches" on page 315](#).
- A search export, with the "Rerun query" option checked (**Analyze > Classic Search > Export Results**).

This page can be helpful in determining if there is a problem, for example:

- A search is not responding
- A search is taking too long to run
- A search is slowing the overall Logger performance
- When there are too many concurrent searches still in memory.


Prerequisites

You must have admin user privileges to end a running search process. See ["Setting Logger User Permissions" on page 510](#) for more information on Logger user rights and how to administer them.

To view the Running Searches page:

Click **Configure | Search > Running Searches**.


Running Searches List

The list shows the session ID, user who started the tasks, the date and time that the task started, the number of hits, the number of scanned events, the elapsed time, the query, the run status, and a delete icon .

To view the currently running searches:

Open the **Configuration | Search** menu and click **Running Searches**.
Any searches that are currently running are displayed.

To end a currently running search:


1. Open the **Configuration | Search** menu and click **Running Searches**.
2. To end a search process, click the  icon for the task.

Lookup Files

Lookup files are used by the **lookup** search operator to enrich Logger data during a search. After you upload a valid Lookup file to Logger, you can use that Lookup file in a **lookup** search command.

The Lookup Files page displays the uploaded Lookup files.

Lookup Files



| Name | Schema | Row count | Schedule |
|--------------------------------------|--------|-----------|----------|
| There are no lookup files to display | | | |

- For information on when to use the **lookup** operator, see ["Enriching Logger Data Through Static Correlation" on page 146](#).

- For information on how to use the **lookup** operator when searching, see ["lookup" on page 539](#).

Creating Lookup Files

Lookup files must be in CSV format with the Lookup field names as the first row. (A Lookup field is an individual column in the Lookup file.) Each row in the table is loaded sequentially and the first row is treated as the definition of the columns in the table. Any subsequent row that does not contain the same number of comma-separated values as the first row will be skipped during the search by the **lookup** operator. If a search using the **lookup** operator needs to skip one or more rows, a warning message displays on the search page. Micro Focus recommends that you check the table with a tool such as Microsoft Excel to make sure that each row has the same number columns as the header row before uploading it as a lookup file.

Tip: For more information on the CSV format your lookup files need to follow, refer to RFC 4180.

Naming Lookup Files

The Lookup filenames can contain only alphanumeric characters and underscore, and must NOT begin with a number. Do not include **+**, **-**, or ***** in the filename. These characters are reserved for the **lookup** command.

Creating a short and meaningful Lookup filenames make it easy to identify Lookup fields in the output. To help differentiate them from Logger fields, fields from the Lookup file are appended with the first six characters of the Lookup file name when displayed in the search results.

As an example, look at the following search:

```
lookup _table_20160608 ip as src output hostname
```

In this example, "_table_" will be appended to the Lookup field "hostname". The date (**20160608**) will not be included. The name displayed in the search results will be "hostname_table_" because only the first six characters of the Lookup file name are appended.

Naming Fields in the Lookup File

Lookup fieldnames can contain only alphanumeric characters and underscore, and must NOT begin with a number. Do not include **+**, **-**, or ***** in the fieldname. These characters are reserved for the **lookup** command.

Duplicate Values in the Lookup File

When there are multiple rows with identical values in a Lookup column, the lookup operation only uses the first row that matches and ignores any subsequent matches.

When using Logger exported search results as Lookup file, you can use "dedup" operator to remove the duplicate values in the fields that will be used as Lookup fields. For more information on duplication in

Lookup fields, see the **lookup** operator ["lookup" on page 539](#). For more information on the dedup operator, see ["dedup" on page 529](#).

Lookup Capacity

- The maximum size Lookup file that can be uploaded is 50 MB (uncompressed or compressed)
- The maximum disk space allocated for storing Lookup files is 1 GB. This is the cap on overall disk space allowed for storing all Lookup files.
- Maximum number of Lookup entries is 5,000,000 (A Lookup entry is an individual comma-separated value in the Lookup file.)

For example, if a Lookup file has four columns and ten rows, the total number of lookup entries is $4 \times 10 = 40$. When such a Lookup file is used in the search, all of its entries will be loaded into memory. It is worth noting that the maximum number of rows loaded for lookup varies depending on the number of columns in the Lookup file.

For example, if a Lookup file contains 500 columns, the maximum number of rows allowed for lookup will be $5,000,000 / 500 = 10,000$ rows, and any subsequent rows will not be used. On the other hand, if the table has only four columns, the maximum number rows allowed for lookup will be $5,000,000 / 4 = 1,250,000$ rows.

When exporting Logger search results to use them as Lookup files, uncheck **All Fields** and export only the fields you need.

Since there is an overall limit of 5 million lookup entries, exporting only the necessary fields will reduce the number of rows loaded for lookup.

Uploading Lookup Files


Click **Add** on the Lookup Files page to upload a Lookup file in **.csv**, **.zip**, or **.gz** format. You can upload an individual Lookup file from your local desktop or schedule a lookup file to be uploaded regularly from a location accessible to Logger.

Uncompressed files (files uploaded in .csv format) will be compressed into .zip format and stored with the name you specified (**<name>.zip**.) Compressed files will be uploaded and stored in their original compression format with the name you specified (**<name>.zip** or **<name>.gz**.) Upload compressed Lookup files (**.zip** or **.gz**) when possible. This saves upload time and loads more information for the same upload file size. You can only include one Lookup file in .csv format in each **.zip** or **.gz** file.

For information on how to use the **lookup** operator when searching, see ["lookup" on page 539](#).

To add a Lookup file:

1. Open the **Configuration | Search** menu and click **Lookup Files**.
2. Click **Add**. The Add Lookup File page opens.



Add Lookup File

Name

File Location

Lookup File IntellicusReport...enchmarking.zip

3. Enter a meaningful name for the Lookup file. This name can contain only alphanumeric characters and underscore, and must NOT begin with a number. Do not include +, -, or * in the name. These characters are reserved for the **lookup** command.
4. Select where to access the Lookup file.
 - Select **Local** to browse to a location on your local machine and upload the file one time only.
 - Select **On Logger** to enter a path on the Logger's server. If you select this option, you can choose to set up a regular update schedule.

The available options change based on your selection.


5. Specify the Lookup file's location:
 - If you selected **Local**, click **Browse**, navigate to the desired .csv, .zip or .gz file, and then click **Open**.
 - If you selected **On Logger**, specify the absolute path and file name on the Logger system. For example, if the file is in the /opt folder on your Logger you could specify **/opt/lookup.csv**. The lookup file must already exist in this location. The user Logger was installed with must have read permissions on the lookup file itself and on the directory you specify here.

Note: The Logger Appliance supports mounting through the user interface. Software Logger uses its file system, which can contain remote folders mounted through the operating system.

6. If you selected **On Logger**, specify how often to upload the Lookup file.
 - To upload the Lookup file only once, check **One time only**.
 - To schedule the Lookup file to be uploaded now and at regularly scheduled interval, remove the checkmark by **One time only** and then use the schedule options to specify how frequently to update the lookup file. For details about these options, see ["Scheduling Date and Time Options" on page 145](#).
7. Click **Save**. After the Lookup file is uploaded, it will be displayed in the list of Lookup files. If you specified a schedule, the Lookup process will look in the specified location at the indicated time and upload the new version (if there is one).

Managing Uploaded Lookup Files

After you upload a Lookup file, you can view it, edit it or delete it by using the icons at the end of the row for that file.



To view an uploaded Lookup file:

2. Open the **Configuration | Search** menu and click **Lookup Files**.
3. Find the Lookup file you want to view, click the view icon (🔍) or the Lookup file's name.

This view only shows a few rows. The entire file may not be displayed.

Note: The Schedule field is only displayed if the Lookup file has been scheduled for update.

4. Click **Done** to return to the list of Lookup files. You cannot edit the file from here. If you need to change something, follow the steps under "[To edit a Lookup file:](#)" below.


To delete a Lookup file:

2. Open the **Configuration | Search** menu and click **Lookup Files**.
3. Find the Lookup file you want to remove, click the Remove icon (✖) on that row and then click **OK**.

Note: Attempting to remove a Lookup file that is still being used in a current search session will result in an error message. The file will not be deleted. To quickly clear such files from the search cache so that they can be removed, run a search that does NOT use the **lookup** operator. This closes the lookup search session and ensures that the Lookup file is no longer in use. Once the session is closed, you can remove the Lookup file.

To edit a Lookup file:

2. Open the **Configuration | Search** menu and click **Lookup Files**.
3. Find the Lookup file you want to edit, click the Edit icon (✎) on that row and then click **OK**. The Edit Lookup File page opens.



You can upload a new version of the Lookup file, schedule a lookup update, or change the existing update schedule.

4. Select where to access the Lookup file.
 - Select **Local** to browse to a location on your local machine and upload the file one time only.
 - Select **On Logger** to enter a path on the Logger's server. If you select this option, you can choose to set up a regular update schedule.

The available options change based on your selection.

5. Specify the Lookup file's location.
 - If you selected **Local**, click **Browse**, navigate to the desired **.csv**, **.zip** or **.gz** file, and then click **Open**.
 - If you selected **On Logger**, specify the absolute path and file name on the Logger system. For example, if the file is in the /opt folder on your Logger you could specify **/opt/lookup.csv**. The lookup file must already exist in this location.

Note: The Logger Appliance supports mounting through the user interface. Software Logger uses its file system, which can contain remote folders mounted through the operating system.

6. If you selected **On Logger**, specify how often to upload the Lookup file.
 - To upload the Lookup file only once, check **One time only**.
 - To schedule the Lookup file to be uploaded now and at regularly scheduled interval, remove the checkmark by **One time only** and then select a schedule. For scheduling information, see ["Scheduling Date and Time Options" on page 145](#).
7. Click **Save**. After the Lookup file is uploaded, it will be displayed in the list of Lookup files. If you specified a schedule, the Lookup process will look in the specified location at the indicated time and upload the new version (if there is one).

Import Geolocation Files

Geo localization functionality is ready for use in Logger 7.0. Yet, context updates are released every month. To have the most updated geolocation data, user is required to manually import the files to Logger on a monthly basis.

To import files:

User needs to download the file first. For more information, see [ArcSight Context Update Release Notes](#). Once the file has been downloaded and stored in a secure network location, proceed with the following steps:

1. From the Configuration menu, go to import content.
2. Click **choose file** and look for the Arcsight_Context_Update_CurrentMonth_year.xxxxxx.zip package.
3. Click **import**. Logger will display a message acknowledging the request has been completed.
4. Verify the file has been correctly imported in `<loggerInstallation>/config/logger/server/`. A new file named ipdataV6.mmdb should appear.

As new release files are imported into Logger every month, previous release files are automatically renamed using the following format: ipdataV6_year-month.mmbd.

Note: By default, Logger stores a maximum of 4 geolocation files. Any searches with dates outside the time period in store will be executed but only using data of the latest file imported.

To extend file storage:

1. Go to `<LoggerInstallation>/config/logger/logger.defaults.properties`
2. Edit the property `mm.num.old.versions.keep` to `> 4`.
3. Restart the Logger.

Data

The options in the **Configuration | Data** category enable you to control the data going in and out of your Logger.

| | |
|---------------------------------------|-----|
| • Devices | 343 |
| • Device Groups | 345 |
| • Receivers | 346 |
| • Source Types | 367 |

| | |
|---|-----|
| • Parsers | 371 |
| • Forwarders | 376 |
| • Real Time Alerts | 383 |
| • SNMP Destinations | 392 |
| • Syslog Destinations | 393 |
| • Sending Notifications to ESM Destinations | 394 |
| • ESM Destinations | 395 |
| • Certificates | 398 |
| • Forwarding Log File Events to ESM | 399 |
| • Data Validation | 400 |
| • SecureData Decryption | 402 |

Devices

A device is a named event source, comprising of an IP address (or hostname) and a receiver name. Two receivers can receive events from the same IP address, so IP address alone is insufficient to identify a device. Event source is the device that directly sends the event to Logger. When an event is sent through a SmartConnector, the event source is the system on which the SmartConnector is running and not the device that sent the event to the SmartConnector.

Devices can be added to device groups, and device groups can be referenced in filters and queries. Receivers perform **autodiscovery** by automatically creating a device for each source IP address. Devices created by autodiscovery are named for their hostname, or if the hostname cannot be determined, their IP address.

The Devices page displays all defined devices and includes controls to add, edit, or delete them.

Devices page

Maximum number of devices that can be defined on Logger: No limit.

Autodiscovery creates devices automatically, but you can also define them manually.

Add Device

Name

IP Address

0.0.0.0

Receiver

Apache URL Access Error Log ▼

Save

Cancel

To define a device:

1. Open the **Configuration | Data** menu and click **Devices**.
A display similar the ["Devices page" on the previous page](#) appears.
2. Click **Add**.
3. Enter a name, an IP address, and select a receiver for the new device.
4. Click **Save** to add the new device, or **Cancel** to abandon it.

One reason for editing a device is to replace the default name created by autodiscovery (the IP address or hostname) with a more meaningful one.

To edit a device:

1. Open the **Configuration | Data** menu and click **Devices**.
A display similar the ["Devices page" on the previous page](#) appears.
2. Locate the device that you want to edit and click the Edit icon (✎) on that row.
3. Change the Name or IP address for the device.
4. Click **Save** to update the device group, or **Cancel** to abandon your changes.

To delete a device:

1. Open the **Configuration | Data** menu and click **Devices**.
A display similar the ["Devices page" on the previous page](#) appears.
2. Locate the device that you want to delete and click the Remove icon (✖) on that row.
Deleting a device does not block the source IP address from sending events. If new events are received, autodiscovery recreates the device.
3. Confirm the deletion by clicking **OK**, or click **Cancel** to retain the device.

Device Groups


Device groups allow you to categorize named source IP addresses called devices. The Device Groups page lists all device groups with edit and delete icons and includes the ability to create new device groups.

Tip: You can associate Device groups with storage rules. Storage rules specify the storage groups in which event from specific sources are stored. Doing so enables you to retain event data from different sources for different lengths of times (because you can define different retention policies on different storage groups). For more information about storage rules, see ["Storage Rules" on page 407](#).

Tip: There is no maximum number of device groups that can be created on Logger.

To create a device group:

1. Open the **Configuration | Data** menu and click **Device Groups**.
2. Click **Add**. A display similar to that shown below appears.



Add Device Group

You may assign one or more devices to a device group.

If you wish to add a device which is not yet created, you must first go to the [Devices](#) page and create it.

To select or deselect devices, ctrl-click each device name.

Name

Devices

Use ctrl-click to select or deselect items

Save **Cancel**

3. Enter a name for the new device group. Click to select devices from the list. Press and hold the **Ctrl** key when clicking to add additional devices to the selection. To select a range of devices, click to select the first device, then press and hold the **Shift** key while clicking the last device.
4. Click **Save** to create the new device group, or **Cancel** to abandon it.

To edit a device group:

1. Open the **Configuration | Data** menu and click **Device Groups**.
2. Locate the device group that you want to edit and click the Edit icon (✎) on that row.
3. Change the Name, add, or remove devices from the selection. Ctrl-Click devices that are not selected to select them, or Ctrl-Click selected devices to remove them from the selection.
4. Click **Save** to update the device group, or **Cancel** to abandon your changes.

To delete a device group:

1. Open the **Configuration | Data** menu and click **Device Groups**.
2. Locate the device group that you want to delete and click the Remove icon (✕) on that row. Deleting a device group does not affect the set of devices.
3. Confirm the deletion by clicking **OK**, or click **Cancel** to retain the device group.

Receivers

Logger can receive text events, either sent through the network or read from a file. From the Receivers page, you can set up and configure the receivers that will capture event data, and populate each event with information about its origin. Some receivers capture streaming events transmitted over the network by devices, applications, services, and so on. Other types of receivers monitor individual files for events or monitor files selected from a directory tree, based on a pattern you specify. Since receivers can only receive events of a single source type, you should set up separate receivers for each type of log file.

To start receiving events, direct your event sources to the default receivers. For more information about the default receivers, refer to the Logger Installation guide.

Receiver types include UDP, TCP, SmartMessage, and three types of file based receivers, File Transfer, File Receiver, and Folder Follower Receiver.

Before the receiver can receive data, the port it is listening on must be opened through the firewall. For more information, see ["Firewall Rules" on page 522](#).

You can configure the following types of receivers:

- **UDP Receiver:** UDP receivers listen for User Datagram Protocol messages on the port you specify. Logger comes pre-configured with a UDP Receiver on port 514 or 8514, enabled by default. For Software Loggers, this port may vary based on the port numbers available at installation time.
- **CEF UDP Receiver:** UDP receivers that receive events in Common Event Format.
- **TCP Receiver:** TCP receivers listen for Transmission Control Protocol messages on the port you specify. Logger comes pre-configured with a TCP receiver on port 515 or 8515, enabled by default. For Software Loggers, this port may vary based on the port numbers available at installation time.
- **CEF TCP Receiver:** TCP receivers that receive events in Common Event Format.

- **Transformation Hub Receiver:** Transformation Hub receivers are consumers for the Transformation Hub's publish-subscribe messaging system. They subscribe to event topics and receive events in Common Event Format (CEF) from Transformation Hub.
- **File Receiver:** Depending on the type of Logger, file receivers read log files from a local file system, Network File System (NFS), Common Internet File System (CIFS), or Storage Area Network (SAN). File receivers read single or multi-line log files. They provide a snapshot of a log file at a single point in time.
- **Folder Follower Receiver:** Folder follower receivers actively read the log files in a specified directory as they are updated. If the source directory contains different types of log files, you can create a receiver for each type of file that you want to monitor. Logger comes pre-configured with folder follower receivers for Logger's Apache Access Error Log, the system Messages Log, and Audit Log (when auditing is enabled). You must enable these receivers in order to use them.
- **File Transfer:** File Transfer receivers read remote log files using SCP, SFTP, or FTP protocol. These receivers can read single- or multi-line log files. You can schedule the receiver to read a file or batch of files periodically.

Note: Be aware of the following when setting up file transfer receivers.

- The SCP, SFTP, and FTP file transfer receivers depend on the FTP (File Transfer Protocol) SCP (Secure Copy Protocol) and SFTP (SSH file transfer protocol) clients installed on your system. Ensure that the appropriate client is installed on the system before you create the receiver.
- The SCP and SFTP protocols on Logger Appliances are not FIPS compliant.

- **SmartMessage Receiver:** SmartMessage receivers listen for encrypted messages from ArcSight SmartConnectors. Logger comes pre-configured with a SmartMessage receiver with the name "SmartMessage Receiver." To use this receiver to receive events from a SmartConnector, set the **Receiver Name** to be "SmartMessage Receiver" when configuring the SmartConnector's destination. For more information on SmartConnectors, see ["Using SmartConnectors to Collect Events" on page 559](#).

Transformation Hub Receivers

Logger's Transformation Hub receivers connect to Secure Open Data Platform Transformation Hubs and consume all events for the topics that they subscribe to. Loggers receiving events from the Transformation Hub can be part of a pool of Loggers for balanced distribution and redundancy. The events will be distributed among Loggers in the pool in a round-robin fashion. If one Logger in the pool is down, the events will be sent to one of the others.

You can configure multiple Loggers with Transformation Hub receivers that subscribe to the same Event Topic List and belong to the same Consumer Group. Each Logger Transformation Hub receiver in the group will receive events from a different subset of partitions in the topic. The Transformation Hub will balance the partitions between all Transformation Hub receivers configured in the same Consumer Group.

The events are published to the Transformation Hub by ArcSight SmartConnector. When configuring your SmartConnector to send data to an Transformation Hub receiver, use the "Transformation Hub" option.

To configure Transformation Hub receiver using Client Authentication or FIPS, you must set up two way authentication between the Logger and the TH. For information and instructions, see ["Transformation Hub Authentication" below](#). On the other hand, if Transformation Hub is configured using TLS, the user is only required to create the TH receiver and import the certificates; CSR, Sign in, and import are done automatically.

Before using Transformation Hub receivers in appliances, DNS must be configured. For more information, see ["System DNS" on page 459](#).

For more information about ArcSight Transformation Hub, refer to the ArcSight Transformation Hub Administrator's Guide, available for download from the [Micro Focus Security Community](#).

For more information about SmartConnectors, refer to the SmartConnector User's Guide, available for download from the [Micro Focus Security Community](#).

Transformation Hub Authentication

Before configuring an Transformation Hub receiver using Client Authentication, a two-way authentication between the Logger and the Transformation Hub needs to be established. The steps detailed below need to be executed for FIPS as well.

To set up two-way authentication, follow the steps in these sections:

- [Step 1: Generate a CSR on the Logger Side](#)
- [Step 2: Locate Tranformation Hubs Intermediate Certificate and Key](#)
- [Step 3: Sign the Logger CSR on the Transformation Hub](#)
- [Step 4: Move the Signed Certificate File to Logger](#)
- [Step 5: Import the Certificate Chain to the Logger Keystore](#)

Repeat these steps for each Logger that needs to receive data from Transformation Hub. Authentication can be performed for a new Logger at any time.

Step 1: Generate a CSR on the Logger Side

1. Log in to the Logger host using your operating system credentials.
2. Run the **th_cert_tool** script to generate a CSR:

```
th_cert_tool.sh --generate-csr --th-host <FQDN of TH master> --key-length 2048.
```

On the Logger appliance, the script is located in:

```
/opt/arcsight/logger/bin/scripts/th_cert_tool.sh.
```

On Software Logger, the script is located in:

```
<install_dir>/current/arcsight/logger/bin/scripts/th_cert_tool.sh.
```

3. Copy the CSR text file to the Transformation Hub host.

For example: **scp /tmp/csr.csr root@<th_host_ip>:/tmp/.**

Step 2: Locate Transformation Hubs Intermediate Certificate and Key

Obtain TH's intermediate certificate, key and the CA certificate.

1. Self signed certificate for TH is automatically generated during TH installation and it is located in: `/opt/arcsight/kubernetes/ssl/ca.crt` and `ca.key`.
2. If CA-signed certificate is used, acquire TH's intermediate certificate and key issued by the root CA.

Step 3: Sign the Logger CSR on the Transformation Hub

For information, refer to the *ArcSight Transformation Hub Administrator's Guide*.

1. Log in to the Transformation Hub host.
2. Run the following command to sign the CSR:

```
openssl x509 -req -CA <path to intermediate certificate> -CAkey <path to intermediate key> -in /tmp/csr.csr -out /tmp/signedLoggerCert.pem -days 3650 -CAcreateserial -- passin pass <password> -sha256.
```

Step 4: Move the Signed Certificate File to Logger

1. If self-signed certificate is used, copy the signed certificate to the Logger host, for example: `scp /tmp/signedLoggerCert.pem [Logger IP]:/tmp/`.
2. If CA-signed certificate is used, generate the chained certificates by cat: `<path to TH's CA certificate> <path to intermediate certificate> <path to signed certificate> <path to new chained PEM file>`.
After the information is retrieved, copy the chained certificate to Logger: `scp <path to new chained PEM file> [Logger IP]:/tmp/`.

Step 5: Import the Certificate Chain to the Logger Keystore

Note: If you are reusing the same Logger from previous test (Not freshly installed Logger):

1. Remove previous import by using the command:

```
mv <arcsight_home>/user/logger/fips/receiver/bcfks_ks <arcsight_home>/user/logger/fips/receiver/bcfks_ks.bak.
```

2. Restart logger.

1. Log in to the Logger host using operating system credentials. Use the same credentials that were used to generate the CSR.
2. Run the `th_cert_tool` to import the certificate:

On Software Appliance:

```
/opt/arcsight/logger/current/arcsight/logger/bin/scripts/th_cert_tool.sh
```

```
--import-cert --th-host <FQDN of TH master> --cert-path <path to the chained PEM file>
```

On Logger Appliance: **/opt/arcsight/logger/bin/scripts/th_cert_tool.sh --import-cert --th-host <FQDN of TH master> --cert-path <location of cert signed by TH>**

3. Follow the instructions in ["Working with Receivers" on page 353](#) to configure Transformation Hub Receivers for the Transformation Hub. Only one signed certificate is required for each Transformation Hub or Transformation Hub Cluster.
4. Repeat the steps in each section of this topic for all Transformation Hubs that do not have the same CA certificate, from which Logger needs to receive events.

You can now configure Transformation Hub receivers on your Logger.

Import Transformation Hub RE Certificate

The user is required to manually import the Realm External CA (RE CA) certificate exported from the TH cluster prior the Kafka receiver creation. The RE certificate does not change if the Transformation Hub is restarted or redeployed. Any newly generated certificates after restart are trusted by this RE CA enabling the receiver to continue accepting events.

To configure Transformation Hub using TLS, the user is only required to create the TH receiver and import the files as described below; Authentication and Sign in are done automatically. Meanwhile, for Client Authentication, you must set up two way authentication between the Logger as described in ["Transformation Hub Authentication" on page 348](#).

Step 1: Obtain Transformation Hub RE Certificate

1. On Transformation Hub 3.0 SSH console, run the following command to retrieve Transformation Hub RE certificate:

```
/opt/kubernetes/scripts/cdf-updateRE.sh > /tmp/RE.crt
```

2. Copy the **/tmp/RE.crt** obtained from step 1 to Logger box at **/tmp**;

Step 2: Set the environment

1. Set the **ARCSIGHT_HOME** environment variable:
 - Appliance: **export ARCSIGHT_HOME=/opt/arcsight/logger**
 - Software: **export ARCSIGHT_HOME=[logger install directory]/current/arcsight/logger**

For existing Kafka receivers only:

1. In Logger SSH console, look for the previous TH certificate(s) from Logger receiver trust store running the script available at:
 - Appliance: `/opt/arcsight/logger/bin/scripts/keytool_util.sh`.
 - Software: `[Install dir]/current/arcsight/logger/bin/scripts/keytool_util.sh`

Caution: `<verisignserverca>` uses a 1000-bit RSA key which is considered a security risk.

2. Delete the TH certificate(s) from previous step in Logger receiver trust store running the script available at:
`/opt/arcsight/logger/bin/scripts/keytool_util.sh`

Make sure to execute the command as it follows: `./keytool_util.sh receiver delete [alias]`

Step 3: Import the RE Certificate

1. In Logger SSH console, import the new TH RE certificate using the `RE.crt` file copied from TH running the script available at:

`/opt/arcsight/logger/bin/scripts/keytool_util.sh`

Make sure to execute the command as it follows: `./keytool_util.sh receiver importcert [certificate]`

2. Confirm TH FQDN is settled in Logger DNS before creating Kafka receivers in SSL mode in Logger.

For existing Kafka receivers:

Restart the receiver processes available at:

- Appliance: `/opt/arcsight/logger/bin/loggerd restart receivers`
- Software: `[install dir]/current/arcsight/logger/bin/loggerd restart receivers`

File Based Receivers

File based receiver types include File Receivers, File Transfer Receivers, and Folder Follower Receivers. You can set them up as multiline receivers, and configure them to use source types with associated parsers to extract data from captured events.

Note: When a receiver cannot read the file it logs from, such as when the file or folder is deleted or renamed, Logger records a message in `current/arcsight/logger/logs/logger_receiver.log`

Multi-line Receivers

TCP and UDP receivers interpret line break characters, such as `\r` or `\n`, as the end of the event. If the input event contains embedded `\r` or `\n` characters, the event will be treated as more than one event. If your events span more than one line, you may want to use a multi-line receiver. Multi-line receivers include the File Transfer, File Receiver, and Folder Follower Receivers.

A multi-line receiver can read events that span more than one line, such as a server log. You could set up the receiver to handle stack traces reported in the log by reading the entire stack trace as a single event instead of reading each line separately.

When creating a multi-line receiver, you must specify a regular expression that the receiver should use to detect the start of a new event in the log file. Each new event starts where the characters in the log file match the regular expression.

For example, in the following log file, each event starts with a timestamp embedded within square brackets (`[yy-MM-dd HH:mm:ss.SSS]`); therefore, you can use this regular expression to identify each event:

```
^\[\d+-\d+-\d+ \d+:\d+:\d+,\d+\].*
```

```
[2016-06-06 13:11:26,824][INFO][I18N]Locale has not been chosen by the user.  
[2016-06-06 13:11:26,824][ERROR][DirectConnection$ReadChannel]  
java.io.IOException: end of communication channel  
    at com.arcsight.logger.distributed.DirectConnection.a(DirectConnection.java:39)  
    at com.arcsight.logger.distributed.DirectConnection.access$200(DirectConnection.java:19)  
    at com.arcsight.logger.distributed.DirectConnection$ReadChannel.run(DirectConnection.java:85)  
    at java.util.concurrent.ThreadPoolExecutor$Worker.runTask(ThreadPoolExecutor.java:886)  
    at java.util.concurrent.ThreadPoolExecutor$Worker.run(ThreadPoolExecutor.java:908)  
    at java.lang.Thread.run(Thread.java:619)
```

- For multi-line file receivers and file transfer receivers, the regular expression that identifies the beginning of a new event must be specified in the receiver's **Multiline Event Starts With** field.
- For multi-line folder follower receivers, the regular expression that identifies the beginning of a new event must be specified in the **Multiline Event Starts With** field of the **source type** associated with that receiver, rather than in the receiver itself.

For information on creating and using receivers, see ["Working with Receivers" on the next page](#). For information on creating and using source types, see ["Source Types" on page 367](#).

Folder Follower Receivers

When you want to monitor active files as they are updated, use a folder follower receiver. After you set up a folder follower receiver and enable it, it will monitor the specified files in that directory and continuously upload new events to the system. Folder follower receivers recognize file rotation.

Overview of the steps to monitor a directory:

1. Determine the types of logs you need to monitor.
2. Determine whether the out-of-box source types or source type/parser pairs will satisfy your needs. For more information, see ["Source Types" on page 367](#), and ["Parsers" on page 371](#).
If so, proceed to the next step.
If not, create the parsers and source types that you need.
 - a. Select an appropriate parser or set of parser for the log files in the directory you want to follow. If the out-of-box parsers do not provide what you need, create appropriate parsers.
 - b. Assign a source type for each parser. If the out-of-box source types do not provide what you need, create appropriate source types.
3. Create the folder follower receivers required to monitor the logs in the directory, selecting the source type you chose or created, above. For more information, see ["Working with Receivers" below](#).
4. Enable the receivers.
5. Optionally, to forward log file events, set up and configure one or more forwarders. For more information, see ["Forwarders" on page 376](#).

Using Source Types with File Follower Receivers

Logger uses the parser associated with the source type you select for a receiver to extract fields and their respective values from the received events. These fields are parsed at search time. For more information on using source types and parsers, see ["Source Types" on page 367](#), and ["Parsers" on page 371](#).

When creating a file follower receiver, you must select a source type appropriate to monitor a specific type of log file. After you select the source type for the file follower receiver, ensure that the parser associated with it works with your source files.

Events from different versions of the same source type can be in different formats. Similarly, events from different source types of the same vendor might be formatted differently. Therefore, if the source type of your source file does not exactly match the specifications of your source type, the associated parser will not parse events correctly, and the search results will not display any parsed fields.

To confirm whether the source type has a valid parser for your source type, after you have set up the receiver, check whether the incoming events are parsed. To determine this, run a search and review the "parser" field in the search results. The parser used in the search will be displayed in the parser column of the search results. If the event was parsed, this field contains the name of the parser. If the event was not parsed successfully, this field contains "Not parsed." If no parser is defined for the source type or if there is no source type, the field is blank.

Working with Receivers


Several receivers come set up on your system. You can add other receivers as needed. The maximum number of receivers that you can create is limited by system resources—memory, CPU, disk input/output

and possibly network bandwidth. The receiver ports available on your system may vary from the image shown.

Before the receiver can receive data, the port it is listening on must be opened through the firewall. For more information, see ["Firewall Rules" on page 522](#).

Receivers page

Add Receiver



The screenshot shows a web form titled "Add Receiver". It contains two input fields: "Name" (a text box) and "Type" (a dropdown menu). The "Type" dropdown is currently set to "SmartMessage Receiver". Below these fields are two buttons: "Next" (a blue button) and "Cancel" (a white button with a black border).

Before creating a receiver of type File Receiver:

- For the Logger Appliance, set up a Network File System mount. See ["Storage" on page 404](#).
- For Software Logger, the file system from which the log files will be read needs to be mounted on the system on which you have installed Logger.

Note: Before creating a receiver of type File Transfer, ensure that the appropriate SCP, SFTP, and FTP client is installed on your system.

The Logger Appliance supports mounting through the user interface. Software Logger uses its file system, which can contain remote folders mounted through the operating system. Log files can contain one event per line or event messages that span multiple lines separated by characters such as newline (`\n`) or a carriage return (`\r`).

To create a receiver:

1. Open the **Configuration | Data** menu and click **Receivers**.
The ["Receivers page" above](#) displays the current receivers and their status. You can sort the fields by clicking the column headers.
2. Click **Add**.
3. Enter a name for the new receiver. Provide a name that is unique and not likely to be duplicated elsewhere. SmartMessage receiver names are used when configuring the associated ArcSight SmartConnectors.
4. Choose the receiver type. Select UDP Receiver, TCP Receiver, CEF UDP Receiver, CEF TCP Receiver, File Receiver, Folder Follower Receiver, File Transfer, or SmartMessage Receiver. The receiver type

cannot be changed after the receiver is created.

Note: Before you can configure an Transformation Hub receiver, you must set up two way authentication between the Logger and the Transformation Hub. For information and instructions, see ["Transformation Hub Authentication" on page 348](#) ["Transformation Hub Authentication" on page 348](#).

5. Click **Next** to edit receiver parameters.

The fields displayed in the Edit Receiver dialog box vary according to the type of Logger and the type of receiver.

6. Fill in the appropriate fields. Refer to the following tables for field descriptions.

- ["UDP, TCP, CEF UDP, and CEF TCP Receiver Parameters" on the next page](#)
- ["Transformation Hub Receiver Parameters" on page 358](#)
- ["File Receiver Parameters" on page 359](#)
- ["Folder Follower Receiver Parameters" on page 361](#)
- ["File Transfer Receiver Parameters" on page 363](#)
- ["SmartMessage Receiver Parameters" on page 365](#)

7. The **Enable** checkbox is flagged by default, so that the receiver will be enabled immediately after you create. If you do not want to enable the receiver now, click the checkbox to remove the flag. You can enable it later.

8. Click **Save**.

To enable or disable a receiver:



Note: Before enabling the following preconfigured folder follower receivers for Software Logger, ensure that the files are readable by the non-root user that you installed with or specified during installation.

- `/var/log/messages`
- `/var/log/audit/audit.log`

1. Open the **Configuration | Data** menu and click **Receivers**.

The ["Receivers page" on the previous page](#) displays the current receivers and their status. You can sort the fields by clicking the column headers.

2. Locate the receiver that you want to enable or disable.

- If the receiver is currently disabled, click the Disabled icon () to enable it.
- If the receiver is currently enabled, click the Enabled icon () to disable it.

Tip: Wait a few minutes after enabling a receiver before disabling it. Likewise, wait before

enabling a receiver that has just been disabled. Background tasks initiated by enabling or disabling a receiver can produce unexpected results if they are interrupted.

To edit a receiver:

1. Open the **Configuration | Data** menu and click **Receivers**.
The ["Receivers page" on page 354](#) displays the current receivers and their status. You can sort the fields by clicking the column headers.
2. Locate the receiver that you want to update and click the Edit icon (✎) on that row.
The fields displayed in the Edit Receiver dialog box vary according to the type of Logger and the type of Receiver.
3. Edit the appropriate fields. Refer to the following tables for field descriptions.
 - ["UDP, TCP, CEF UDP, and CEF TCP Receiver Parameters" below](#)
 - ["Transformation Hub Receiver Parameters" on page 358](#)
 - ["File Receiver Parameters" on page 359](#)
 - ["Folder Follower Receiver Parameters" on page 361](#)
 - ["File Transfer Receiver Parameters" on page 363](#)
 - ["SmartMessage Receiver Parameters" on page 365](#)
4. Flag the **Enable** checkbox to have the receiver immediately enabled, or remove the flag from the checkbox to enable the receiver later.
5. Click **Save**.

To delete a receiver:

1. Open the **Configuration | Data** menu and click **Receivers**.
The ["Receivers page" on page 354](#) displays the current receivers and their status. You can sort the fields by clicking the column headers.
2. Locate the receiver that you want to delete and click the Remove icon (✖) on that row.
3. Click **OK** to confirm the delete.

UDP, TCP, CEF UDP, and CEF TCP Receiver Parameters

Fill in the following fields when creating or editing UDP Receivers, TCP Receivers, CEF UDP Receivers, and CEF TCP Receivers.

| Parameter | Description |
|-------------|--|
| Name | Enter the name of the Receiver, used for reporting and status monitoring. |
| IP/Host | <p>Select one of the available network connections for the receiver to listen to, or select All to listen on both network connections.</p> <p>Note: If localhost (127.0.0.1) appears in the list, it means that the Logger hostname has not been configured. To configure the hostname, see "Network" on page 458.</p> |
| Port | <p>For the Logger Appliance:</p> <ul style="list-style-type: none"> The default UDP Receiver is pre-configured on port 514. For SmartMessage receivers, configure the SmartConnector for port 443. <p>For Software Logger:</p> <ul style="list-style-type: none"> If you installed Software Logger as a root user, you can use any available port. The default UDP Receiver is pre-configured on port 514. If that port is not available, then the next higher available port is chosen. If you installed Software Logger as a non-root user, you can only use a port numbers greater than 1024. The default UDP Receiver is pre-configured on port 8514. If that port is not available, then the next higher available port is chosen. |
| Encoding | Select a character encoding, such as US-ASCII, Big5, or EUC-KR, from the pulldown list. CEF UDP, CEF TCP, and SmartMessage receivers must use US-ASCII or UTF-8 encoding. |
| Source Type | <p>Select from the pull-down list of log file types, including:</p> <ul style="list-style-type: none"> Apache HTTP Server Access Apache HTTP Server Error Juniper Steel-Belted Radius Microsoft DHCP Log IBM DB2 Audit More options... <p>Additionally, you can define your own source types, based on the needs of your company. See "Source Types" on page 367.</p> <p>A receiver can only receive events of a single source type. Set up separate receivers for each type of log file.</p> <p>Note: CEF TCP and CEF UDP receivers are set to the CEF source type, and cannot be changed. Currently, there is no parser associated with the CEF source type.</p> <p>TCP and UDP created in releases earlier than Logger 5.3 SP1 use the "Other" source type.</p> |

Transformation Hub Receiver Parameters

Fill in the following fields when creating or editing Transformation Hub receivers. For more information, refer to the Transformation Hub Administrator's Guide, and the [Apache Kafka documentation](#).

| Parameter | Description |
|--------------------------------------|---|
| Name | <p>This is a required field.</p> <p>Enter the name of the Transformation Hub receiver.</p> |
| Transformation Hub host (s) and port | <p>This is a required field.</p> <p>Tip: Micro Focus Security ArcSight recommends to use the FQDN rather than the IP address.</p> <p>To use IP address:</p> <ol style="list-style-type: none">1. Enter the IP and connecting port followed by a colon <IP>:<Port>.2. Enter the remaining worker nodes IPs to initially connect to Transformation Hub cluster. <p>Note: Insert a master IP only if it is simultaneously acting as a worker node. Do not add non-worker master nodes, otherwise, an error will be displayed.</p> <p>Tip: For TH using TLS, make sure to include nodes with port 9093 enabled.</p> |
| Event Topic List | <p>This is a required field.</p> <p>Enter the event topics the receiver should subscribe to. Event topic names are case sensitive.</p> <p>Valid Values: Comma separated list of event topics.</p> |
| Retrieve Events from Earliest Offset | <p>This option is only used during the initial configuration.</p> <p>To retrieve all events sent to Transformation Hub that are currently under the retention policy for this topic, set to true. To skip over them and start with the latest events, set to false. In either case, all events received by the Transformation Hub for this topic from now on will be retrieved.</p> <p>The default is true.</p> |
| Consumer Group | <p>Required for the Transformation Hub receiver to receive events. Enter a name that uniquely identifies the Consumer Group this receiver belongs to.</p> <p>When multiple Loggers have Transformation Hub receivers that subscribed to the same topic and belong to the same Consumer Group, each Logger in the group will receive events from a different subset of partitions in the topic. The Transformation Hub will balance the partitions between all Logger configured in the same Consumer Group.</p> <p>Note: You do not need to actually create a Consumer Group anywhere. The Consumer Group is simply a logical grouping of consumers, specified by this field. It must be the same on every Logger in the pool.</p> |

| Parameter | Description |
|---------------------------|--|
| Use SSL/TLS | <p>To enable SSL/TLS encryption, set to true. To send information to this receiver in plain text, set to false.</p> <p>Caution: Micro Focus Security ArcSight recommends that you set this option to true.</p> <p>The default is false.</p> |
| Use Client Authentication | <p>This is a required field.</p> <p>Set this field to true to enable client authentication when establishing a TLS connection with Transformation Hub.</p> <p>The default is false.</p> |
| Enable | To enable the receiver, check this box. |

File Receiver Parameters

Fill in the following fields when creating or editing File Receivers.

| Parameter | Description |
|-------------|--|
| Name | Enter the name of the receiver, used for reporting and status monitoring. |
| RFS Names | <p>Select from the pulldown list of NFS or CIFS mount names. The list also includes attached SANs on Logger models that support SAN.</p> <p>To mount NFS volumes, see "Storage" on page 475. To mount CIFS shares, see "Storage" on page 475. For more information about SAN, see "SAN" on page 478.</p> |
| Folder | <p>Choose "Local" and then specify the directory on your Logger where the remote file system is mounted in the "Folder" field.</p> <p>To mount a remote file system on the system on which you have installed Logger, see its operating system's documentation.</p> |
| Source Type | <p>Select from the pulldown list of log file types, including:</p> <ul style="list-style-type: none">• Apache HTTP Server Access• Apache HTTP Server Error• Juniper Steel-Belted Radius• Microsoft DHCP Log• IBM DB2 Audit• More options... <p>Additionally, you can define your own source type, based on the needs of your enterprise. See "Source Types" on page 367.</p> <p>A receiver can only receive events of a single source type. Set up separate receivers for each type of log file.</p> |

| Parameter | Description |
|--------------------|--|
| Wildcard (regex) | <p>A regular expression (regex) describing the log files to read.</p> <p>This is a regular expression, not a typical file wildcard like <code>*.*</code>.</p> <p>The default is <code>.*</code>, meaning all files.</p> <p>Examples:</p> <p>To include all files ending with <code>.process</code>, you could use: <code>.*\.process</code></p> <p>To monitor only <code>*.properties</code> files, you could use: <code>.*\.properties</code></p> <p>To include only <code>.log</code> files with eight digit filenames, you could use: <code>\d{8}\.log</code></p> <div> <p>Note: Uploading any type of data other than text, including binary files such as <code>.zip</code> or <code>.bin</code>, may prevent Logger from functioning correctly. Use caution when pulling everything from a directory by specifying <code>.*</code> in the Regex field, as you could inadvertently include binary files.</p> </div> |
| Mode | <p>Select one of the following:</p> <ul style="list-style-type: none"> Delete - delete the log file once it has been processed Rename - rename the log file once it has been processed. The file is named by appending the Rename Extension. Persist - Logger remembers which files have been processed and only processes them once. |
| Rename extension | <p>The suffix to append to log files that have been processed.</p> |
| Character encoding | <p>Select a character encoding, such as US-ASCII, Big5, or EUC-KR, from the pulldown list.</p> <div> <p>Note: Configure CEF UDP, CEF TCP, and SmartMessage receivers using only ASCII or UTF-8 encoding. Otherwise, non-CEF events sent to those receivers will be dropped.</p> </div> |
| Delay after seen | <p>Number of seconds to wait after a source file is first seen until it is processed. This allows the entire file to be copied to Logger or (in the case of File Receiver) copied to the remote file system, before processing begins.</p> <p>The default is 10 seconds.</p> <div> <p>Note: For File Transfer Receivers, this parameter should be set to a larger value if large files are expected. The default, 10 seconds, does not allow enough time for a large file, such as 1 GB.</p> </div> |
| Event Time Locale | <p>Select a locale from the pulldown list, such as English (United States), Chinese (Hong Kong), Chinese (Taiwan), and so on.</p> |
| Date/time zone | <p>Required if the timestamp in the log file does not specify a time zone.</p> <p>For File Transfer and File Receivers, this parameter is ignored if either Date/time format or Date/time location regex are blank.</p> <p>On appliance Loggers you can see the time zone configured on the Logger System Admin System Network > Time/NTP tab. Software Loggers use the system time.</p> |

| Parameter | Description |
|-----------------------------|---|
| Event Time Location | <p>A regular expression describing which characters represent the timestamp in the log file. For example:</p> <pre>.*\[(.*?)\].*</pre> <p>This regular expression specifies that the timestamp is found inside the first set of square brackets on each line. The first capturing group (the part of the regex in parentheses) is that part that is then parsed using the Date/time format.</p> <p>The default is no timestamp.</p> |
| Event Time Format | <p>Required if the log file contains timestamps in the same format for each event. If not specified (or if the Date/time location regex is blank), each event in the file will be stamped with the date that the file itself was first seen by Logger (not its file system timestamp).</p> <p>See "Date and Time Specification" on page 365 for a list of formats.</p> <p>The default is no timestamp.</p> |
| Multiline Event Starts With | <p>A regular expression that specifies the start of a new event in a log file. Specify this expression to enable the receiver to read multi-line log files. Each new event starts at the point where the regular expression is matched to the characters in the log file. For example,</p> <pre>^\[\d+-\d+-\d+ \d+:\d+,\d+\].*</pre> <p>This regular expression matches timestamps such as:</p> <pre>[2010-12-06 13:09:46,818]</pre> <p>When this field is left blank, each line in the log file is treated as a single event.</p> <p>The default is each line in the log file is a single event.</p> |

Folder Follower Receiver Parameters

Fill in the following fields when creating or editing Folder Follower Receivers.

| Parameter | Description |
|--------------|--|
| Name | Enter the name of the receiver, used for reporting and status monitoring. |
| Local Folder | Specify the local folder to process. On the Logger Appliance, this field is only available if you select "Local" for the Mount Name. |
| Source Type | <p>Select from the pulldown list of log file types, including:</p> <ul style="list-style-type: none"> • Apache HTTP Server Access • Apache HTTP Server Error • Juniper Steel-Belted Radius • Microsoft DHCP Log • IBM DB2 Audit • More options... <p>Additionally, you can define your own source type, based on the needs of your company. See "Source Types" on page 367.</p> <p>A receiver can only receive events of a single source type. Set up separate receivers for each type of log file.</p> |

| Parameter | Description |
|--------------------|--|
| Wildcard (regex) | <p>A regular expression (regex) describing the log files to read.</p> <p>This is a regular expression, not a typical file wildcard like <code>"*.*"</code>.</p> <p>The default is <code>.*</code>, meaning all files.</p> <p>Examples:</p> <p>To include all files ending with <code>.process</code>, you could use: <code>.*\.process</code></p> <p>To monitor only <code>*.properties</code> files, you could use: <code>.*\.properties</code></p> <p>To include only <code>.log</code> files with eight digit filenames, you could use: <code>\d{8}\.log</code></p> <div> <p>Note: Uploading any type of data other than text, including binary files such as <code>.zip</code> or <code>.bin</code>, may prevent Logger from functioning correctly. Use caution when pulling everything from a directory by specifying <code>.*</code> in the Regex field, as you could inadvertently include binary files.</p> </div> |
| Blacklist (regex) | <p>A regular expression (regex) describing the name of the log files to ignore. Files are not monitored if they match this expression.</p> <p>This is a regular expression, not a typical file wildcard like <code>*.*</code>.</p> <p>Example:</p> <p>To exclude files that end in <code>.txt</code>, you could use: <code>.*\.txt</code></p> <p>To monitor all files except <code>*.txt</code>, you could use: Wildcard: <code>.*</code> Blacklist: <code>.*\.txt</code></p> |
| Character encoding | <p>Select a character encoding, such as US-ASCII, Big5, or EUC-KR, from the pulldown list.</p> <div> <p>Note: Configure CEF UDP, CEF TCP, and SmartMessage receivers using only ASCII or UTF-8 encoding. Otherwise, non-CEF events sent to those receivers will be dropped.</p> </div> |
| Date/time zone | <p>Required if the timestamp in the log file does not specify a time zone.</p> <p>For File Transfer and File Receivers, this parameter is ignored if either Date/time format or Date/time location regex are blank.</p> <p>You can see the time zone configured on the Logger System Admin System Network > Time/NTP tab.</p> <p>Software Loggers use the system time.</p> |

File Transfer Receiver Parameters

Fill in the following fields when creating or editing File Transfer Receivers.

| Parameter | Description |
|------------|--|
| Name | Enter the name of the receiver, used for reporting and status monitoring. |
| Protocol | Select SCP, SFTP or FTP protocol. |
| Port | The port number for the receiver. The default port is 22. |
| IP/Host | Select one of the Logger's network connections for the receiver to listen to, or select All to listen on both network connections. Note: If localhost (127.0.0.1) appears in the list, it means that the Logger hostname has not been configured. To configure hostname, see "Network" on page 458 . |
| User | Enter a user on the host with privileges to view and read the source log files. If the protocol is FTP, you can specify the special user, "anonymous." |
| Password | Enter the password of the specified User. The password must not be empty, even in the case of anonymous FTP (although in this case, the password will be ignored.) |
| File path | Enter the path and the name of the log file(s) to be read. You can use wild cards like ? and * (for example, *.log or Log-?.txt) in the path name and the file name. Separate directories with forward slashes (/). Separate multiple file specifications with commas. Example: /tmp/SyslogData/syslog.log.gz, /security/logs/*/, /security/log?/admin/special/ Note: Uploading any type of data other than text, including binary files such as .zip or .bin, may prevent Logger from functioning correctly. Be sure that any directories you specify do not include binary files. Use caution when pulling everything from a directory by specifying *, as you could inadvertently include binary files. |
| Schedule | Specify when and how often you want the File Transfer to run. If no schedule is specified, the File Transfer will occur just once. For scheduling information, see "Scheduling Date and Time Options" on page 145 . |
| Zip Format | Choose gzip, zip, or none. |

| Parameter | Description |
|--------------------|--|
| Source Type | <p>Select from the pulldown list of log file types, including:</p> <ul style="list-style-type: none"> • Apache HTTP Server Access • Apache HTTP Server Error • Juniper Steel-Belted Radius • Microsoft DHCP Log • IBM DB2 Audit • More options... <p>Additionally, you can define your own source type, based on the needs of your enterprise. See "Source Types" on page 367.</p> <p>A receiver can only receive events of a single source type. Set up separate receivers for each type of log file.</p> |
| Character encoding | <p>Select a character encoding, such as US-ASCII, Big5, or EUC-KR, from the pulldown list.</p> <div> <p>Note: Configure CEF UDP, CEF TCP, and SmartMessage receivers using only ASCII or UTF-8 encoding. Otherwise, non-CEF events sent to those receivers will be dropped.</p> </div> |
| Delay after seen | <p>Enter the number of seconds to wait after a source file is first seen until it is processed. This allows the entire file to be copied to Logger or (in the case of File Receiver) copied to the remote file system, before processing begins.</p> <p>The default is 10 seconds.</p> <p>For File Transfer Receivers, this parameter should be set to a larger value if large files are expected. The default, 10 seconds, does not allow enough time for a large file, such as 1 GB.</p> |
| Event Time Locale | <p>Select a locale from the pulldown list, such as English (United States), Chinese (Hong Kong), Chinese (Taiwan), and so on.</p> |
| Date/time zone | <p>Enter the date/time zone. For more information, see "Date and Time Specification" on the next page.</p> <p>Required if the timestamp in the log file does not specify a time zone.</p> <p>For File Transfer and File Receivers, this parameter is ignored if either Date/time format or Date/time location regex are blank.</p> <p>You can see the time zone configured on the Logger System Admin System Network > Time/NTP tab.</p> <p>Software Loggers use the system time.</p> |

| Parameter | Description |
|-----------------------------|---|
| Event Time Location | <p>A regular expression describing which characters represent the timestamp in the log file. For example:</p> <pre>.*\[(.*)\].*</pre> <p>This regular expression specifies that the timestamp is found inside the first set of square brackets on each line. The first capturing group (the part of the regex in parentheses) is that part that is then parsed using the Date/time format.</p> <p>The default is no timestamp.</p> |
| Event Time Format | <p>Required if the log file contains timestamps in the same format for each event. If not specified (or if the Date/time location regex is blank), each event in the file will be stamped with the date that the file itself was first seen by Logger (not its file system timestamp).</p> <p>See "Date and Time Specification" below for a list of format specifiers.</p> <p>The default is no timestamp.</p> |
| Multiline Event Starts With | <p>A regular expression that specifies the start of a new event in a log file. Specify this expression to enable the receiver to read multi-line log files. Each new event starts at the point where the regular expression is matched to the characters in the log file. For example:</p> <pre>^\[\d+- \d+- \d+ \d+: \d+, \d+ \].*</pre> <p>This regular expression matches timestamps such as:</p> <pre>[2010-12-06 13:09:46,818]</pre> <p>When this field is left blank, each line in the log file is treated as a single event.</p> <p>The default is each line in the log file is a single event.</p> |

SmartMessage Receiver Parameters

Fill in the following fields when creating or editing SmartMessage Receivers.

| Parameter | Description |
|-----------|---|
| Name | Enter the name of the receiver, used when configuring an associated ArcSightSmartConnector. |
| Encoding | Select a character encoding, such as US-ASCII, Big5, or EUC-KR, from the pulldown list. Note: Configure CEF UDP, CEF TCP, and SmartMessage receivers using only ASCII or UTF-8 encoding. Otherwise, non-CEF events sent to those receivers will be dropped. |

Date and Time Specification

To specify the date and time format so that it can be parsed from a file receiver, (File Receiver, Folder Follower Receiver, or File Transfer), refer to the table ["Date/Time Format Specification" on the next page](#). Internally, Logger uses a common Java method called SimpleDateFormat. Sophisticated uses of SimpleDateFormat, as described in Java sources, will work with Logger. Pattern letters are usually repeated, as their number determines the exact presentation.

The following examples show how date and time patterns are interpreted in the U.S. locale. The given date and time are July 4th 2013, at 12:08:56 local time, in the “U.S. Pacific Time” time zone.

Date/Time Examples

| Source | Date and Time Pattern |
|--------------------------------------|-------------------------------|
| 2013.07.04 AD at 12:08:56 PDT | yyyy.MM.dd G 'at' HH:mm:ss z |
| Wed, Jul 4, '13 | EEE, MMM d, 'yy |
| 12:08 PM | h:mm a |
| 12 o'clock PM, Pacific Daylight Time | hh 'o'clock' a, zzzz |
| 0:08 PM, PDT | K:mm a, z |
| 2013.July.04 AD 12:08 PM | yyyyy.MMMMMM.dd GGG hh:mm aaa |
| Wed, 4 Jul 2013 12:08:56 -0700 | EEE, d MMM yyyy HH:mm:ss Z |
| 130704120856-0700 | yyMMddHHmmssZ |
| 2013-07-04T12:08:56.235-0700 | yyyy-MM-ddTHH:mm:ss.SSSZ |

Date/Time Format Specification

| Symbol | Meaning | Presentation | Examples |
|--------|-------------------------|--------------|-------------------|
| G | Era designator | (Text) | AD |
| y | Year | (Number) | 2013 or 13 |
| M | Month in year (1-12) | (Month) | July or Jul or 07 |
| w | Week in year (1-52) | (Number) | 39 |
| W | Week in month (1-5) | (Number) | 2 |
| D | Day in year (1-366) | (Number) | 129 |
| d | Day in month (1-31) | (Number) | 10 |
| E | Day in week | (Text) | Tuesday or Tue |
| F | Day in week of month | | |
| a | Am/pm marker | (Text) | AM or PM |
| H | Hour in day (0-23) | (Number) | 0 |
| k | Hour in day (1-24) | (Number) | 24 |
| K | Hour in am/pm (0-11) | (Number) | 0 |
| h | Hour in am/pm (1-12) | (Number) | 12 |
| m | Minute in hour (0-59) | (Number) | 30 |
| s | Second in minute (0-59) | (Number) | 55 |

Date/Time Format Specification, continued

| Symbol | Meaning | Presentation | Examples |
|--------|---------------------|--------------|---|
| S | Millisecond (0-999) | (Number) | 978 |
| z | Time zone | (Text) | Pacific Standard Time, or PST, or GMT-08:00 |
| Z | Time zone | (RFC 822) | -0800 (indicating PST) |

Source Types

Source types identify the kind of event that comes from a specific data source. For example, an event could come from an Apache access log, a simple syslog, or the log of an application you created. You can use parsers to parse event data from a specified source type.

Once events are associated with a source type, if the source type is associated with a parser, the events are parsed by that parser when you run a search that matches those events. The search result displays the matching parsed event fields in columns, similar to the CEF events. (Use the "User Defined Fields" field set to view these events.) For more information, see ["Parsers" on page 371](#).

The source of the event, the source type, and the parser will be displayed in the column list of the search results if any row is fetched from a search that contains a non-CEF source type.

Prerequisites

Users must be assigned to the following User Groups to access this feature:

- Default Logger Rights Group
- Default System Admin Group

See ["Setting Logger User Permissions" on page 510](#) for more information.

The following columns are displayed in the search results when a source type is used:

- **Source:** The name of the log file from which the event was received.
For example, `/opt/mnt/testsoft/web_server.out.log`. If no source was applied when the event was received, this field is blank. You can control whether this field is displayed from the Search Options page. See ["Global Search Options" on page 328](#) for how to set this option.
- **Source Type:** The type of file from which the event was received, as defined on the Source Type page (**Configuration | Data > Source Types**). If no source type was applied when the event was received, this field is blank. You can control whether this field is displayed from the Search Options page. See ["Global Search Options" on page 328](#) for how to set this option.
- **Parser:** If the event was parsed, this field contains the name of the parser. If the event was not parsed successfully, this field contains "Not parsed." If no parser is defined for the source type or if there is no source type, the field is blank.

Working with Source Types

Logger provides a number of source types with pre-configured parsers. Additionally, you can define new source types and assign parsers to them. This lets you choose the set of fields you want to extract for a given kind of event. Only one parser can be associated with a source type, however, multiple source types can be associated with a parser. Out-of-box source types cannot be edited or deleted, but you can copy them to make similar source types to meet your needs. You can edit or delete custom source types, as desired. The source types available on your Logger may vary from the image below.

Source Types page

Add Source Type

If a parser that you need does not exist in the Parser dropdown list below, go to the [Parsers](#) page to add it.

| | |
|---|--|
| Name | <input type="text"/> |
| Description | <input type="text"/> |
| Parser | <input type="text" value="NONE"/> |
| Event Time Location | <input type="text"/> |
| Event Time Format | <input type="text"/> |
| Multiline Event Starts With | <input type="text"/> |
| Locale | <input type="text" value="English (United States)"/> |
| <input type="button" value="Save"/> <input type="button" value="Cancel"/> | |

The following source types have associated parsers:

| Source type | Description |
|----------------|----------------------------|
| Apache_access | Apache Access Log |
| Apache_error | Apache Error Log |
| audit_log | Syslog for Audit Log files |
| Bluecoat_proxy | Bluecoat Proxy SG |
| Cisco_PIX | Cisco PIX |
| IBM_DB2 | IBM DB2 9.x Audit Log |
| Juniper_NSM | Juniper NSM 2009 Syslog |

| Source type | Description |
|------------------|---|
| logger_syslog | Syslog for syslog files on Logger Appliance |
| Microsoft_DHCP | Microsoft DHCP for 2008 v6 log files |
| syslog | Simple Syslog |
| TippingPoint_SMS | Tipping Point SMS 2.5 Syslog |
| VMware_ESX | VMware ESX Syslog |

Logger can forward an event to ESM by using a Connector forwarder, which then forwards it to a Streaming Connector. This connector normalizes the event and forwards it to ESM.

If you need forward events to ESM by using a Connector forwarder, you must choose one of the following source types:

| Source Type | |
|---------------------------|-----------------------------|
| Apache HTTP Server Access | Juniper Steel-Belted Radius |
| Apache HTTP Server Error | Microsoft DHCP Log |
| IBM DB2 Audit | Other |

To add a source type:

1. Open the **Configuration | Data** menu and click **Source Types**.
The ["Source Types page" on the previous page](#) displays the current source types. You can sort the fields by clicking the column headers.
2. Click **Add**


- Fill in the fields to define the source type:

Source Type Fields

| Field | Description |
|-----------------------------|--|
| Name | The name of the source type. |
| Description | A description of the source type. |
| Parser | The parser you want to associate with this source type. If the parser you need does not appear in the drop-down list, you can add one. For information on how to add a parser, see "Parsers" on the next page . |
| Event Time Location | <p>A regular expression describing the timestamp in the log file. For example:</p> <p><code>.*\[(. *?)\].*</code></p> <p>This expression specifies that the timestamp is found inside the first set of square brackets on each line. The first capturing group (the part of the regex in parentheses) is the part that is then parsed using the Date/time format.</p> <p>You can specify that there is no timestamp in the log file with <code>' '</code>.</p> |
| Event Time Format | <p>A regular expression describing the date and time format in the log file. For example,</p> <p><code>dd/MMM/yyyy:HH:mm:ss Z</code></p> <p>You can specify that there is no timestamp in the log file with <code>' '</code>.</p> <p>For more information about event time, see "Time Range" on page 86 and "Date and Time Specification" on page 365.</p> |
| Multiline Event Starts With | A regular expression describing how to recognize when adjacent lines are of the same event or when a new event starts. For example if each event starts with the date in the format, yy-MM-dd HH:mm:ss.SSS you could use <code>(\d+-\d+-\d+ \d+:\d+:\d+.\d+)</code> to indicate the start of a new event. |
| Locale | Select a locale from the pulldown list, such as English (United States), Chinese (Hong Kong), Chinese (Taiwan), and so on. This is locale of the data Logger should find in the file. |

- Click **Save**.

To edit a source type:


- Open the **Configuration | Data** menu and click **Source Types**.
The ["Source Types page" on page 368](#) displays the current source types. You can sort the fields by clicking the column headers.
- Locate the source type that you want to update and click the Edit icon () on that row.

Note: The Edit icon () is not available for out-of-box source types. You can copy the source type and make a similar one instead.


- Edit the fields as appropriate.
See the table ["Source Type Fields" above](#) for field details.
- Click **Save**.
- Disable and then re-enable any receivers that use this source type.


Note: Changes in source type are not reflected in the associated receivers until you have re-enabled them.

To copy a source type:

1. Open the **Configuration | Data** menu and click **Source Types**.
The ["Source Types page" on page 368](#) displays the current source types. You can sort the fields by clicking the column headers.
2. Locate the source type that you want to copy and click the Copy icon () on that row.
3. Enter a name for the new source type and edit the fields as appropriate.
See the table ["Source Type Fields" on the previous page](#) for field details.
4. Click **Save**.

To delete a source type:

1. Open the **Configuration | Data** menu and click **Source Types**.
The ["Source Types page" on page 368](#) displays the current source types. You can sort the fields by clicking the column headers.
2. Locate the source type that you want to delete and click the Remove icon () on that row.

Note: The Remove icon () is not available for out-of-box source types. You can only remove source types that you added.

3. Click **OK** to confirm the removal.

Parsers

Parsers enable you to extract and manipulate raw events (non-CEF data) from different sources in your network environment. Once you have parsed event fields, you can easily search for data, chart it, and perform other operations on it. One user with in-depth knowledge of the events can create the parser, and then all users who look at those events will get the benefit of that work.

Parsers provide you with a simple way to read events. Instead of looking at raw event data and trying to figure out what it means, you can use a parser to extract portions of non-CEF events into fields. However, the fields created by the parser are available only for search operations, and are not added to the Logger schema.

You can use a parser either of the following ways:

- **Use the parser with a source type:** You can associate the parser with a source type to extract any set of fields in any kind of event. For more information, see ["Source Types" on page 367](#).

- **Use the parse command in a search:** During a search, you can use the parse command to extract fields from events and use other search operators (such as where, chart, top, and so on) to further refine the search or manipulate the data in the fields. This is particularly useful for IT operations and other customers who need to extract and manipulate raw event data.

Prerequisites

Users must be assigned to the following User Groups to access this feature:


- Default Logger Rights Group
- Default System Admin Group

See ["Setting Logger User Permissions" on page 510](#) for more information.

Using Parsers with Source Types

Logger provides a number of pre-configured parsers with associated source types. You can also define new parsers and associate them with source types. Only one parser can be associated with a source type, however, multiple source types can use the same parser. Out-of-box parsers cannot be edited or deleted, but you can copy them to make a similar parser to meet your needs. You can edit or delete custom parsers as desired.

Add Parser

A screenshot of the 'Add Parser' form. It features a light gray header with the title 'Add Parser' in bold. Below the header is a horizontal line. The form contains two input fields: 'Name' with an empty text box, and 'Parser Type' with a dropdown menu showing 'Rex Parser' and a downward arrow. At the bottom of the form are two buttons: a blue 'Save' button and a white 'Cancel' button with a black border.

Name

Parser Type Rex Parser ▼

Save **Cancel**

Using the Parse Command

The **parse** command can be used to invoke a parser on any non-CEF events that are returned by a search. It applies the definition of the parser, such as the regular expression of a rex parser, to each event. Then it adds the fields that are extracted by that regular expression to the fields that are being passed through. For a REX parser, this is functionally the same as having a rex command with the same regular expression as the definition of the parser, so you can think of a REX parse command as invoking a saved rex expression.

For more information about the **parse** command, see ["parse" on page 544](#). For information about searching in general, see ["Searching and Analyzing Events" on page 71](#).

Working with Parsers

You can define two types of parsers—a REX parser or an Extract parser. Before adding the parser, you need to define the query you want to use for parsing events.

For a Rex parser, one way to do this is to use the rex search operator to test and adjust a regular expression until it returns the desired fields from the events that you want it to handle. Then copy the rex expression and paste it into the parser's **Definition** field. For an Extract parser, use the extract operator. For more information about the search operators, see ["parse" on page 544](#), ["rex" on page 549](#), and ["extract" on page 535](#).

The parser used in a search will be displayed in the Parser column of the search results. If the event was parsed, this field contains the name of the parser. If the event was not parsed successfully, this field contains "Not parsed." If no parser is defined for the source type or if there is no source type, the field is blank.

Prerequisites

Users must be assigned to the following User Groups to access this feature:

- Default Logger Rights Group
- Default System Admin Group

See ["Setting Logger User Permissions" on page 510](#) for more information.

To add a parser:

1. Open the **Configuration | Data** menu and click **Parsers**.

The Parsers page, shown in ["Parsers" on page 371](#), displays the current parsers. You can sort the fields by clicking the column headers.

2. Click **Add**.
3. Enter a name for the parser.
4. Choose the Parser Type from the drop-down list.
5. Click **Save**.

The fields display in the **Edit Parser** dialog box according to the type of parser.

6. Fill in the fields for the parser.

Parser Fields

| Field | Description |
|-----------------------------|--|
| Name | The name of the parser. Enter a new name if you want to change the existing name. |
| Description | A meaningful description of the purpose of the parser. |
| Rex parsers only | |
| Definition | The rex expression that you want to use to parse events. |
| Extract parsers only | |
| Pair Delimiter | The characters separate key/value pairs within an event. Enter only the separator characters, for example: <code>\ ,</code> |
| Key/Value Delimiter | The characters that separate the key from the value. Enter only the delimiter character, for example: <code>=</code> |
| Fields | The list of field names to use when parsing events. Enter the field names, separated by comma (.). For example, to parse events like: foo=abc, bar=xyz, baz=def Enter: foo,bar,baz |


7. Click **Save**.

To edit a parser:

1. Open the **Configuration | Data** menu and click **Parsers**.

The Parsers page, shown in ["Using Parsers with Source Types" on page 372](#), displays the current parsers. You can sort the fields by clicking the column headers.

2. Locate the parser that you want to update and click the Edit icon () on that row.

Note: The Edit icon () is not available for out-of-box parsers. You can copy the parser and make a similar one instead.

3. Edit the parser fields as appropriate.


The fields displayed in the Edit Parser dialog box according to the type of parser. Parser fields are documented in the table ["Parser Fields" above](#).

4. Click **Save**.


To copy a parser:

1. Open the **Configuration | Data** menu and click **Parsers**.

The Parsers page, shown in ["Using Parsers with Source Types" on page 372](#), displays the current parsers. You can sort the fields by clicking the column headers.

2. Locate the parser that you want to copy and click the Copy icon () on that row.
The fields displayed in the Edit Parser dialog box according to the type of parser.
3. Enter a name for the new parser and edit the fields as appropriate.
Parser fields are documented in the table ["Parser Fields" on the previous page](#), above.
4. Click **Save**.

To delete a parser:

1. Open the **Configuration | Data** menu and click **Parsers**.
The Parsers page, shown in ["Using Parsers with Source Types" on page 372](#), displays the current parsers. You can sort the fields by clicking the column headers.
2. Locate the parser that you want to delete and click the Remove icon () on that row.

Note: The Remove icon () not available for out-of-box parsers. You can only remove parsers that you added.

3. Click **OK** to confirm the removal.

Tip: Be cautious when deleting a parser. Logger doesn't warn you when you modify or delete a parser that is associated with a Source Type.

Example: Creating an Extract Parser

Suppose you want to create a parser to find the contents of the INT, MAC, DST, and SRC fields of a log like the one below.

```
Jul 12 14:30:31 n15-214-128-h92 kernel: IN=eth2
MAC=00:24:e8:60:cb:82:00:50:56:92:2a:d5:08:00 SRC=192.0.2.9 | DST=192.0.2.2
LEN=52 TOS=0x00 PREC=0x00 TTL=128 ID=21408 DF PROTO=TCP SPT=56978 DPT=443
WINDOW=8192 RES=0x00 SYN URGP=0
Jul 12 14:30:31 n15-214-128-h92 kernel: IN=eth2 |
MAC=00:24:e8:60:cb:82:00:50:56:92:2a:d5:08:00 | SRC=192.0.2.9 | DST=192.0.2.2
LEN=52 TOS=0x00 PREC=0x00 TTL=128 ID=21408 DF PROTO=TCP SPT=56978 DPT=443
WINDOW=8192 RES=0x00 SYN URGP=0
Jul 12 14:30:31 n15-214-128-h92 kernel: IN=eth2 |
MAC=00:24:e8:60:cb:82:00:50:56:92:2a:d5:08:00 | SRC=192.0.2.9 | DST=192.0.2.2
LEN=52 TOS=0x00 PREC=0x00 TTL=128 ID=21408 DF PROTO=TCP SPT=56978 DPT=443
WINDOW=8192 RES=0x00 SYN URGP=0
```

In this sample log, the field values are indicated with an equal sign (=), and fields are delimited by pipe (|) and colon (:). You could use the following query to search for the contents of the IN, MAC, DST, and SRC fields.

```
extract pairdelim= "|" kvdelim= "=" fields= "IN,MAC,DST,SRC"
```

The following steps describe how to make an extract parser using that query.

To create an example extract parser:

1. Open the Configuration | Data menu and click **Parsers**.
2. Click **Add**. The Add Parser dialog box opens.
3. Enter a Name and select the Parser Type. For the example, enter:
Name: **Sample_Extract_Parser**
Parser Type: **Extract Parser**
4. Click **Save**. The Edit parser dialog box opens.

Edit Parser

Name: Syslog parser

Description: Sample Extract Parser

Definition: `(?<priority>\d+)>)?(?<timestamp>\w{3}\s*\w{0,3}\s*\d+ \d{0,4}\s?\S{8})\s*(?<DeviceHostName>[^\s:]*)?(?<message>.*)`

Save **Cancel**

5. Enter the Pair Delimiter, Key value, and Fields for the parser. For the example, enter:
Pair Delimiter: `\|`:
Key/Value Delimiter: `=`
Fields: **INT, MAC, DST, SRC**

Note: You need to escape the pipe (|) and the colon (:) with a backslash (\).

6. Click **Save**. The Parsers page displays the new parser.

Forwarders

Forwarders send all events, or events that match a particular filter, on to a particular host or destination such as ArcSight Manager.

The ability to define a different filter for each forwarder allows Logger to divide traffic among several destinations. For example, because Logger can handle much higher event rates than ArcSight Manager,

Logger might be used to forward events to a number of ArcSight Managers. Forwarder filters make it possible to split the flow between the Managers, using one forwarder for each Manager. Additionally, forwarding enables you to send a subset of events to other destinations for further processing while maintaining all events on Logger for long-term storage.

The forwarding filter is a query that searches for matching events, optionally within a time range. You can create two types of forwarder filters—**continuous** and **time-range bound**.

- A **continuous** filter constantly evaluates the incoming events and forwards the matching ones to the specified destination.
- A **time-range bound** filter uses a time range in addition to the specified condition to determine whether an event should be forwarded to the destination. If the event falls within the specified time range and matches the specified condition, it is forwarded; otherwise, it is not. The Logger receipt time of an event is used to determine whether an event will be forwarded to a destination when a forwarder filter specifies a time range by which events are evaluated for forwarding. Once a forwarder has forwarded all events within a time range, it does not forward any more events.

A forwarder only forwards events from the Logger that it is configured on; it cannot forward events from peers.

A forwarder's operation can be paused and resumed at any point in time. When a forwarder resumes operation, forwarding resumes from the last checkpoint that was established before the forwarding operation was paused.

You can also disable and re-enable a forwarder. When you re-enable a forwarder, all previously established checkpoints are removed and forwarding starts over again as per the forwarder configuration—forwarders with continuous filters start from the current time, while forwarders with time-range bound filters start from beginning of the configured time range.

Forwarder types include UDP Forwarder, TCP Forwarder, Connector Forwarder, and ArcSight ESM Forwarder:

- **UDP Forwarder**: UDP forwarders forward events by using the User Datagram Protocol.
- **TCP Forwarder**: TCP forwarders forward events by using the Transmission Control Protocol.
- **Connector Forwarder**: Connector forwarders send events to the Logger Streaming Connector.
- **ArcSight ESM CEF Forwarders**: ArcSight ESM CDF forwarders send Common Event Format (CEF) events to an ESM Destination. The built-in connector on Logger is used to forward these events to ESM.

Note: In order to create an ArcSight ESM forwarder, you must first create an ESM Destination. See ["ESM Destinations" on page 395](#) for more information.

As a best practice, do not add more than ten regular expression forwarders. Even though each additional forwarder improves the forwarding rate, the relation is not proportional. In high EPS (events per second) situations or situations where other resource-intensive features are running in parallel (alerts, reports, and several search operations) and the forwarding filter is complex, adding too many forwarders may reduce

performance because forwarders have to compete for the same Logger resources besides competing for the same built-in connector for forwarding.

You can specify a regular expression or an indexed search query (Unified Query) for the filter. Doing so enables you to take advantage of the indexing technology to quickly and efficiently search for events to forward.

Note: Unified query-based forwarders forward events once they have been indexed. Therefore, these forwarders can exhibit “bursty” behavior because indexing occurs in batches on Logger. You might notice the bursty behavior in the EPS out bar gauge (on top of the Logger interface screen)—the bar gauge will display high EPS level as a burst of data is forwarded and then drop back to normal level.

To create a forwarder:

1. Open the **Configuration | Data** menu and click **Forwarders**.
2. Click **Add** to display the following form.
3. Enter a name for the new forwarder. Provide a name that is unique and not likely to be duplicated elsewhere. For example, if you create an Alert called "MyTest" and a forwarder called "MyTest," you will get an error message asking for a unique name.
4. Choose the forwarder type appropriate for your needs: UDP Forwarder, TCP Forwarder, Connector Forwarder, or ArcSight ESM (CEF) Forwarder type.
5. Select the type of forwarding filter you want this forwarder to use—**Unified** or **Regular Expression**. Select “Unified” if you want to specify an indexed search query or “Regular Expression” to specify a regular expression query.
6. Click **Next**.
7. Enter additional type-specific information as described in the following table.

Forwarder Parameters

| Parameter | Forwarder Types | Description |
|-----------|-----------------|--|
| Name | All | The name that you entered in the previous screen is displayed automatically. If you want to change the name, make the change on this screen. |
| Query | All | <p>Enter the query that will be used to filter events that the forwarder will forward, or select a filter from the Filters list.</p> <p>Forwarder queries can be constrained by device groups and storage groups, but not by Peers.</p> <p>If you selected Unified Query in the previous screen, enter an indexed search query that includes full-text and field-based indexed fields. You can click the Advanced Search link to access the Search Builder tool to build an indexed query. (See "Accessing the Advanced Search Builder" on page 98 for more information.)</p> <div> <p>Tip: The unified query you specify must follow the following guidelines, or you will not be able to save the query or the forwarder.</p> </div> <p>Queries in the following format are valid; no other formats are allowed.</p> <p>(full-text terms field search)* regex</p> <p>That is, the query must only contain full-text (keyword) and field-based query elements; it cannot contain any aggregation search operators, or operators that process the searched data further to refine the search. For example, chart, sort, eval, top, and so on.</p> <p>Therefore, this is a valid query:</p> <p>failed message CONTAINS "failed device"</p> <p>However, this is an invalid query:</p> <p>failed message CONTAINS "failed device" sort deviceEventCategory</p> <p>The query can contain the regex operator after a pipeline character (). Therefore, this is a valid query for a forwarder:</p> <p>failed message CONTAINS "failed device" regex deviceEventCategory = "fan"</p> <div> <p>Tip: All search terms (except the "regex" portion) in a query must be indexed. If a query contains full-text (keyword) terms, full-text indexing must be enabled. Similarly, if the query contains a field, field-based indexing must be enabled and the specified field must be indexed.</p> </div> <p>If you selected Regular Expression in the previous screen, specify a regular expression in this text box. See "Searching for Events" on page 108.</p> |
| Filters | All | <p>Instead of specifying a unified query, you can select a filter from the Filters list. The Filters list contains all saved filters and predefined system filters on your Logger. Select a filter that meets the validity guidelines described in "Query" above. Otherwise, the user interface will display an error when you save the forwarder definition.</p> <p>You can only select one unified query filter per forwarder. However, You can select multiple filters for a regular expression-based forwarder.</p> <p>Similarly, when creating a regular expression-based filter, select a filter from this list.</p> |

Forwarder Parameters, continued

| Parameter | Forwarder Types | Description |
|---------------------------------|---------------------|--|
| Filter by time range | All | <p>If you are creating a continuous filter, which continuously evaluates incoming events and forwards the matching ones, skip this parameter. In this case, the query is run continuously and forwarding continues until you pause it.</p> <p>If you are creating a time range bound filter, check this box to specify a time range of events that the forwarder will forward. If you enter a time range, the forwarder sends events that are within that time range and stops.</p> <p>When you check this box, the Start and End dates and Time fields are displayed.</p> <p>Start must be earlier than End. Specifying a time in the future changes that field to the current time. For example, specifying a Start of the current day at 7 AM and an End of current day at 7 PM will produce events with timestamps from 7 AM to the time the filter is saved (that is, earlier than 7 PM).</p> |
| Source Type | Connector | <p>Select from the pull-down list of log file types, including:</p> <ul style="list-style-type: none"> • Apache HTTP Server Access • Apache HTTP Server Error • IBM DB2 Audit • Juniper Steel-Belted Radius • Microsoft DHCP Log • Others... <p>Note: The Source type must be the same in receiver, forwarder, and SmartConnector. See "Forwarding Log File Events to ESM" on page 399.</p> <p>A receiver can only receive events of a single source type. Set up separate receivers for each type of log file.</p> |
| Preserve Syslog Timestamp | UDP, TCP | <p>Set to true to preserve the syslog timestamp. The default is true. In this case, the timestamp is the original receipt time of the event.</p> <p>If set to false, original timestamp is replaced with Logger's receipt time.</p> |
| Preserve Original Syslog Sender | UDP, TCP | <p>Set to true to send the event as-is, without inserting Logger's IP address in the hostname (or equivalent) field of the syslog event. The default is true.</p> <p>If set to false, Logger's information is inserted in the hostname (or equivalent) field of the syslog event.</p> |
| IP/Host | UDP, TCP, Connector | <p>The IP address or host name of the destination that will receive forwarded events.</p> <p>Note: You cannot configure a Logger forwarder to send data to the same system on which it is configured.</p> |

Forwarder Parameters, continued

| Parameter | Forwarder Types | Description |
|--------------------------|---------------------|--|
| Port | UDP, TCP, Connector | The port on the destination that will receive the forwarded events. The default port is 514. |
| Connection Retry Timeout | TCP, Connector, ESM | The time, in seconds, to wait before retrying a connection. The default is 5 seconds. |
| ESM Destination | ESM | An existing ESM Destination that will receive the forwarded events. (For more information, see "ESM Destinations" on page 395.) |

8. Flag the **Enable** checkbox to have the forwarder immediately enabled. If you choose not to enable the forwarder now, you can enable it later.
9. Click **Save**.

To edit a forwarder:

1. Open the **Configuration | Data** menu and click **Forwarders**.
2. Locate the forwarder you want to edit.
3. If the forwarder is enabled, click the **Enabled** icon (✓) to disable it.
4. Click the **Edit** icon (✎).

The following screen shows the Edit Forwarder screen for a regular expression based forwarder. The Edit Forwarder screen for a Unified Query forwarder lists the Unified Query based filters and the Query text box only allows you to specify one query.

Specifying Query Terms, Filters, and other forwarder parameters

Edit Forwarder

Name

Query

Filters

- Configuration - Configuration Changes (Unified)
- Firewall - Deny
- Firewall - Drop
- Firewall - Permit
- Intrusion - Malicious Code (Unified)
- Logins - All Logins (Unified)
- Logins - Failed Logins

Selecting a filter from the above list will replace the query with the filter definition.

☐ Filter by time range

Connection Retry Timeout

ESM Destination

Enable ☒

Save **Cancel**

5. Edit the information in the form, as described in the table ["Forwarder Parameters" on page 379](#).
6. Flag the **Enable** checkbox to have the forwarder immediately enabled. If you choose not to enable the forwarder now, you can enable it later.
7. Click **Save**.

To delete a forwarder:

1. Open the **Configuration | Data** menu and click **Forwarders**.
2. Locate the forwarder that you want to delete.
3. If the forwarder is enabled, click the Enabled icon (✓) to disable it.
4. Click the Remove icon (✕).
5. Click **OK** to confirm the delete.

To pause a forwarder:

1. Open the **Configuration | Data** menu and click **Forwarders**.
2. Locate the forwarder that you want to pause.
3. Click the Running icon (||) to pause the forwarder.

To resume a forwarder:

1. Open the **Configuration | Data** menu and click **Forwarders**.
2. Locate the forwarder whose operation you want to resume.
3. Click the Paused icon (▶) to resume forwarder operation.

To disable a forwarder:

1. Open the **Configuration | Data** menu and click **Forwarders**.
2. Click **Event Output** in the left panel.
3. Locate the forwarder that you want to disable.
4. Click the Enabled icon (✓) to disable it.

To enable or re-enable a forwarder:

Tip: Wait a few minutes to disable a forwarder that was just enabled. Likewise, wait before enabling a forwarder that has just been disabled. Background tasks initiated by enabling or disabling a forwarder can produce unexpected results if they are interrupted.

1. Open the **Configuration | Data** menu and click **Forwarders**.
2. Locate the forwarder that you want to enable or re-enable.
3. Click the Disabled icon (⊘).

Real Time Alerts

This section describes Real Time Alerts. For information on Saved Search Alerts, see ["Saved Search Alerts" on page 323](#). For a description of the types of alerts, see ["Logger Alert Types" on page 388](#).

You can set up real time alerts that will be triggered by specified events or event patterns, and optionally, send notifications to previously configured destinations such as an email address or an SNMP server. Event patterns are specified events that occur above a particular frequency (a threshold number of events in a specified period). For example, you could create alert that is generated when five events from a specific device contain the word "unauthorized" within a five-minute interval. Additionally, alerts can also be generated for internal events such as storage capacity warnings or, on some Logger Appliance models, CPU temperature warnings.

To create an Alert, you will need to specify a query or filter, event aggregation values (Match count and Threshold), and (optional) one or more notification destinations. If the new Alert will send notifications to an email, SNMP, or Syslog Destination, set up the destination before creating the Alert. See ["Static Routes" on page 461](#), ["Receiving Alert Notifications" on page 390](#), and ["Setting Up Alert Notifications" on page 391](#) for more information.

Audit events for alerts are only written to the Internal Storage Group and not forwarded to ESM Destinations by default. If you need to forward these audit events to ESM, please contact customer support for assistance.

Note: This change only applies to audit events generated for alerts; other audit events are can be sent to ESM Destinations.

Logger comes with predefined filters with commonly needed event patterns so that you can use to quickly create the alerts you need. You can also create new filters that to find specific event patterns of interest.

To see a list of the configured Real Time Alerts:



1. Open the **Configuration | Data** menu and click **Alerts**.

The Realtime Alert list is displayed.



To add a Real Time Alert:

See ["Creating Real Time Alerts" on page 386](#).

Add Realtime Alert

| | |
|---|--|
| Name | <input type="text"/> |
| Query | <input type="text"/>   |
| Filters | <div><div>Configuration - System Configuration Changes (CEF format)</div><div>Events - CEF</div><div>Events - High and Very High Severity CEF Events</div><div>Intrusion - Malicious Code (CEF format)</div><div>Logins - All Logins (CEF format)</div><div>Logins - All Logins (Non-CEF format)</div><div>Logins - Successful Logins (CEF format)</div><div>Logins - Successful Logins (Non-CEF format)</div><div>Logins - Unsuccessful Logins (CEF format)</div><div>Logins - Unsuccessful Logins (Non-CEF format)</div></div> |
| Use ctrl-click to select or deselect items | |
| Match count | <input type="text"/> |
| Threshold (sec) | <input type="text"/> |
| Email address(es) | <input type="text"/> |
| SNMP destination | <div>NONE ▼</div> |
| Syslog destination | <div>NONE ▼</div> |
| ESM destination | <div>NONE ▼</div> |
| <div><div>Save</div><div>Cancel</div></div> | |


To enable or disable a Real Time Alert:

1. Open the **Configuration | Data** menu and click **Alerts**.
2. Locate the Alert that you want to disable or enable. Click the associated icon ( or ) to enable or disable the Alert.

Note: A maximum of 25 alerts can be enabled at one time. To enable an additional alert, you will need to disable a currently enabled alert.


If you have the maximum number of alerts enabled, and the receiver EPS is higher than 30k, you may see some slow-down in receiver EPS to prevent slower search times.

To edit a Real Time Alert:

1. Open the **Configuration | Data** menu and click **Alerts**.
2. Locate the Alert that you want to edit and click the Edit icon () on that row.

A screen similar to the one in ["Creating Real Time Alerts" below](#) is displayed. Only alphanumeric characters can be used in an Alert name.

To remove a Real Time Alert:

1. Open the **Configuration | Data** menu and click **Alerts**.
2. Locate the Alert that you want to remove and click the Remove icon () on that row.
3. Confirm the deletion by clicking **OK**, or click **Cancel** to retain the Alert.

To view triggered alerts:

See ["Viewing Alerts" on page 149](#).

Creating Real Time Alerts



This section describes how to create real time alerts. For information on Saved Search alerts, see ["Creating Saved Search Alerts \(Scheduled Alerts\)" on page 323](#). For a description of the types of alerts, see ["Logger Alert Types" on page 388](#).

To create a real time alert:

1. Open the Configuration | Data menu and click **Alerts**.
2. Click **Add**. The Add Realtime Alert dialog box is displayed.

Add Realtime Alert

Name

Query ☐  

Filters

- Configuration - System Configuration Changes (CEF format)
- Events - CEF
- Events - High and Very High Severity CEF Events
- Intrusion - Malicious Code (CEF format)
- Logins - All Logins (CEF format)
- Logins - All Logins (Non-CEF format)
- Logins - Successful Logins (CEF format)
- Logins - Successful Logins (Non-CEF format)
- Logins - Unsuccessful Logins (CEF format)
- Logins - Unsuccessful Logins (Non-CEF format)

Use ctrl-click to select or deselect items

Match count

Threshold (sec)

Email address(es)

SNMP destination

Syslog destination

ESM destination

3. Enter a name for the new alert, specify a query, or select an available filter from the list. Events that match this query are candidates for the alert.

Tip: Give the new alert a name that is unique and not likely to be duplicated elsewhere. For example, if you create an alert called "Remote" and a forwarder called "Remote," you will get an error message asking for a unique name.

4. You can edit the search filter query to meet your needs. Alphanumeric characters and spaces are acceptable, however, some special characters such as % and & are not.

For more information on Filters, see ["Filters" on page 311](#).

Tip: To test the validity of an alert query, use the **Search** user interface. Enter the query in the Search text box in the following format:

Real time alert: |regex "regex expression"

Scheduled saved alert: **_deviceGroup IN ["192.0.2.3 [TCPC]"] name="*[4924TestAlert]*" AND ("192.0.*" OR categoryBehavior CONTAINS Stop)**

If the query is valid, cut and paste the regular expression between the double quotes (" ") in the **Query** text box on the Add Alert page.

5. Enter **Match count** and **Threshold** values. If the number of candidate events equals or exceeds the Match count within the Threshold number of seconds, the alert will be triggered.

If you want to be notified when any event matches the filter (for example, for an internal event such as High CPU Temperature), enter a Match count of 1 and a Threshold of 1.

Note: To maintain an optimal size of an alert event, the event does not contain event IDs of all the triggering events if you specify **Match count of 101 or higher**. As a result, the **baseEventCount** field in the event does not reflect the true number of matching events for such alert events.

Triggering events are truncated in multiples of 100. Therefore, if you specify a Match count of 101, only one event is included in the alert event and the **baseEventCount** field value is 1. Similarly, if you specify a Match count of 720, only 20 events are included and the **baseEventCount** field value is 20.

6. Enter notification destinations. Enter any combination of:
 - One or more e-mail addresses, separated by commas
 - An SNMP Destination—for more information, see ["SNMP Destinations" on page 392](#).
 - A Syslog Destination—for more information, see ["Syslog Destinations" on page 393](#).
 - An ArcSight Manager—for more information, see ["Sending Notifications to ESM Destinations" on page 394](#).

7. Click **Save**.

When you create an alert, it is in disabled state. Enable it using the instructions in ["To enable or disable a Real Time Alert:" on page 385](#).

Logger Alert Types

Logger provides two types of alerts:

- Real time alerts search continually and automatically send notifications if specified criteria are found. For more information, see ["Real Time Alerts" on page 383](#).
- Saved Search Alert search at a scheduled interval and send notifications if specified criteria are found. For more information, see ["Saved Search Alerts" on page 323](#).

The following table compares the two types of alerts.

| Real Time Alerts | Saved Search Alerts |
|---|---|
| <p>No limit on the number of alerts that are defined.</p> <p>A maximum of 25 alerts can be enabled at any time.</p> | <p>Any number of alerts can be defined. All defined alerts are enabled and effective, however, a maximum of 50 alerts can run concurrently.</p> |
| <p>No limit on the number of configured e-mail destinations; however, you can only set one SNMP, one Syslog, and one ESM Destination.</p> | <p>No limit on the number of configured e-mail destinations; however, you can only set one SNMP, one Syslog, and one ESM Destination.</p> |
| <p>Only regular expression queries can be specified for these alerts.</p> | <p>Queries for these alerts are defined using the flow-based search language that allows you to specify multiple search commands in a pipeline format, including regular expressions.</p> <p>Aggregation operators such as chart and top cannot be included in the search query.</p> |
| <p>Alerts are triggered in real time. That is, when specified number of matches occurs within the specified threshold, an alert is immediately triggered.</p> | <p>These alerts are triggered at scheduled intervals. That is, when a specified number of matches occurs within the specified threshold, an alert is triggered at the next scheduled time interval.</p> |
| <p>To define a real time alert, you specify a query, match count, threshold, and one or more destinations.</p> <p>A time range is not associated with the queries defined for these alerts. Therefore, whenever the specified number of matches occurs within the specified threshold, an alert is triggered.</p> | <p>To define a Saved Search Alert, you specify a Saved Search (which is a query with a time range), match count, threshold, and one or more destinations.</p> <p>A time range (within which events should be searched) is specified for the query associated with these alerts. Therefore, specified number of matches within the specified threshold (in minutes) must occur within the specified time range. You can also use dynamic time range (for example, \$Now-1d, \$Now, and so on).</p> <p>For example, if a Saved Search query has these start and end times:</p> <ul style="list-style-type: none"> Start Time: 5/11/2010 10:38:04 End Time: 5/12/2010 10:38:04 <p>And, the number of matches and threshold are the following:</p> <ul style="list-style-type: none"> Match count: 5 Threshold: 3600 <p>This will trigger an alert whenever five events occur within one hour between May 11th, 2016 10:38:04 AM and May 12th, 2016 10:38:04.</p> |

Alert Triggers and Notifications

An alert is triggered if a specified number of matches occurs within the specified threshold (time interval in seconds). When an alert is triggered, Logger creates an alert event containing the triggering events or event IDs, and sends notification through previously configured destinations—e-mail addresses, SNMP server, Syslog server, and ArcSight Manager.

By default, only alert notifications sent to e-mail destinations include all matching events that triggered the alert. You can configure your Logger to include matched events for SNMP, Syslog, and ESM Destinations as well. However, that kind of configuration is only possible through the command-line interface of the Logger; therefore, please contact customer support for instructions.

When are Alert events triggered?

You also specify a time window and a number of matching events. When that number of matching events is detected within the time window, an alert event is triggered.

Logger resets the count after detecting 100 matching events. Therefore, all events that occur in the time window will not necessarily be recorded in an alert. For example, if you configure the alert to be sent when there are 20 matching events in two minutes, and 152 events occur within two minutes, you will get seven alerts, and 12 matching events will not be included in any alert. In this situation, the following alert events are triggered:

- Alert one has 20 matching events.
- Alert two has 40 matching events.
- Alert three has 60 matching events.
- Alert four has 80 matching events.
- Alert five has 100 matching events (1-100).
- Alert six has 20 matching events (101-120).
- Alert seven has 40 matching events (101-140).

The remaining 12 events are being held, waiting to meet the threshold of 20 more events in a two-minute interval.

Receiving Alert Notifications

In order to receive notification from an alert, set up the alert to be sent to a previously configured destination, such as an e-mail address, SNMP server, Syslog server, and ArcSight Manager.

By default, only alerts to e-mail destinations include all matched events that triggered the alert. You can configure your Logger to include matched events for SNMP, Syslog, and ESM Destinations as well. However, such a configuration is only possible through the command-line interface of the Logger; therefore, please contact customer support for instructions.

For information on how to configure destinations, see ["ESM Destinations" on page 395](#), ["SNMP Destinations" on page 392](#), and ["Syslog Destinations" on page 393](#). To configure e-mail destinations, see ["Static Routes" on page 461](#), as well.

Note: Audit events for alerts are only written to the Internal Storage Group and not forwarded to ESM by default. If you need to forward these audit events to ESM destinations, please contact customer support for assistance. This only applies to audit events generated for alerts; other audit events can be

sent to ESM destinations.

Sending Notifications to E-mail Destinations

When you send notifications for an alert via e-mail, the e-mail message contains both the trigger alert information and the matched (base) events.

The following is an example of the trigger alert information:

Alert event match count [1], threshold [10] sec

And the matched event:

Event Time [Tue May 11 16:46:49 PST 2016]

Event Receipt Time [Tue May 11 16:46:50 PST 2016]

Event Device Address [192.0.2.1]

**Event Content [May 11 10:31:20 localhost
CEF:0|NetScreen|Firewall/VPN||traffic:1|Permit|Low| eventId=590 msg=start_
time\= "2016-05-11 15:25:02" duration\=15 policy_id\=0 service\=SSH proto\=6
src zone\=Trust dst zone\=Untrust action\=Permit sent\=656 rcvd\=680
src\=192.0.2.4 dst\=192.0.2.5 src_port\=54759 dst_port\=22 translated
ip\=192.0.2.2 port\=54759 app=SSH proto=TCP in=680 out=656
categorySignificance=/Normal categoryBehavior=/Access
categoryDeviceGroup=/Firewall categoryOutcome=/Success
categoryObject=/Host/Application/Service art=1165861874880 cat=Traffic Log
deviceSeverity=notification act=Permit rt=1165861874880 shost=n111-
h046.qa.arcsight.com src=192.0.2.4 sourceZoneURI=/All Zones/System
Zones/Private Address Space/RFC1918: 192.0.2.0-192.255.255.255
sourceTranslatedAddress=192.0.2.2 sourceTranslatedZoneURI=/All Zones/System
Zones/Public Address Space/192.0.2.0-192.0.255.255 spt=54759
sourceTranslatedPort=54759 dst=192.0.2.10 destinationZoneURI=/All
Zones/System Zones/Private Address Space/RFC1918: 192.0.2.0-192.255.255.255
dp]**

Setting Up Alert Notifications

To set up alerts notifications:

1. Configure the Logger's SMTP with the desired e-mail address destination (see ["Static Routes" on page 461](#)) or create an SNMP Destination (see ["SNMP Destinations" on the next page](#)) or Syslog Destination (see ["Syslog Destinations" on page 393](#)).

Number of destinations per alert:

- E-mail: Multiple, each separated by a comma.
 - SNMP: One
 - Syslog: One
2. Create a query to find the events of interest; save the query as a filter. See ["Saving Queries, Creating Saved Searches and Saved Filters." on page 138.](#)

Note: Only regular expressions can be used in queries specified for alerts.

3. Create an Alert that uses the new filter and specify match count and threshold (see ["Saved Searches" on page 315.](#))
4. Enable the new Alert.

Sending Notifications to Syslog and SNMP Destinations

When configuring Logger to send alerts to SNMP and Syslog destinations, you should be familiar with this information:

- Logger supports SNMP v2c and v3.
- Unlike an e-mail alert, a trigger alert is sent separately from the alert that contains the matched (base) events that triggered the alert.
- All SNMP alerts are sent as SNMP traps; therefore, trigger alerts and their associated matched (base) events are received as SNMP traps on an SNMP destination. The SNMP trap includes the trigger event, but it does not include the events that caused the alert to trigger (matched events). The trigger event does include the event IDs of all the matched events. You can use the event IDs in the trigger alert to identify the associated matched events.

Note: Non-CEF events do not contain event IDs. If you need to associate such base events with their trigger alert, send such events to Logger through a connector.

- SNMP uses UDP to send packets. As a result, the order in which alerts arrive at an SNMP destination is not guaranteed.
- When Syslog events are sent using UDP, the order in which the trigger alert and matched events arrive is not guaranteed.
- Avoid sending alerts to SNMP using non-ASCII characters in the community field as the trap displays "??" characters. However, this does not impact SNMP authentication to Logger.

SNMP Destinations

SNMP Destinations describe how Alert notifications should be sent using Simple Network Management Protocol (SNMP). Set up SNMP Destinations before creating Alerts that will use them. Before configuring SNMP destinations, you should be familiar with the information in ["Sending Notifications to Syslog and SNMP Destinations" above.](#)

To add an SNMP Destination:

1. Open the **Configuration | Data** menu and click **SNMP Destinations**.
2. Click the **Add** button.
3. Enter parameters:

| Parameter | Description |
|-----------------------|--|
| SNMP Destination Name | A name for this destination. |
| Connector Name | The SmartConnector name. |
| Connector Location | The physical location of the SmartConnector machine. If you do not want to specify a location, enter "None." |
| Logger Location | Optional comment describing Logger's physical location. |
| SNMP Host | Host name or IP address. |
| SNMP Port | 162, by default. |
| Community Name | SNMP community name. |

4. Click **Save** to create the new SNMP Destination.

To remove an SNMP Destination:

1. Open the **Configuration | Data** menu and click **SNMP Destinations**.
2. Locate the SNMP Destination that you want to remove and click the Remove icon (✕) on that row.
3. Confirm the deletion by clicking **OK**, or click **Cancel** to retain the SNMP Destination.

Syslog Destinations

Syslog Destinations describe how Alert notifications should be sent using the comparatively simple syslog protocol. You need to set up Syslog Destinations before creating Alerts that will use them. Before configuring Syslog destinations, you should be familiar with the information in ["Sending Notifications to Syslog and SNMP Destinations" on the previous page](#).

To add a Syslog Destination:

1. Open the **Configuration | Data** menu and click **Syslog Destinations**.
2. Click the **Add** button.
3. Enter parameters:

| Parameter | Description |
|-----------|---|
| Name | A name for this destination. Note: Syslog Destination requires a unique name. |
| Type | UDP or TCP Syslog. Note: This choice cannot be edited later. |

- Click **Next**. Enter the secondary parameters:

| Parameter | Description |
|--------------------------|--|
| Name | The name for the destination. |
| Type | This is the value you entered in the previous screen. This value cannot be changed. |
| Ip/Host | Host name or IP address. |
| Port | Port (default is 514). |
| Connection Retry Timeout | (Only for TCP Syslog Destinations) The time, in seconds, to wait before retrying a connection. The default is 5 seconds. |

- Click **Save** to create the new Syslog Destination.

To edit a Syslog Destination:

- Open the **Configuration | Data** menu and click **Syslog Destinations**.
- Click the Edit icon (✎). You can edit the parameters of the Syslog Destination except its type.
- Click **Save** to make the changes, or **Cancel** to return to the Syslog Destination table.

To remove a Syslog Destination:

- Open the **Configuration | Data** menu and click **Syslog Destinations**.
- Locate the Syslog Destination that you want to remove and click the Remove icon (✕) on that row.
- Confirm the deletion by clicking **OK**, or click **Cancel** to retain the Syslog Destination.

Sending Notifications to ESM Destinations

ESM Destinations describe how Alert notifications should be sent to an ArcSight Manager. Set up ESM destinations before creating Alerts that will use them.

If an ArcSight Manager uses a signed SSL certificate, you will need to load it on the Logger.

Note: Audit events for alerts are only written to the Internal Storage Group and not forwarded to ESM by default. If you need to forward the audit events generated for alerts to ESM, please contact customer

support for assistance.

To setup Logger to send alerts to an ArcSight Manager:

1. If the ArcSight Manager uses a certificate, copy the server SSL certificate file from an ArcSight Console or other component that is already communicating with the target Manager, and upload the certificate file to Logger, as described ["Uploading a Certificate to the Logger:" on page 398](#).

Note: You cannot import the cacerts file, which is a repository of trusted certificates, to the Logger. Instead, you need to import specific SSL certificate files.

2. Create an ESM Destination, as described in ["To create an ESM Destination:" on the next page](#).

ESM Destinations

An ESM Destination establishes a trusted connection between Logger and an ArcSight Manager so that you can forward events and alerts in Common Event Format (CEF) from the Logger to the Manager using Logger's built-in SmartConnector.

The CEF events are already normalized or categorized. For more information about CEF, refer to the document "Implementing ArcSight CEF". For a down-loadable a copy of this guide, search for "ArcSight Common Event Format (CEF) Guide" in the [Micro Focus Security Community](#).

Logger can forward these types of events to an ArcSight Manager:

- Syslog events to an ArcSight Syslog SmartConnector that is connected to an ArcSight Manager
- Common Event Format (CEF) events directly to an ArcSight Manager using Logger ESM Destinations. An ESM Destination appears as a SmartConnector to an ArcSight Console.
- Events received by file receivers where the type specified is not Other. Such events are forwarded using the ArcSight Streaming SmartConnector.

Maximum ESM Destinations: As many destinations as are allowable on the SmartConnectors you are using. However, for performance reasons, Micro Focus ArcSight recommends that you create no more than two ESM Destinations pointing to a single ArcSight Manager. (One should suffice in most cases.)

Note: Do not use basic aggregation for Logger's built-in SmartConnector because it is resource intensive. (Basic aggregation is set using the **Enable Aggregation (in seconds)** field from the ArcSight Console.) Instead, follow these steps on the ArcSight Console to configure field-based aggregation:

1. Ensure that Processor > Enable Aggregation (in seconds) is set to **Disabled**, to disable basic aggregation.
2. Right-click the connector and select **inspect/edit/**.

For additional details about configuring field-based aggregation, refer to the ArcSight SmartConnector *User's Guide*.

To setup Logger to forward events to an ArcSight Manager:

1. Copy the server SSL certificate file from an ArcSight Console or other component that is already communicating with the target Manager, and upload the certificate file to Logger, as described ["Uploading a Certificate to the Logger:" on page 398](#).

If your Logger operates in FIPS mode, a valid and current (non-expired) server SSL certificate file from the ArcSight Manager is required on the Logger; otherwise, the forwarder will not forward events to it.

Note: You cannot import the `cacerts` file, which is a repository of trusted certificates, to the Logger. Instead, you need to import specific SSL certificate files.

2. Create an ESM Destination, as described in ["To create an ESM Destination:" below](#).
3. Create an ESM forwarder that refers to this ESM Destination. (See ["Forwarders" on page 376](#)).

ESM Destinations page

Add ESM Destination

| | |
|--|---|
| Name | <input type="text" value="n185-h129"/> |
| Connector Name | <input type="text" value="n185-h129"/> |
| Connector Location | <input type="text" value="//All Connectors/Devices"/> |
| Logger Location | <input type="text"/> |
| IP/Host | <input type="text" value="n185-h129"/> |
| Port | <input type="text" value="8443"/> |
| User Name | <input type="text" value="Username"/> |
| Password | <input type="password" value="....."/> |
| <div><input type="button" value="Save"/> <input type="button" value="Cancel"/></div> | |

To create an ESM Destination:

Make sure you have loaded the certificate file for ArcSight Manager as described in ["Uploading a Certificate to the Logger:" on page 398](#) before adding it as a destination on the Logger. If the certificate file

does not exist on the Logger, you will not be able to create an ESM Destination.

1. Open the **Configuration | Data** menu and click **ESM Destinations**.
2. Click **Add**. The ESM Destinations page is displayed.
3. Enter the following parameters:

| Parameter | Description |
|--------------------|---|
| Name | The name for this ESM Destination. |
| Connector Name | The SmartConnector name. |
| Connector Location | The physical location of the SmartConnector machine. If you do not want to specify a location, enter "None." |
| Logger Location | The physical location of the Logger. If you do not want to specify a location, enter "None." |
| IP or Host | <div>The ArcSight Manager to which the forwarder will direct events. Note: Make sure the name or IP address you specify in this field is exactly the name or IP address configured on the ArcSight Manager. If the two names or IP addresses do not match, you will not be able to set up an ESM Destination successfully.</div> |
| Port | Typically 8443. |
| User Name | The name of an existing User of the ArcSight Manager with administrator privileges. |
| Password | <div>The password for the Login user. This password cannot contain the special characters percent (%), equal to (=), semicolon (;), double quote ("), single quote ('), less than (<), or greater than (>). Caution: While ArcSight Manager allows these special characters in passwords, Logger does not. If the ArcSight Manager user's password contains those characters, you will need to change the password in ArcSight Manager before configuring this password.</div> |

4. Click **Save**.

Tip: If you receive the following error when adding a new ESM Destination, make sure the host name you specified in the IP or Host field **exactly matches** the name configured on the ArcSight Manager.

There was a problem: Failed to add destination

Additionally, if the ArcSight Manager is configured using a host name instead of IP address, make sure you add the ArcSight Manager host name and IP address in the Logger's hosts file (**System Admin > Network > Hosts**).

To delete an ESM Destination:

1. Open the **Configuration | Data** menu and click **ESM Destinations** (or click **Alerts** and then open the **ESM Destinations** page if you are deleting an ESM Destination for forwarding Alerts.)
2. Locate the ESM Destination that you want to delete and click the Delete icon (✕) on that row.
3. Confirm the deletion by clicking **OK**, or click **Cancel** to retain the ESM Destination.

Certificates

Uploading a Certificate to the Logger:

Upload a valid server SSL (Secure Sockets Layer) certificate file for the ArcSight Manager that you are establishing as a Logger destination for forwarding events and alerts.

Note: Certificate names might include "JDK" after upgrading to Logger 6.5.

If your Manager *does not* have FIPS 140-2 mode enabled, you can obtain a certificate file for your Manager in these ways:

- From the Manager's keystore
- From the ArcSight Console's truststore
- From the truststore of one of the SmartConnectors that communicates with the Manager

Use the **keytoolgui** utility to export a Manager's certificate as described in the "Using Keytoolgui to Export Certificate" procedure in the ArcSight ESM *Administrator's Guide*. For detailed information about keystore, truststore, their locations on the Manager, ArcSight Console, and the SmartConnectors, see the ArcSight ESM *Administrator's Guide*.

Once you have exported a certificate for your Manager, copy it to the machine from which you connect to your Logger.

If your Manager *has* FIPS 140-2 mode enabled, run this command to export the Manager's certificate from the Manager's `<ARCSIGHT_HOME>/bin` directory:


```
arcsight runcertutil -L -n managerkey -r -d <ARCSIGHT_HOME>/config/jetty/nssdb -o <absolute_path_to_manager.cert>
```

This command generates the **manager.cert** file, the Manager's certificate, in the location that you specified in the above command.

Note: By default, the **manager.cert** file will be exported to your `<ARCSIGHT_HOME>` directory if you do not specify the absolute path to the **manager.cert** file destination.

To upload a certificate file for an ESM Destination:

1. Make sure you have copied the Manager certificate to the machine from which you connect to your Logger.
2. Open the **Configuration | Data** menu and click **Certificates**.
3. Click **Add** to display the following screen.



Add Certificate

Specify Certificate File to Upload

Certificate Alias

Certificate File No file chosen

Overwrite Certificate ☒


4. Enter an alias for the certificate file. This name is used to easily identify a certificate file. For example, **arcsight_esm_manager1_cert**.
5. Click **Browse** to locate the Manager Certificate file you copied.
6. Check the “Overwrite Certificate” box if you want this certificate to overwrite an existing certificate with the same alias.
7. Click **Save**.

Forwarding Log File Events to ESM

Logger can read events from a log file and forward those events to a Logger streaming SmartConnector that sends the events on to ArcSight Manager.

To forward log file events to ESM, configure the receiver, forwarder, and SmartConnector to accept the same source type (as described in ["Working with Source Types" on page 368](#)).

Note: The receiver, forwarder, and SmartConnector must all be configured with **the same Source Type value** to successfully forward log file events from Logger to ArcSight ESM.



Unlike events that Logger receives, such as syslog, SmartMessage, or CEF, log file events must be parsed to determine event timestamp. Therefore, if you need forward events to ESM by using a Connector forwarder, you must choose one of the following source types for the receiver:

| Source Type | |
|-----------------------------|------------------------------|
| Apache HTTP Server Access | Microsoft DHCP Log |
| Apache HTTP Server Error | Other |
| IBM DB2 9.x Audit Log | Tipping Point SMS 2.5 Syslog |
| IBM DB2 Audit | VMware ESX Syslog |
| Juniper Steel-Belted Radius | |

Data Validation

The data validation screen enables you to perform audit-quality validation on your Logger data files. From here, you can check the hash value of all data files within specified time range to validate the data. This feature is only available to administrators. See ["Users/Groups" on page 495](#) for more information on Logger user rights and how to administer them.

The data validation process takes the digest algorithm based on the Logger version in use at the time the data files are filled-up. Each data file contains up to 1 GB of data. The data validation process in Logger 6.5 and following releases for new and partially-filled data files uses the SHA-2 hash algorithm. It is also backward-compatible with the previous digest algorithm.

The process takes the hash value for the data files in the specified time range, compares it to the pre-computed value and determines the data file integrity.

Prerequisites


Users must be assigned to the following User Groups to access this feature:

- Default Logger Rights Group
- Default System Admin Group

See ["Setting Logger User Permissions" on page 510](#) for more information.

To validate data on Logger:

1. Open the **Configuration | Data** menu and then click **Data Validation**.



The screenshot shows the 'Data Validation' configuration window. It has a title bar 'Data Validation'. Below the title bar, there are two date fields: 'Start Date' with the value '29-January-2019' and 'End Date' with the value '31-January-2019'. Each date field has a calendar icon to its right. Below the date fields, there is a 'Schedule Time' section. It consists of two time input fields: the first contains '12' and the second contains '19', separated by a colon. To the right of these fields is a dropdown menu currently set to 'PM'. There are up and down arrow icons above and below each time field. At the bottom of the window is a blue button labeled 'Update Data Validation'.

2. Specify the range of data you want to validate in the **Start Date** and **End Date** fields.
3. Specify the time you want to run the validation by using the up and down-arrows on the **Schedule Time** fields.
4. Check the **Email Me Validation Results** checkbox to have Logger send an email letting you know the validation result as soon as the validation process is complete. Logger sends this to the email address stored for the logged-in user.

Note: If the **Email Me** option is not available, Logger's SMTP server has not been configured. Logger's system administrator may be able to enable this feature. For more information, see ["SMTP" on page 465](#).

5. Click **Schedule Data Validation**.

Note: You cannot cancel a Data Validation in progress. The data validation process can take a long time for large amounts of data. Therefore you should schedule the process to run during off-peak hours, and narrow down the time range to include only the data you are interested in.

Once the data validation process is complete, each data file in the specified time range is displayed along with its Validation Result. If the emailme checkbox was selected, an email with the subject, "Data Validation results from Logger <logger host name>" is sent to the email address stored for the logged-in user.

To view the validation results:

- Click the down-arrow in the **Validation Result** dropdown to select the type of result that you want to see. You can select All, Corrupt, Intact, or Hash Unavailable.

OR

- Click **Export** to download a spreadsheet containing the validation data.

The following table describes the possible validation results:

| Displayed Value | Value in Exported File | Description |
|------------------|------------------------|--|
| Intact | True | The hashes match; the data is intact. |
| Corrupt | False | The hashes do not match; the data has been changed or become corrupt. |
| Hash unavailable | N/A | The file has no hash; the data could not be validated. This is most likely because the data file is not yet full or the data file was created by an older version of Logger. |

Note: If the system has been upgraded from a version earlier than Logger 6.0, data from the earlier version will have a status of N/A. This is because no data validation hash value was stored when the data was created. However, in the case of future upgrades, hash validation data will be kept, and you will be able to validate the data after an upgrade.

SecureData Decryption

Prerequisites

Default Logger Rights Group.

Event Data Encryption.

About

SecureData Decryption allows users to decrypt values that Logger receives from **SmartConnectors**. The fields are previously configured and consequently decrypted when running **Searches and Reports**.

Procedure

From Configuration > SecureData Configuration, users establish a connection with the SecureData Server. The SecureData Configuration window shows a list of default fields with the decryption feature enabled in **Analyze> Search** and **Reports**.

Note: The new rights are only available for users that belong to "Default System Admin Group".

SecureData Configuration

| | |
|--|--|
| Server | <input type="text"/> |
| Port | <input type="text"/> |
| Auth Identity | <input type="text"/> |
| Shared Secret | <input type="text"/> |
| Fields | <input type="text" value="rawEvent, requestUrl, requestCookies, deviceCustomNumber1, deviceCustomString1, deviceDomain, deviceEventClassId, deviceVendor, deviceProduct, sourceHostName, sourceNtDomain, sourcePort, sourceUserName, sourceUserId, sourceUserPrivileges, destinationHostName, destinationNtDomain, destinationPort, destinationUserName, destinationUserId, destinationUserPrivileges"/> |
| <div><input type="button" value="Save"/> <input type="button" value="Cancel"/></div> | |



Note: Make sure to add encode 64 password in the shared secret field before configuring SecureData Decryption. Otherwise, the following error is displayed: ***Cannot establish connection with SecureData server: Failed to authenticate with the current credentials configured in the system***.



Fields/ Columns with SecureData decryption are shown with a red padlock icon next to them in the search results. When the user clicks a red padlock, the system decrypts the value of that particular field. Users can decrypt all the values in a column by clicking on the padlock that is next to the column's name.

The system only decrypts values in the current page, so if the user goes to another page, the values are reset. SecureData Decryption is also enabled in graph searches.






If the Field/Column is encrypted-configured but the value is not, when you click the padlock icon, the value is encrypted on the screen but not in the database. Fields/columns can also be decrypted in Classic and Smart reports with tabular format.

The icons change based on the decryption status.

| Lock Status | Description |
|--|---|
| Closed Red Padlock  | The value is encrypted. If the user clicks on the icon, the system sends the SecureData server a decryption request. The encrypted value is then replaced with the decrypted value. |
| Open Green Padlock  | The field is decrypted. If the user clicks on that icon the system shows original encrypted value. |

| | |
|--|---|
| Loading Spinner  | The field is SecureData configured and it is being decrypted. The system will show this icon the first time a value is decrypted. |
| Information icon  | The decryption was not completed due to an error. |
| | Note: For error details, click on the information icon. |

Types of Error Messages

| Error Message | Description |
|--|--|
| The remote decrypting service is unavailable, please contact your system administrator for assistance.  | Error message for the HTTP status code 503 (Service Unavailable) returned by the secure data decryption server |
| An error has occurred in the remote decrypting service, please contact your system administrator for assistance.  | Error message for the HTTP status code 500 returned by the secure data decryption server. The user should check if remote server is up and running correctly. |
| Failed to authorize the decrypting request, please contact your system administrator for assistance.  | Error message for the HTTP status code 403 returned by the secure data decryption server. The user should check if the request is authorized in the remote server. |
| Failed to authenticate with the current credentials configured in the system.  | Error message for the HTTP status code 401 returned by the secure data decryption server. The user should check the credentials in the remote server. |
| An error has occurred in the decrypting process, please contact your system administrator for assistance.  | General error message. The user should check if the information in the Secure Data Configuration Page is completed and the connection with the remote server is working. |

Storage

The options in the **Configuration | Storage** category enable you to manage how data is stored in Logger. Different storage groups support the implementation of multiple retention policies. Each group can have a different policy, and storage rules determine which storage group is used for events from specific device groups. For more information, refer to the Logger *Installation Guide*. A storage group's size can be

increased or decreased and the retention policy defined for it can be changed. Events are stored compressed. You cannot configure the compression level.

| | |
|--|-----|
| • Storage Groups | 405 |
| • Storage Rules | 407 |
| • Storage Volume | 408 |
| • Java Memory Allocation | 410 |
| • Event Archives | 410 |
| • Archiving Events | 412 |
| • Daily Archive Settings | 416 |
| • Archive Storage Settings | 416 |

Storage Groups

Storage Groups support multiple retention policies by defining a maximum size (Allocated (GB) and number of days (Maximum Age) to retain events. Once events are older than the specified Maximum Age or there are more events than the storage group will hold (as specified by Allocated size), the oldest events are deleted at the next retention cycle. The retention process triggers periodically on Logger, therefore, events might not be deleted immediately when events get older than maximum age or the storage group size exceeds the allocated size.

Logger allows users to add up to 48 custom storage groups if there is enough storage volume available. Adding more storage groups in Logger is determined by the partition size and the storage volume available.

Micro Focus recommends that you create four additional storage groups in addition to the two that pre-exist, so that you have five storage groups available for event storage and one for Logger's internal events.

To add additional storage groups, see ["Adding Storage Groups" on page 430](#)

These are the minimum requirements for Storage Groups:

Once a storage group is created, it cannot be deleted however its size can be increased or decreased any time. If you are decreasing the size of the storage group and the new size is lesser than the currently used space on the storage group, you need to delete data to achieve the new size. In this situation, the Logger UI guides you to delete sufficient data.


To edit (including resizing) a storage group:

1. Open the **Configuration | Storage** menu and then click **Storage Groups**.

The Storage Groups page displays the available storage groups.

2. Identify the storage group you want to modify and click the associated **Edit** icon (✎). The Storage Groups page displays the Edit <Storage Group Name> Storage Group pane.

Edit Default Storage Group

 **Important:**
Please be aware that if you reduce the maximum age from the current value you will lose all events that are older than the new maximum age. Retention time is based on the event date contained in the archive and not the date in which archive was created. Reducing the maximum storage group age may take a few minutes to complete.

Maximum Live Data Age (Days)

Allocated (GB)

Maximum Archives Age (Days)

Used (GB)

3. Access the Archive Storage Settings Configuration page. Update the following spaces:

- **Storage Group:** Edit the name of the storage group.

Note: The names of the Internal Storage Group and Default Storage Group cannot be modified.

- **Maximum Archives Age:** Set the maximum days for archive data to remain in the remote system. By default, the retention policy for event archives is disabled (-1). To enable the policy, add a value not equal to -1 and greater than 0 which stands for the number of retention policy days. Please note the retention time is based on the event in the archive and not the date in which the archive was created.
- **Maximum Live Data Age:** Set the number of days for the data to remain in Logger before transition to an archive.
- **Allocated:** If reduction of storage group size is smaller than the **Used (GB)** size in the **Edit Storage Group** page, Logger displays a message indicating that reducing storage group size in this situation will require you to delete existing data.

If you choose to delete data to reduce the storage group size, follow these steps:

- a. Set the **Maximum Age** value to the number indicated in the message. Doing so triggers the deletion of events.
- b. Refresh the Edit Storage Group screen. When the **Used (GB)** value is less than or equal to the storage group size you want to set, go to the next step. Otherwise, keep refreshing the screen periodically.
- c. Set the **Allocated (GB)** value to suit your needs.
- d. If you wish, restore the **Maximum Age** setting (that you changed in Step a) to the original value. If you choose **not** to delete data, go to the next step to exit the procedure.

Note: If there is sufficient space to reduce the storage group size, you can change it without modifying the Maximum Age value (to modify the retention policy to delete data).

4. Click **Save** to store the changes, or **Cancel** to quit.

Note: The used (GB) value, changes as data are deleted. This process can take some time, wait before proceeding to the next step.

Storage Rules

Storage rules create a mapping between device groups and storage groups. Doing so enables you to store events from specific sources to a specific storage group. You can configure these storage groups with different retention policies, and thus retain event data based on the source of incoming events. For example, all events from firewall devices can be subject to a short retention period. To accomplish this, manually assign the firewall devices to a device group and then create a storage rule that maps the device group to a storage group with the desired short retention period.


Tip: Events that are not subject to any storage rule are sent to the Default Storage Group.

Before you add a storage rule, make sure that the storage group to which you want to store the events and the device group that contains the devices whose events you want to store exist. For information on how to create device groups, see ["Device Groups" on page 345](#).

Logger allows you to create up to 40 storage rules. If you create additional rules, an error might be generated.

To add a storage rule:

1. Open the **Configuration | Storage** menu and then click **Storage Rules**.
2. Click **Add** The Add Storage Rule page displays.



Add Storage Rule

Storage Group: Default Storage Group ▼

Device Group: Devices ▼

Priority: 60

Save **Cancel**

3. Enter the following parameters:

| Parameter | Description |
|---------------|---|
| Storage Group | Select a storage group from the drop-down list. The storage groups must already be set up before any storage rules are added. |
| Device Groups | Select a device to associate with the storage group. Note: If you want to include events from more than one device in the storage group, create a Device Group which contains all the Logger Devices you want and then select that Device Group for the Storage Rule. |
| Priority | An integer that indicates the new rule's priority. The number must be unique for each storage rule. The smaller the number, the higher the rule's priority. |

4. Click **Save** to add the new storage rule, or **Cancel** to quit.

To edit or reorder a storage rule:

1. Open the **Configuration | Storage** menu and then click **Storage Rules**.
2. Find the storage rule that you want to edit and click the Edit icon (✎) on that row.
3. Change the information in the form—for example, change the priority value to reposition the storage rule in the table—and click **Save**.

To delete a storage rule:

1. Open the **Configuration | Storage** menu and then click **Storage Rules**.
2. Find the storage rule that you want to delete and click the Remove icon (✕).
3. Click **OK** to confirm the delete.

Storage Volume

The Storage Volume page displays the mount location and current storage volume settings.

To view the existing storage volume settings:

1. Select **Storage Volume Settings** from the navigation bar Configuration | Storage menu.

Storage path is configured to /opt/arcsight/data/logger. To increase the Storage Volume size, go to the System Maintenance page. You must have admin-level privileges to perform this operation.

Storage Volume Settings

Allocated (GB) 583

Status Ready

To increase the Storage Volume size:

See ["Storage Volume Size Increase" on page 428](#) for full details. You must have admin-level privileges to perform this operation. See ["Users/Groups" on page 495](#) for more information on Logger user rights and how to administer them.

To allocate disk space:

1. Go to <LOGGER-FOLDER>/data and look for the available storage volume.
2. Multiply the data-file folder space per .93. The result will be the initial storage volume space.
3. Obtain the storage volume space specified in your License. Logger 7.0 has assigned up to 24 TB disk space for permanent license and Instant-On-license. If you want to use the maximum storage volume size of 24TB in Logger, you must allocate at least 26.4TB (which includes the % of reservation) of disk space in bigger capacity storage appliances.

Note: If the license disk space is greater than storage volume, no changes are needed.

4. Allocate the storage disk space:
 - a. Default storage group: 50% of current storage volume
 - b. Internal storage group: 5GB for Appliance or 3GB for Software.

Note: In regards to file system, Logger is adaptable to both xfs and ext4. Logger does not recommend one in particular as none of them causes a significant impact in performance.

Java Memory Allocation

Logger 7.0 should be installed with a minimum of Java memory for the Report Engine to properly run. Logger will take the java memory values from the **logger.defaults.properties** file. If these are inferior to what is stated below, the user can update the values in **logger.properties** file accordingly.

To allocate Java memory space for Report Engine:

1. Follow the path based on installation type:
 - Appliance: **/opt/arcsight/userdata/logger/user/logger/logger.properties**
 - Software: **<logger-install-path>/userdata/logger/user/logger/logger.properties**
2. Update the file based on the appliance model:
 - L7600: Set Java memory to 24 GB as minimum.
 - L7500, L7500: Set Java memory to 4096 MB as minimum.

Event Archives

Event Archives enable you to save the events for any day in the past, **not including the current day**. Logger 6.5 or later saves the event along with its index information.

Caution: Ensure that both Configuration Backups (for configuration settings) and Event Archives (for data) run on a regular basis and are stored in a remote location. In the event of catastrophic failure, you will need to restore the most recent Configuration Backup and Event Archive. For information on Configuration Backups, see ["Configuration Backup and Restore" on page 436](#)

- For Logger Appliances, the location needs to be an NFS mount, CIFS mount, or SAN, which is configured using the Logger user interface.
- For Software Loggers, the location is a directory (either local or a mount point that you have already established on the Logger host).

Events in each storage group are archived separately. That is, one archive file is created for each storage group, for each day. In addition, you can bulk archive events—that is, specify a range of dates to archive events in a single archive operation.

Archiving events from each storage group to a separate archive location enables you to keep data in specific storage groups longer than others. You need to specify these locations when you configure the Archive Storage Settings before archiving any events. The **Mount Location** field is not available on a Software Logger.

- For Logger Appliances, the path you specify in the Archive Path field is appended to the path specified in the Mount Location.
- On a Software Logger, you need to enter a complete path where the archive file will be written in the Archive Path field. This path could be a local directory or a mount point that is already established on the machine on which the Logger software is installed. The **Mount Location** field is not available on a Software Logger.

Logger uses the receipt time of an event to determine its archival day. For example, an event with a timestamp of 11:55:00 PM on December 7 is received at 12:01:00 AM on December 8 on the Logger. This event is archived in the archive file created for December 8th and not December 7th. When an archive operation occurs, one archive file per storage group is created at the location specified in **Archive Storage Settings**. Each archive file contains events from 12:00:00 AM to 11:59:59 PM for a single storage group of any given day. When you specify a range of dates, one archive file per storage group, for each specified day is created.

You can archive events in two ways: **manually** and **scheduled**. When archiving events manually, you specify the start and end dates of the event archive, and the storage groups that should be archived. This operation occurs once for the specified date range. When scheduling event archives, you specify the time at which the archive operation should occur every day and select the storage groups that should be included.

Note: You cannot set event archives to start at 1 AM for scheduled archives. This restriction is by design to account for the Daylight Savings Time (DST) changes.

When Logger starts archiving, it proceeds sequentially through the various storage groups, as listed on the **Daily Task Settings** page (for scheduled archives) or the **Add Event Archives** page (for manual archives).

Once the events have been archived, they are not deleted from the local storage until the events (and their related indexing information) age out due to the Maximum Live Data. These events continue to be included in search operations until they age out.

Once events that have been archived are deleted from Logger's local storage, they are not included in search operations. To include such events in search operations, you must load the archive in which those events exist back to the Logger. When an Event Archive is loaded, its events are included in searches, but the archive itself remains on the remote storage.

Nevertheless, archived events on a remote storage can also have a retention period. By editing the correspondent storage group, the user can determine a maximum age parameter. **Maximum Archives Age** (Days) prevents the user from taking additional steps to periodically clean the remote system space. Once the retention policy is triggered, the non compliant archives are removed from the database and filesystem with no option for rollback or backup. For information about setting archived events retention policy, see ["Storage Groups" on page 405](#)

The source type information (if associated with an event) is preserved when the event is archived. For information on creating and using source types, see ["Source Types" on page 367](#)

Archiving Events

To save events for a particular day, you need to add an Event Archive. The table in the Event Archives page shows the current archives and their status.

An archive storage location must be established on the Logger before you can archive its events. This is a one-time configuration. To establish an archive storage location, see ["Archive Storage Settings" on page 416](#).

Guidelines for Archiving Events

- Be sure to run configuration backups as well as event archives regularly, and to store them in a remote location. In the event of catastrophic failure, you will need to restore the most recent configuration backup and event archive. For information on configuration backups, see ["Configuration Backup and Restore" on page 436](#).
- If you need to archive a large number of events (in the order of tens of GB), Micro Focus recommends that you archive during the off-peak hours to prevent impacting the performance of your Logger.
- Events are archived based on the receipt time only.
- Multiple archiving operations such as loading, unloading, archiving, and deletion of archives can occur simultaneously. Therefore, you can initiate the loading of an existing archive, while an archive operation is in progress.

Tip: Only one manual archive job can run at a time. However, a scheduled archiving operation can run in parallel with a manual job.

- You cannot re-archive the events that have already been archived. If you try to do so, the Logger reports an error.
- Do not move the archived files from their archive location. The archives that have been moved from the originally archived location cannot be loaded on to the Logger. If you need to delete the archives, use the Logger user interface to do so.
- If an archive job fails, you need to initiate it manually. To do so, delete the failed archive and archive it manually. To be notified of a failed archive, configure an alert for this audit event: **Event Archive Failed**. For more information about this event, see ["Logger Audit Events" on page 569](#). For more information about configuring alerts, see ["Saved Searches" on page 315](#).
- If a Logger Appliance goes down while an archive operation is in progress, you need to re-initiate the archive operation for only the storage groups that were not archived when the operation failed. The status of such storage groups is marked "Failed" in the Status column on the Event Archives page.
For example, you archive the event data of 12/1/16, which consists of events from four storage groups "Default", "Internal", "Short-Term", and "Long-Term". The appliance goes down after the events from the "Default" and "Internal" groups have been successfully archived, and the events from "Short-Term" are being archived. The status of the "Short-Term" storage group on the Event Archives page will display

“Failed”, while the status of the “Default” and “Internal” groups will display “Archived”. (The status of the “Long-Term” storage group will not be displayed.) In this case, you need to manually re-initiate the archive for the “Short-Term” and “Long-Term” storage groups.

Note: In the above example, the status of the “Long-Term” storage group is not displayed on the Event Archives page after the failure occurs because archival of this group was never initiated during that archive operation.

If an archive operation fails, make sure you determine the storage groups that could not be archived and re-initiate the archival for all of those groups manually.

- You can cancel an in-progress archive operation that was manually initiated at any time using the **Cancel** link that displays on top of the Event Archives page.

To add an Event Archive:

1. Open the **Configuration | Storage** menu and then click **Event Archives**.
2. Click **Add** in the Event Archives page.
3. Enter a meaningful name in the **Name** field for the new Event Archive and specify the **Start** and **End** dates in the format **m/dd/yy**, where **m** is month number, **dd** is the day of the month (with a leading zero if necessary), and **yy** is the two-digit year number.

When the Start and End dates are different, one archive file per storage group, for each specified day is created. For example, if you specify the following Start and End dates:

Start Date: 8/12/19

End Date: 8/13/19

Note: If a day's events have already been archived, you will not be able to archive them again. If you try to archive the same day's events twice, Logger will display a message with the already archived day or dates. If you are archiving a range of dates and some of them have been archived, the archive process will complete, skipping any days already archived, and a message will display the already archived dates.

And, if you configure both storage groups—**Internal Event Storage Group** and **Default Storage Group**, four archive files will be created as a result of this archive operation—two files per storage group for the specified two days.

The Event Archives table (under the Event Archives page) lists the archives by an alias in this format: **<archive_name> [<yyyy-m-dd>] [<storage_group_name>]**.

4. Select the names of storage groups that need to be included in the archive.
5. Click **Save** to start archiving events, or **Cancel** to quit.

Note: You can cancel an in-progress archive operation at any time using the **Cancel** link that displays on top of the Event Archives page.

To remove an Event Archive:

1. Open the **Configuration | Storage** menu and then click **Event Archives**.
2. Select the event archives that you want to delete by clicking the checkbox in the left side.
3. Click **Remove** from the top of the screen to delete the selected archives.
4. Confirm the deletion by clicking **OK**, or click **Cancel** to retain the Event Archive.

To sanitize an Event Archive:

Logger performs a sanitize process to find and fix inconsistencies in your stored data.

1. From the **Configuration | Storage** menu, click **Event Archives**.
2. Select the event archives that you want to sanitize by clicking the checkbox on the left side of each row.
3. Click **sanitize** from the top of the screen. This button will be enabled only when the archive is unloaded.
4. Confirm the action by clicking **OK**, or click **Cancel** to dismiss the request.

The sanitize process can take several minutes depending on the size of the archive. For instance, a 26 GB archive with 2 non-consistent metadata can take up to 10 minutes to sanitize. Check the sanitize status for more information:

- **None:** This is the default value for new archives created or during upgrades to 7.0.
- **Pending:** Process has been interrupted or not started.
- **Done:** Process is successfully completed.
- **Failed:** Process has failed.

Once the process is completed, Logger displays the **logger_archive_sanitization.log** which allows you to review the deleted chunks, CSV generated, data files and metadata analyzed, and beginning and end time of execution.

Loading and Unloading Archives

Archived events must be loaded back on Logger before they can be included in a search operation. When an Event Archive is loaded, its events are included in searches, but the archive itself remains on the remote storage. When an Event Archive is unloaded, it is available for loading, but its events are not included in searches. You can unload a loaded archive if you no longer need to include it in your search operations.

Starting from Logger 6.5, archive indexes are loaded and unloaded with the archive. See ["Indexing Archived Events" on the next page](#) for more information.

Note: Even though an archive has been created, you cannot load an archive for data that is still in current storage. That is, loading the archive will fail if that data has not already passed its retention date and been aged out of current storage.

To load or unload an Event Archive:

1. Open the **Configuration | Storage** menu and then click **Event Archives**.
2. Click the checkboxes in the left-most column to select the event archives that you want to load or unload.
3. Click **Load** or **Unload** from the top of the screen to load or unload the selected archives.

Note: If you index an archive while the archive is loaded, the archive will be automatically reloaded after the index is created.

Indexing Archived Events

About

Archived events created since Logger 6.5 are automatically indexed. Although Index data is not stored when the events are archived in Logger 6.41 or older versions, you can build an index for existing archives. After creation, the index will be located in the same root of current archive and in the newly created subdirectory name with “Index” postfix.

Searching for events in loaded archives that do not have indexes is slower than searching events that still exist in current storage. Indexing an archive will increase performance when searching the archived data. After indexing an archive searching on events in that archive will be as fast as searches in local storage.

When indexing archives that are already loaded, users must unload the archive and load it again.

Tip: The tmp directory and the archive directory must both be writable and have enough space for the index to be created.

To index an Event Archive in Logger 6.41 or older versions

1. Open the **Configuration | Storage** menu and then click **Event Archives**.
2. Click the checkboxes in the left-most column to select the event archives that you want to index.

Caution: Archives take a long time to index and searches may be slower while indexing is taking place. Only index the archives you need.

3. Click **Index** from the top of the screen to index the selected archives.

Tip: You cannot cancel the indexing once it is in progress, but you can cancel indexing of archives in the pending queue. To cancel indexing, click the checkboxes in the left-most column

and select event archives with the Indexing Status of **Pending**. Then click **Cancel Index**.

Note: If indexing fails, check the log for the cause of failure. After you fix the problem, try indexing again.

Daily Archive Settings

You can schedule a daily event archive and specify what hour of the day it should run. Scheduled event archives that have finished running appear on the archive list on the Event Archives page. Only one scheduled event archive can run at a time; however, it can run in parallel with a manually scheduled archive.

Make sure you are familiar with the information in ["Time/NTP" on page 462](#) before you schedule an event archive.

To schedule a daily event archive:

1. Open the **Configuration | Storage** menu and then click **Daily Archive Settings**.
2. Select a time from the **Time For Daily Archive to Start** list.

Tip: Scheduled archives must start on the hour. Midnight and 1:00 AM are not on the list to allow your Logger to receive all of the previous day's events.

3. Select the storage groups whose events should be included in the scheduled archive.
4. Click **Save** to schedule daily event archive, or click on another page to cancel.

Archive Storage Settings

On the Logger Appliance, Event Archives are saved to a specific NFS or CIFS mount point, or SAN. For the Software Logger, event archives are saved to the specified directory, which can be a path to a local directory or to a mount point on the machine on which the Software Logger is installed. To establish a mount point, see your system's operating system documentation.

To perform Archive Storage Setting setup:

1. If you are using the Logger Appliance, create the NFS or CIFS mount point. (See ["Storage" on page 475](#) and ["Remote File Systems" on page 475](#).)
If you are using Software Logger and intend to use an NFS or CIFS mount point, ensure that the external storage point is mounted on the machine on which Logger is installed. See your system's operating system documentation for more information.
2. Open the **Configuration | Storage** menu and then click **Archive Storage Settings**.

3. Specify a mount location and an archive path for each storage group. You can specify a different path for each storage group, thus enabling the Logger to archive events to a different location for each storage group.
 - For Logger Appliances, choose the name of an NFS mount, CIFS mount, or SAN mount point for the **Mount Location** field. This drop-down list contains the names you specified when creating the NFS, CIFS, or SAN mount points (**System Admin > Storage > Remote File Systems**).
For example, if the mount location you selected refers to the path `/opt/ARCHIVES`, and the archive directory in that location is `archivedir`, then specify `archivedir` in the **Archive Path** field.
 - For Software Loggers, the **Mount Location** field does not exist. You need to enter a complete path where the archive file will be written in the **Archive Path** field. This path could be a local directory or a mount point that is already established on the machine on which the Logger software is installed.
For example, you could specify `/opt/ARCHIVES/archivedir`.

Note: You must configure settings for all storage groups on the Archive Storage Settings page even if you do not intend to archive all of them.

4. Click **Save**.

Scheduled Tasks

Scheduled tasks are jobs that are programmed to happen automatically. Job types include Configuration Backup, File Transfer, Event Archive, and Saved Search. The options in the **Configuration | Scheduled Tasks** category enable you to manage the scheduled tasks.

Make sure you are familiar with the information in ["Time/NTP" on page 462](#) that can impact a scheduled task.

- [Scheduled Tasks](#)417
- [Currently Running Tasks](#) 418
- [Finished Tasks](#) 418

Scheduled Tasks

Scheduled Tasks can be created for the following activities:

- Saved Searches (See ["Scheduled Searches/Alerts" on page 317](#).)
- File Receivers and File Transfer Receivers (See ["Receivers" on page 346](#).)
- Event Archives (See ["Archiving Events" on page 412](#).)
- Configuration Backups (See ["Configuration Backup and Restore" on page 436](#).)
- Lookup File Updates (See ["Lookup Files" on page 336](#).)

The Scheduled Tasks page displays the list of scheduled jobs. Some tasks can be managed from this screen. The available management options, which may include edit, enable, disable and delete, are displayed at the right end of the column.

A drop-down list at the top of the page lets you display all scheduled tasks (**All**), or only tasks of a specific type.

To view Scheduled Tasks:

1. From the Configuration menu under Scheduled Tasks, click **Scheduled Tasks**.
2. Filter the list by selecting a specific type of Scheduled Task from the drop-down list, or select **All**.
3. Click **Refresh** to update the list of tasks.

To delete a Scheduled Task:

1. From the Configuration menu under Scheduled Tasks, click **Scheduled Tasks**.
2. Locate the Scheduled Task that you want to delete and click the Remove icon (✕) on that row.
3. Confirm the deletion by clicking **OK**, or click **Cancel** to retain the Scheduled Task.

Currently Running Tasks

The Currently Running Tasks page displays the Scheduled Tasks that are running right now. The table shows task name, type, and the date and time that the task started.

Prerequisites

Users must be assigned to the following User Groups to access this feature:

- Default Logger Rights Group
- Default System Admin Group

See ["Setting Logger User Permissions" on page 510](#) for more information.

To view tasks that are running now:

1. From the Configuration menu under Scheduled Tasks, click **Currently Running Tasks**.
2. Click **Refresh** to update the list of tasks.
3. Filter the list by selecting a specific type of Scheduled Task from the drop-down list, or select **All**.

Finished Tasks

The Finished Tasks page displays the Scheduled Tasks that have finished running. The Finished Tasks page acts like a log of all Scheduled Task runs, with the most recently finished tasks on top.

To View Finished Tasks:

From the Configuration menu under Scheduled Tasks, click **Finished Tasks**.

Filtering the Task List

You can filter the task list by time or duration, job type, task result, or by text search. By default, the task list displays the finished tasks for the last 24 hours, displaying 20 entries per page.


Tip: Click **Filter** at any time to update the Finished Tasks list.

Filtering finished tasks by time

1. From the first filter menu, select one of the following options, or leave the default:
 - **Last 24 hours** (the default) — Returns completed tasks for the previous 24 hours.
 - **Last 7 Days** — Returns completed tasks for the previous seven days.
 - **30 days** — Returns completed tasks for the previous 30 days.
 - **Custom Time Range** — Returns completed tasks for a custom date and time range. See ["Filtering finished tasks by a specific date and time"](#) below.
2. Optionally, click **Filter** to see your results, or add more filtering criteria.

Filtering finished tasks by a specific date and time

When you select Custom Time Range, the Date and Time fields display.

1. Enter a date in the **Start Date** field. You can enter the dates in **mm/dd/yyyy** format, or click the calendar icon () to select a date. Do the same for the **End Date** field.
2. Optionally, enter a start and end time from the **Time** menus. You can enter the times in **hh:mm:ss** format, or accept the default start time of **00:00:00** and end time of **23:59:59**.
3. Optionally, click **Filter** to see your results, or add more filtering criteria.

Filtering finished tasks by job type or task result

Optionally, select from the list of job types and job results to further narrow your search criteria. Click **Filter** to see your results, or add more filtering criteria.

Filtering finished tasks by text search

Optionally, enter a text word or phrase in the text search field to return a list of tasks containing the text. As you type, matching text will be highlighted. Click **Filter** to see your results.

Finished Tasks

Last 7 days ▾ Job Type Report ▾ Job Result Passed ▾ [Filter](#)

repor

| Name | Start |
|------|-------|
| | |
| | |

Report

- All
- Aggregate Info Maintenance
- Cleaning Service
- Configuration Backup
- FTP Transfer
- Lookup File Update
- Peer Authorization Expiration
- Report
- Scheduled Search
- Scheduled Alert
- Scheduled Archive
- SCP Transfer
- SFTP Transfer

Advanced Configuration

The options in the **Configuration | Advanced** category enable you to manage the advanced tasks. Most of these tasks require administrator privileges.

- [Retrieve Logs](#)420
- [Maintenance Operations](#)422
- [Maintenance Results](#) 436
- [Configuration Backup and Restore](#)436
- [Content Management](#) 441
- [How does EPS license differ from GB per day license?](#) 444
- [Standalone License Information](#)445
- [Managed by ArcMC License Information](#)448
- [Trial Licenses](#)449
- [Logger Software Installations and Licenses](#) 449
- [Peer Nodes](#) 450

Retrieve Logs

Logger records some audit and debug information, including details of any issues that occur. These system logs (not be confused with the event logs), are like the "black box" on an airliner. If something goes wrong, the logs can be helpful. Customer support may ask you to retrieve logs as part of an incident investigation. If so, follow the steps below and provide the resulting .zip file to customer support.

When retrieving logs, you have the option to sanitize the log files by obfuscating the IP addresses, hostnames, and email addresses. However, sanitizing adds extra time to log retrieval. Each sanitized IP

address, hostname, and email address is replaced by the symbols **xxx.xxx.xxx.xxx** (for IP addresses), **sanitized@email** (for emails) and **sanitized.host.name** (for hostnames).

Retrieve Logs page

To retrieve Logger system logs:

1. Open the **Configuration | Advanced** menu and then click **Retrieve Logs**.
2. Select the Log Retrieval options to use when creating the Log file.
 - If you select **Do not sanitize logs (fastest)**, then all IP addresses, hostnames and email addresses will be kept in the log file.
 - If you select **Remove IP addresses**, all IP addresses in the log will be obfuscated. You cannot specify individual IP addresses.
 - If you select **Remove IP addresses, hostnames, email addresses, session IDs, and passwords (slowest)**, the password string will be obfuscated. You must specify the suffixes of the hostnames and email addresses in the text box.

Separate multiple suffixes with comma, space, or line-break. For example, to obfuscate all hostnames and email addresses that end with microfocus.com and gmail.com, you could specify the following:

microfocus.com, gmail.com

All IP addresses, hostnames, and email addresses with the specified suffixes will be obfuscated. Specifying individual email addresses like name@microfocus.com is not supported. Individual email addresses and their suffixes will be ignored.

For security purposes, the information from sessions table is excluded in this report. In that same regard, passwords will be hashed when rendering report that includes .dat and .SQL files.

3. Click Retrieve Logs. The page will display a progress bar while the logs are being retrieved.
4. When the collection is complete, the system log files have been compressed into a single zip file. A link to this file is displayed on the Log Retrieval page. Click the link to download the file.

Collecting Logger deployment environment information

This option enables you to compile the basic environment information in one single file allowing a more direct interaction with the Support Team. The retrieve package will usually be available (but can vary based on Logger type) at [LOGGER_HOME] /tmp. The **include deployment info/stats** box (checked by default) includes a json file attachment in the logs.zip. To get only the json file, click **Download Environment info** button.

loggerdeploymentinformation.json contains the following information:

- current time
- Logger information : installation type (SW/Appliance), Product version, Model, ESP.
- OS information

- Processor information
- Memory information
- Average EPS, current EPS
- Receivers
- Forwarders
- Peers
- Alerts
- Storage Group
- Storage volume
- Failed Archive
- Data volume

Maintenance Operations

Certain operations on Logger, such as database defragmentation, extending the storage volume size, adding storage groups, and adding additional schema fields, require that Logger be in a maintenance state—a state in which operations related to data on the Logger are not running. Maintenance mode enables you to place the Logger in such a state. When a Logger is in maintenance mode:

- Events are not processed
- Reports are not generated
- Search cannot run
- Scheduled jobs do not run

Tip: You cannot place a Logger in maintenance mode directly. A Logger can enter maintenance mode only to perform an operation that requires it to be in that mode.

Caution: Do not restart/reboot a Logger in Maintenance Mode from the command line. Use the restart link on the Maintenance page.

Required Permissions for Maintenance Mode


Logger users who will be performing operations that require it to be in maintenance mode must have the “Enable Maintenance Mode” privilege checked (**System Admin > User Management > Groups tab > System Admin Group**). See ["Users/Groups" on page 495](#) for more information on Logger user rights and how to administer them. When a Logger is in maintenance mode, users with the “Enable Maintenance Mode” privilege see a message stating Logger has been placed in maintenance mode.

For all other users, the log-in screen displays a message Logger has been placed in maintenance mode by another user.

Entering and Exiting Maintenance Mode

To Enter Maintenance Mode:

1. From the **Configuration | Advanced** menu, click **Maintenance Operations**. The Maintenance Operations panel displays the available options.



2. Click an option on the Maintenance Operations panel. A confirmation window displays for that option.
3. Click **Enter Maintenance** and follow the instructions for the maintenance operation you selected:
 - ["Defragmenting the Logger Database" on the next page](#)
 - ["Defragmenting Global Summary Persistence" on page 427](#)
 - ["Storage Volume Size Increase" on page 428](#)
 - ["Adding Storage Groups" on page 430](#)
 - ["Adding Fields to the Schema" on page 431](#)

To Exit Maintenance Mode:

1. Reboot the the Logger Appliance or restart the Software Logger using the link on the Maintenance Mode page.

Caution: Do not restart/reboot a Logger in Maintenance Mode from the command line. Use the restart link on the Maintenance page.

Defragmenting the Logger Database

Logger's database can become fragmented over time. Frequent retention tasks can exacerbate this issue. The following symptoms appear on a Logger when the database should be defragmented:

- Slow search and reporting
For example, even a search operation over the last two minutes of data is slow.
- Long pauses in the receiver and forwarder operations

You can defragment a Logger that exhibits these symptoms. Make sure that you have read the following guidelines before starting the defragmentation process.

Guidelines for Database Defragmentation

Ascertain that the Logger symptoms are not due to issues related to network infrastructure, such as network latency or unexpected load on the Logger.

The Logger system needs to be placed in maintenance mode before defragmentation can begin. As a result, most processes on the Logger are stopped—no events are processed or scheduled jobs run, and most user interface operations are unavailable. For more information about maintenance mode, see ["Maintenance Operations" on page 422](#).

A minimum amount of free disk space is required on your system to run database defragmentation. The utility automatically checks for the required free space and displays a message if it doesn't have sufficient disk space.

Tip: Although you can defragment as needed, if you are using this utility too often (such as on a system that was defragmented over the last few days), contact customer support for guidance.

If the defragmentation process fails at any point, the Logger returns to the same state that it was in before you started defragmentation:

You can safely reboot the Logger Appliance and restart the process from the beginning. For the Software Logger, restart the Logger process as described in ["Process Status" on page 469](#).

Required Permissions

You can perform this process only if you have the **"Enable Maintenance Mode"** privilege set to **Yes** in the **System Admin Rights** list for the System Admin Group to which you are assigned. To set, navigate to **System Admin > User Management > Groups tab > Manage Groups** page, select a System Admin Group and click **Add** or **Edit**.

See ["Users/Groups" on page 495](#) for more information on Logger user rights and how to administer them.

Defragmenting a Logger

To defragment a Logger:

1. Open the **Configuration | Advanced** menu and then click **Maintenance Operations**.

The Maintenance Operations panel, described in ["Maintenance Operations" on page 422](#), displays the available options.

2. Click **Database Defragmentation**.

3. Click **Enter Maintenance** so that the Logger can enter maintenance mode.

A minimum amount of free storage is required for the database defragmentation process to proceed. Therefore, Logger performs a check to determine free storage when entering maintenance mode.

4. Click **Begin Defragmentation**.

- If the required storage is not found, follow the instructions found in ["Freeing Defragmentation Storage Space" on the next page](#).
- If the required amount of free storage is found and Logger successfully enters maintenance mode, the following screen is displayed.

Begin Database Defragmentation

Database Defragmentation

Before performing any maintenance operation, Logger must first enter maintenance mode to safeguard event data. During this time, Logger won't receive or forward events. Once in maintenance mode, Logger will need to be restarted to resume normal operations.

This will take about two minutes to complete.

Please check the Logger release notes for additional information.

Press **Enter Maintenance** to enter maintenance mode now.

Enter Maintenance

Note: On the Software Logger, the following Database Defragmentation screens instruct you to click **Restart** to resume normal operation when Logger is in maintenance mode. When you click restart, only the Logger service and its related processes are started on the machine on which the Software Logger is installed.

5. The defragmentation process starts. A progress indicator shows the status of defragmentation, as shown in the example below. Micro Focus recommends that you do not attempt any operation on the

Logger until defragmentation has completed.

Once defragmentation is complete, the Logger reboots automatically. This exits maintenance mode.

Freeing Defragmentation Storage Space

If the required storage is not found, Logger prompts you to free sufficient space:

You can choose from one of the following options:

- **Manual Deletion**

Note: The Manual Deletion option is not available on L7x00 Loggers.

A text file is automatically created on your Logger that lists the files you can safely delete. On the Logger appliance, this file is located in

`/opt/arcsight/logger/user/logger/defragmentation/filelist.txt`

On Software Loggers, this file is located in `<install_dir>/current/arcsight/logger/user/logger/defragmentation/filelist.txt`.

The files are listed in descending order of size in the text file. You can delete sufficient number of files to free up storage. However, **do not** delete the files before contacting customer support for instructions and guidance.

Follow these steps to proceed:

- a. Leave the message screen without taking any action.
- b. Contact customer support for instructions on deleting files listed in the text file.
- c. After deleting sufficient number of files, resume the Database Defragmentation process from the message screen. To resume, click **Recheck** to check whether sufficient storage is now available for defragmentation to proceed.

If sufficient storage is found, the ["Begin Database Defragmentation" on the previous page](#) is displayed. Click **Begin Defragmentation** to proceed further.

If sufficient storage is still not found, a message displayed. Choose from the listed options to create additional space.

Note: If you need to exit the defragmentation process without creating sufficient storage, click **Reboot**.

- **Delete Database Indices**

Logger automatically deletes a sufficient number of database indices, starting with the largest index, to free up the required amount of storage. If sufficient space becomes available after deleting database indices, defragmentation proceeds further automatically.

However, if sufficient storage is not available even after dropping database indices, follow these steps to proceed:

- a. Click **Manual Deletion**.

Note: The Manual Deletion option is not available on L7x00 Loggers.

A text file is created on your Logger that lists the files you can safely delete. The files are listed in descending order of size in a text file.

- b. Click **Reboot**.

Logger exits the maintenance mode.

- c. Contact customer support for instructions on manually deleting the files.

You can delete sufficient number of files to free up storage.

- d. After deleting the files, restart the defragmentation process as described in ["To defragment a Logger." on page 425](#).

Note: If the defragmentation process fails or is aborted at any time, Logger must recover those indices. Although the recovery process is automatic, it can take at least a few hours to complete. You will not lose any data during this process.

- **Reboot**

The database defragmentation process is aborted and Logger returns to the state it was in before you started the defragmentation utility.

Defragmenting Global Summary Persistence

There is a known issue with the Global Summary Persistence functionality. This feature was designed to persist the statistics reported in the global summary section of Logger through a reboot. In some environments, disk space may be affected due to this feature.

Global Summary Persistence is disabled in this release. No action should be necessary in most cases. However, if you have just upgraded from Logger 5.3, you should defragment the Global Summary Table as soon as possible. Make sure that you have read the following guidelines before starting the defragmentation process.

Guidelines for Defragmenting Global Summary Persistence

- The Logger system needs to be placed in maintenance mode before Global Summary Persistence defragmentation can begin. As a result, most processes on the Logger are stopped—no events are processed or scheduled jobs run, and most user interface operations are unavailable. For more information about maintenance mode, see ["Maintenance Operations" on page 422](#).
- A minimum amount of free disk space is required on your system to run Global Summary Persistence defragmentation. The utility automatically checks for the required free space and displays a message if sufficient disk space is not found.

- If the defragmentation process fails at any point, the Logger returns to the same state that it was in before you started defragmentation. You can safely reboot the appliance or restart the Software Logger process and try again.
 - a. Reboot the Logger Appliance as described in ["System Reboot" on page 458](#).
 - b. For the Software Logger, restart the Logger process as described in ["Process Status" on page 469](#).

Required Permissions

You can perform this process only if you have the "Enable Maintenance Mode" privilege set to Yes (**System Admin > User/Groups > Manage Groups > System Admin Group**). See ["Users/Groups" on page 495](#) for more information on Logger user rights and how to administer them.

To defragment for the Global Summary Persistence issue:

1. Open the **Configuration | Advanced** menu and then click **Maintenance Operations**.
The Maintenance Operations panel, described in ["Maintenance Operations" on page 422](#) displays the available options.
2. Click **Global Summary Persistence Defragmentation**.
3. Click **Enter Maintenance** so that the Logger can enter maintenance mode.
4. Click **Begin Global Summary Persistence Defragmentation** to start the defragmentation process.
5. The defragmentation process starts. A progress indicator shows the status of defragmentation. Micro Focus recommends that you do not attempt any operation on the Logger until defragmentation has completed.

Once defragmentation is complete, the Logger reboots or restarts. This automatically exits maintenance mode.

Note: On Software Loggers, only the Logger service and its related processes are restarted.

Storage Volume Size Increase

You can extend the storage volume size you established during initialization at any time. Once extended, the volume size cannot be reduced. The Logger interface guides you about current and the maximum value to which you can increase the size.

Note: For the "Storage Volume Size Increase" operation to show as an option under the System Maintenance operations (**Configuration | Advanced > Maintenance Operations**), you need to belong to the System Admin group (with "Enable Maintenance Mode" privilege enabled) and the Logger Rights group. See ["Users/Groups" on page 495](#) for more information on Logger user rights and how to administer them.

About Increasing Storage Volume Size on a SAN Logger

Logger cannot detect a resized LUN. Therefore, if you change the LUN size after it has been mounted on a Logger, the new size is not recognized by Logger. As a result, you can only increase the size of a storage volume to the LUN size that was initially mounted on the Logger.

You should make your initial LUN size as large as possible before mounting. The following examples illustrate storage volume increase on a SAN Logger.

| Initial LUN Size | LUN Resized | Current Storage Volume Size | Storage Volume Size Increase Allowed |
|------------------|-------------|-----------------------------|--------------------------------------|
| 4 TB | No | 1 TB | Yes, up to 4 TB |
| 4 TB | No | 4 TB | No |
| 8 TB | No | 4 TB | Yes, up to 8 TB |
| 2 TB | 8 TB | 1 TB | Yes, only up to 2 TB |
| 4 TB | 8 TB | 1 TB | Yes, only up to 4 TB |
| 8 TB | 8 TB | 4 TB | Yes, up to 8 TB |
| 12 TB | 12 TB | 8 TB | Yes, up to 12 TB |
| 16 TB | 16 TB | 12 TB | Yes, up to 16 TB |
| 24 TB | 24 TB | 16 TB | Yes, up to 24 TB |

To increase the storage volume size:

1. Select **Configuration | Maintenance Operations** from the navigation bar.
The Maintenance Operations page displays the available options. See ["Maintenance Operations" on page 422](#).
2. Click **Storage Volume Size Increase**.
3. Click **Enter Maintenance** so that the Logger can enter maintenance mode.

While entering the maintenance mode, Logger performs a check to determine if the storage volume size can be increased and by what amount. If the storage volume can be increased, then enter the new size and click **OK**.

Note: On the Software Logger, the Storage Volume Size Increase screen instructs you to click **restart** to resume normal operation when Logger is in maintenance mode. When you click restart, only the Logger service and its related processes are restarted.

If sufficient space is not found to increase the storage volume, a message is displayed. Click **Reboot** to restart Logger and exit maintenance mode.

Adding Storage Groups

In addition to the two storage groups that exist on your Logger by default, you can add up to 48 additional storage groups. You can add storage groups at any time if the following conditions are met:

- The maximum allowed 48 storage groups do not exist on your Logger already.
- The storage volume contains spare storage space that can be allocated to the storage groups you will add.

Tip: If you do not have sufficient space in the storage volume to add another storage group and the existing groups have free space, consider reducing the size of existing storage groups to make space available for the storage groups you want to add. Alternatively, increase the size of your existing storage volume, as described in ["Storage Volume Size Increase" on page 428](#).

The Logger must be in maintenance mode when adding storage groups. When you add a storage group, Logger automatically checks to ensure that the storage group size you specified is greater than the minimum size required (5 GB) and less than the amount of space available in the storage volume.

Once you have added storage groups and rebooted your Logger to exit the maintenance mode, remember to configure the Archive Storage Settings for the groups you just added so that event archives are created for them.

To add a storage group:

1. Open the **Configuration | Advanced** menu and then click **Maintenance Operations**.

The Maintenance Operations panel, described in ["Maintenance Operations" on page 422](#) displays the available options.

2. Click **Add Storage Groups**.

A maximum of 48 storage groups can exist on Logger. Therefore, you can add up to 48 storage groups in addition to the 2 that exist by default on Logger.

If the maximum number of allowed storage groups **do not** exist on Logger, a screen prompts you to enter maintenance mode, as described in the next step.

If all 48 storage groups exist on Logger or sufficient space does not exist in the storage volume to add additional group, a message is displayed on your screen and the Logger cannot enter maintenance mode.

3. Click **Enter Maintenance** so that the Logger can enter maintenance mode.

For more information about maintenance mode, see ["Maintenance Operations" on page 422](#).

4. Once Logger enters maintenance mode, the following Add Storage Groups page is displayed.

This screen also lists information about the existing storage groups and the amount of space remaining in the storage volume.

5. Enter the following information.

| Parameter | Description |
|--------------------|---|
| Name | Choose a name for the storage group. |
| Maximum Age (Days) | Specify the number of days to retain events. Events older than this number of days are deleted. |
| MaximumSize (GB) | Enter a maximum event data size, in GB. |

6. Click **Add**.

The storage group is added to your Logger. If your Logger has not reached the maximum allowed 48 storage groups, you can click **Add** to add more storage groups. However, if the maximum number has been reached, the Add button is not displayed. If you do not want to add more storage group, go to the next step.

7. To apply your changes and exit maintenance mode, reboot your Logger Appliance or restart Software Logger.

Adding Fields to the Schema

The Logger schema contains a predefined set of fields. A field-based query can contain only these fields. Additionally, you can index only these fields for faster search operations. For instructions on how to view the default Logger schema fields, see ["Default Fields" on page 333](#).

Prior to Logger 5.2, if your log analysis needs required you to search on a field that is currently not present in the Logger schema, you did not have a way of adding it to the schema yourself. Starting with Logger 5.2, you can add additional fields to the Logger schema. That is, you can insert fields in your Logger schema that are relevant to the events you collect on your Logger, thus enabling you to search and report using these fields. Additionally, you can index the fields you add so that the search and report queries that use these fields run faster. For example, a financial institution might want to add credit card numbers or social security numbers to the schema.

You can add up to 100 custom schema fields on Logger. You can also import custom fields from a peer Logger. However, the total number of added and imported fields cannot exceed the maximum allowed 100 fields.

You can index up to 123 fields on Logger. Therefore, the number of custom schema fields you can index will depend on the number of default fields you currently have indexed on your Logger.

Note: Logger cannot process the additional fields data received in CEF version 0 from a FlexConnector, and assumes a NULL value for such fields when they are present in a CEF version 0 event. As a result, you cannot search on these fields or index them. However, these fields are displayed in the UI display when you select "*" in the field set because the interface displays information contained in the raw event. Therefore, if Logger receives "ad.callnumber=5678", the Logger UI will display a column, ad.callnumber, with value 5678. However, a search on "5678" will not return this event in the search results.

You need to be in maintenance mode to add or import custom schema fields. The process of adding or importing schema fields involves an add or import operation followed by a save operation. The add or import operation adds the specified fields but does not write them to the Logger schema. You can edit or delete the added or imported fields at this point. Once you save these fields, the fields are written to the schema. From this point on, these fields cannot be edited or deleted. Therefore, carefully review the fields you are adding to the schema before saving them.

Note: For the “Add Fields” operation to show as an option under the System Maintenance operations (**Configuration | Advance > Maintenance Operations**), you need to belong to the System Admin group (with “Enable Maintenance Mode” privilege enabled) and the Logger Rights group. See ["Users/Groups" on page 495](#) for more information on Logger user rights and how to administer them.

You need to specify the following information to add a custom schema field

- **Additional data field** - If the **Add prefix ad. and suffix** box is not checked, the **actual field name** stored in Logger schema and the **field name** entered by the user will be the same. If the **Add prefix ad. and suffix** box is checked, **field name** stored in Logger schema as **actual field name** will be added automatically with prefix and suffix information. CEF events received by Logger must have the corresponding prefix and suffix in the field name, so the event field can be properly indexed and used in field-based search query.
- **Display name** — A meaningful name for the field. This name is displayed as the column header name for the field and is the one you specify in a search query. For example, SocialSecurityNumber. On the other hand, If you are adding a predefined CEF name, an auto suggestion list is displayed in this field.
- **Type** — The type of data this field will contain. The available options are Double, BigInt, DateTime, Text.

The following table describes each data type.

| Type | Description |
|----------|--|
| Double | Use to store decimal numbers or fractions. Numbers from -1.79769313486231570E+308 through -4.94065645841246544E-324 for negative values, and 4.94065645841246544E-324 through 1.79769313486231570E+308 for positive values. |
| BigInt | Use to store whole numbers. Numbers from -2^63 through 2^63-1 , or -9,223,372,036,854,775,808 through 9,223,372,036,854,775,807. |
| DateTime | Use to store both dates and time or only dates. |
| Text | Use to store any characters. You can store a maximum of 255 characters per field. |

- **Length** — This field is only relevant when the Type specified is **Text**. This field specifies the maximum number of characters allowed in the value of the field when the data type is Text.

This field is only relevant when the Type specified is **Text**. This field specifies the maximum number of characters allowed in the value of the field when the data type is Text.

- **Field name** — The field name that you want to add to the Logger schema. Typically, this is an abbreviated version of the **Display** name. For example, **SSN**.

Importing Schema Fields from Peers

If your Logger is a peer of another Logger, you can import the custom fields added to the peer's schema. You specify the peer from which you want to import fields in the user interface screen. Fields can be imported if the following conditions are met:

- A field of the same Display name and Field name does not exist on the Logger to which you are importing schema fields. If conflicting fields exist, they are still imported but are flagged in the user interface screen. You cannot save the imported fields to schema until you resolve the conflicts.
- A maximum of 100 custom fields has not been reached on the importing Logger. If there are more fields than can be imported, only the first **N** until the allowed maximum is reached will be imported.

The custom schema fields contained in a search query must exist on all peers on which the query is run. Otherwise, the query will not run and return an error.

To add or import custom schema fields:

1. Open the **Configuration | Advanced** menu and then click **Maintenance Operations**.

The Maintenance Operations panel, described in "[Maintenance Operations](#)" on page 422 displays the available options.

2. Click **Add Fields (100 additional fields can be added)**.

You can add a maximum of 100 custom fields to Logger schema. The number in the "Add Fields" link reflects the number of custom fields you can add. This number decreases as you add fields to Logger schema.

3. Click **Enter Maintenance** so that the Logger can enter maintenance mode.
4. Once Logger enters maintenance mode, the Add Fields page is displayed.

You can add fields manually or import them from a peer Logger.

To manually add fields:

1. After entering Maintenance Mode, click **Add a New Field**, if it is not selected.
2. With **Add prefix ad. and suffix** box checked, enter a meaningful name in the **Display Name** field.

The display name is the one you specify in a search query and is the column header for the field in search results. For example, SocialSecurityNumber. It is not added to the Logger schema. The majority of the display names are auto populated. If there is text while you hover over the field, it is not necessary to add a prefix (ad) and a suffix (i, d, r). If no text is displayed while you hover the field, add the prefix and its correspondent suffix type.

Follow these guidelines when specifying a display name:

- The display name must be unique; that is, another field (custom or Logger schema) of the same display name must not already exist on the Logger.
- Only ASCII characters are allowed. That is, no native Chinese or Japanese characters are accepted in this field.
- The display name can contain up to 100 alphanumeric and underscore characters. If you are adding a predefined CEF name, an auto suggestion list is displayed in this field.

Note: To be valid, the display name must not *start* with "arc_" or an underscore.

3. Select a data type for the field from the **Type** pull-down menu. The available options are Double, BigInt, DateTime, Text. See ["Adding Fields to the Schema" on page 431](#) for more information.
4. In the **Length** field, enter the maximum number of characters allowed in the value of the field *when the data type is Text*. This field is only available when the Type specified is Text. You can specify from 1 to 255 characters in this field.
5. Enter a name in the **Field** name field.

This is the name that will be added to the Logger schema. Typically, this is an abbreviated version of the Display name. For example, SSN.

Follow these guidelines when specifying a Field name:

- This is a required field.
 - The field name must be unique; that is, a custom field of the same Field name must not already exist on the Logger.
 - Only ASCII characters are allowed. That is, no native Chinese or Japanese characters are accepted in this field.
 - The field name can contain up to 40 characters and can contain alphanumeric, hyphen, and underscore characters. The underscore () is used as an escape character for the actual field name. Therefore, if you include an underscore in the field name, the actual field name will contain a double underscore ().
6. Click **OK**.

The field you added is displayed in the upper section of the Add Fields form, as shown in the following figure. This field is not saved yet (in "Ready to Save" state) and you can edit or delete it. Once you click Save, the field is added to the schema and cannot be changed or deleted.

Save

| Display Name | Type | Length | Field Name | Actual Field Name |
|---------------------|--------|--------|---------------------|------------------------|
| concentratorDevices | TEXT | 1 | concentratorDevices | ad.concentratorDevices |
| deviceProcessId | TEXT | 1 | dvcpid | ad.dvcpid |
| generator | BIGINT | - | generator | ad.generator.i |

You can import fields from peer nodes. Make sure this Logger is configured as the peer of the Logger from which you want to import fields.

Use Prefix ad. and Suffix data type ☒

Display Name

Type

Field Name

ag

managerReceiptTime

agentDescriptorId

agentReceiptTime

concentratorAgents

agentId

agentVersion

7. Repeat the steps above to add additional fields.
8. Review the added fields and make any edits (✎) or deletions (✕), if necessary.

Caution: The next step commits the added fields to Logger's schema. This process is irreversible; that is, once the fields are written to Logger's schema, they cannot be edited or deleted. If you exit this process without saving, the fields you were adding are not remembered and your changes are lost.

9. Click **Save** to commit the added fields and write them to your Logger's schema.

To import fields from a peer:

1. After entering Maintenance Mode, click **Import Fields From Peers**, if it is not selected.
2. Select the peer from which you want to import the fields from the **Peer Host Name** drop-down list.
3. Click **OK** in the bottom right corner of the screen.

If there are no conflicting fields, all fields from the peer are imported successfully.

If there are conflicts, the conflicting fields are displayed ahead of the ones that were imported successfully. The Status column describes the reason for the conflict. You must fix the listed issues

before you can save these fields to the schema. Use the edit (✎) or delete (✕) icons at the end of the row to make changes or delete the added fields.

If there are more fields than can be imported, only the first **N** until the allowed maximum (100) is reached will be imported.

Caution: The imported fields are not committed to Logger's schema yet. The next step commits them. This process is irreversible; that is, once the fields are written to Logger's schema, they cannot be edited or deleted.

If you exit this process without saving, the fields you were adding are not remembered and your changes are lost.

4. Click **Save** to commit the added fields and write them to your Logger's schema. Restart Logger to put the changes into effect.

If you added fields from a peer Logger, be sure to add the same fields to any other peers.

To view the custom schema fields, see ["Custom Fields" on page 335](#).

Maintenance Results

You can check the status of a maintenance operation on the Maintenance Results page.

To access the Maintenance Results page (as shown in the example below), open the **Configuration | Advanced** menu and then click **Maintenance Results**.

Configuration Backup and Restore

By default, Logger does not back up any content. However, you can configure it to back up the following content to a remote system:

- All non-event data (Except Lookup files)
- Reports content only

You can back up this content on ad-hoc basis or schedule it to run periodically. The content is saved to the backup location in a single **.tar.gz** format file.

Caution: Ensure that Configuration Backups (for configuration settings) and Event Archives (for data) run on a regular basis and are stored in a remote location. You should also store a copy of your license. In the event of catastrophic failure, you will need to restore the most recent Configuration Backup, Event Archives, and license. For information on Event Archives, see ["Event Archives" on page 410](#).

You can use the backed-up content to:

- Restore a Logger that is not functioning as expected or that has been reset to its factory defaults.
- Copy content from one Logger to another.

Caution: When you restore content to a Logger, the existing content on it is deleted or overwritten.

The following table lists the information included in the backup when you back up all non-event data and reports-only data.

| All non-event data backup includes... | Reports-only backup includes... |
|---|---|
| <div>System information</div> <div>License *</div> <div>Logs</div> <div>Global settings</div> <div>User and group information</div> <div>All configuration settings</div> <div>Existing filters and saved searches</div> <div>Logger Monitor settings</div> <div>The following Reports content:</div> <div><ul style="list-style-type: none">• Queries, Reports, Parameters, Parameter Value Groups, Dashboards• Templates</div> <div>Note: Lookup files are not included in configuration backups.</div> | <div>The following Report content only:</div> <div><ul style="list-style-type: none">• Queries, Reports, Parameters, Parameter Value Groups, Dashboards• Templates</div> |

Note: Configuration backups include server SSL certificates, located in /opt/arcsight/useropentransformation/platform but they are not automatically retrieved by the restoring script.

Running a Configuration Backup

Follow these steps to create and run a backup of your Logger configuration information.

To run a configuration backup or to edit the configuration backup settings:

1. Open the **Configuration | Advanced** menu and then click **Configuration Backup**.
2. Click the (✎) icon and enter the following parameters:

The screenshot shows a configuration dialog box for a backup. It includes the following fields and options:





- Transfer File Using:** A dropdown menu with 'SCP' selected.
- Port:** A text box containing '22'.
- IP/Host:** A text box with a blurred IP address.
- User:** An empty text box.
- Password:** An empty text box.
- Remote directory:** An empty text box.
- Schedule:** A section with a checkbox for 'One time only' (unchecked), a dropdown for 'Every day' (selected), and a dropdown for 'Hour of day' (selected) next to an empty text box. To the right of these is the label 'Hours (24 hour format)'.
- Backup content:** A dropdown menu with 'All' selected.
- At the bottom are two buttons: 'Save' (blue) and 'Cancel' (black).

| Parameter | Description |
|------------------------|--|
| Transfer File Using | <ul style="list-style-type: none">• Select SCP to transfer the file to a remote host.• Select CP to copy the file to location on Logger. The available options change depending on what you select. |
| Port (SCP Only) | The port on which the Logger should connect to the remote system. |
| IP/Host (SCP Only) | The IP address or hostname of the remote system. |
| User (SCP Only) | A user on the remote system with write privileges on the backup folder (specified in Remote Directory, below). |
| Password (SCP Only) | Password for the user. The password cannot contain these characters: % = ; " ' <> |

| Parameter | Description |
|---------------------------------|--|
| Mount location (appliance only) | Select a mount location on the appliance. Note: The mount location must be added prior to running a configuration backup. |
| Remote Directory | The location in which to save the configuration backup files. The remote directory name cannot contain spaces. Note: The Logger Appliance supports mounting through the user interface. Software Logger uses its file system, which can contain remote folders mounted through the operating system. |
| Schedule | Schedule when and how often the Backup is run. <ul style="list-style-type: none">• If you leave the default One Time Only checkbox enabled, other fields are hidden and the configuration backup occurs just once (ad-hoc), when you click Save.• If you disable the One Time Only checkbox, you can use the schedule options to specify how frequently the configuration backup should run. See "Scheduling Reoccurring Backups" below. |
| Backup Content | Whether to backup all non-event data or only the report content. <ul style="list-style-type: none">• Select All for all non-event data• Select Report Content Only for only the report content. |

3. Click **Save**. The configuration backup you set up is displayed on the Configuration Backup page.

Note: If you chose to run the backup **One Time Only**, the configuration backup is run right away. Otherwise, it is scheduled to run at the specified time.

4. Once you have created one or more configuration backups, you can take the following optional actions from the Configuration Backup page:
 - a. Click **Restore** to begin restoring your configuration backup. See ["Restoring from a Configuration Backup"](#) on the next page.
 - b. Click the associated edit icon (✎) or the name of the backup file to change your configuration backup parameters.
 - c. If the backup file you want is disabled, click the  icon to enable it (.
 - d. If a backup file you want is enabled, click the  icon to disable it (.

Scheduling Reoccurring Backups

When scheduling reoccurring backups, set the scheduling options as described in ["Scheduling Date and Time Options"](#) on page 145.

Restoring from a Configuration Backup

Make sure you are familiar with these guidelines before you restore a backup file on Logger:

- When you restore content to a Logger, the existing content on it is deleted or over-written.
Logger restores the specific environment settings that were current at the time the backup was taken. Any configuration settings that were updated between the time of the backup and the time of the restoration are lost. This includes the license file.
- You must edit the CIFS share settings and re-enter your username and password prior CIFS mount.
- You must restore the content to the same version of Logger that was used to create the backup file.
- You must restore to the same form of Logger (Software, Appliance, or VMware.)
- For Appliance Loggers, the Logger Appliance model must be the same as the one used to create the backup file.
- For Software Loggers and Loggers on VMware, the operating system that Logger is running must be the same as the one used to create the backup file.
- Since the current license will be over-written by the backup, retain a copy of the existing license to re-apply after the Restore is complete, if appropriate.

To restore from a configuration backup:

1. Open the **Configuration | Advanced** menu and then click **Configuration Backup**.
2. Click **Restore**.

The **Upload Configuration Backup** option displays on the Configuration Backup page. You will see a message that after restoring the configuration, Logger will need to be restarted.

3. Click **Browse** to locate the backup file.
4. Click **Submit** to start the restore process.
5. When the restore process is complete, you will be prompted to reboot your Logger:
 - a. Logger Appliance—When the restore process is complete, you will be redirected to the **System Admin > System > System Reboot** page. Select Reboot and click **Reboot**. See ["System Reboot" on page 458](#).
 - b. Software Logger—When the restore process is complete, you will be prompted to reboot your system. See ["Software Logger Command Line Options" on page 520](#).

Tip: You may need to upload a new license or re-apply a copy of the license in place before the backup.

Content Management

Depending on their rights, users can export Alerts, Dashboards, Fieldsets, Filters, Parsers, Saved Searches, and Source Types from a Logger to a file, and then import that content onto another Logger or re-import it onto that same Logger, as a backup. For information on the user rights necessary to import or export a particular type of content, instructions, and guidelines for importing and exporting Logger content, see ["User Rights for Exporting Content" on the next page](#) and ["User Rights for Importing Content" below](#).

Content import and export is useful in these situations:

- When you want to make a backup of Logger content. If your Logger becomes unavailable or is reset to its factory defaults, you can quickly restore its content by importing the saved content.
- When multiple Loggers with the same content need to be installed in your network, you need to configure only one Logger. Subsequent Loggers can be deployed by importing the first Logger's content on them, thus reducing deployment time.
- When you want to add content from one Logger to the content on another.

The **Export** function saves the content from a Logger to a storage location on your network or to the local disk of the computer from which you connect to the Logger. When you need to use that content for any of the situations described previously, simply import the saved content.

User Rights for Importing Content

The content you are able to import depends on your user rights. If you have any of the following rights, the **Import Content** dialog box is available:

- Logger Rights > **Filters**: Edit, save, and remove shared filters.
- Logger Rights > **Forwarders and Alerts**: Edit, save, and remove forwarders and alerts.

Note: While this Logger right enables you to edit, save, and remove both forwarders and alerts, you can only import alerts, but not forwarders.

- Logger Rights > **Dashboards**: Edit, save, and remove dashboards.

If the user has the dashboard save right but does not have the saved search save right, then the dashboards using search results panels will not be imported (A warning message will indicate which dashboards are skipped).

- Logger Rights > **Saved Search**: Edit, save, and remove saved search.
- **System Admin**: For parsers and source types, the user can be assigned to any System Admin group. If the user is not an admin, then Parsers and Source Types are not importable.

See ["Users/Groups" on page 495](#) for more information on Logger user rights and how to administer them.

Even if you see the **Import** page, you may not be able to import all of the content types. If you do not have the associated user rights, then you cannot import that type of content, and will get a warning message instead.

Importing Content

Make sure you are familiar with these guidelines before importing Logger content:

- If an object with the same name exists on the importing system, the object being imported is named **<ObjectName> [import]**. For example, an imported alert is named **AlertName [import]** and an imported filter is named **FilterName [import]**.

If an object with the name **<ObjectName> [import]** already exists on the importing Logger (from a previous import procedure), the object being imported is named **<ObjectName> [import]** **[import]**.

- Be sure to set the alert destinations (SNMP, Syslog, ESM Destination, and SMTP servers) for alerts you import, because this information is not included in the exported content.
- Content Export and Import assumes that the importing Logger has the same configuration setup as the exporting Logger. The Logger your are importing your content to must have the same configuration setup, such as devices, device groups, storage groups as the exporting Logger. If it does not imported content that relies on that configuration cannot be used.

To import content from another Logger:

1. Open the **Configuration | Advanced** menu and then click **Import Content**.
2. Click **Browse** to locate the file

The file must reside on a local or remote drive accessible to the system whose browser you are using to access Logger's user interface.

3. Click **Import**.

User Rights for Exporting Content

The content you are able to export depends on your user rights. If you have any of the following rights, the **Export** page discussed in ["Exporting Content" on the next page](#) is available:

- Logger Rights > **Filters:** Use and view shared filters.
- Logger Rights > **Forwarders and Alerts:** View forwarders and alerts.

Note: While this Logger right enables you to view both forwarders and alerts, you can only export alerts, but not forwarders.

- Logger Rights > **Dashboards:** Use and view dashboards.

If the user has the dashboard read right but does not have the saved search read right, then dashboards having search results panels are not available for selection from the Content to Export dialog box.

- **Logger Rights > Fieldsets:** View fieldsets.
- **Logger Rights > Saved Search:** View saved search.
- **System Admin:** For parsers and source types, the user can be assigned to any System Admin Group. If the user is not an admin, then Parsers and Source Types are not exportable.

See ["Users/Groups" on page 495](#) for more information on Logger user rights and how to administer them.

Even if you see the **Export** page, you may not be able to export all of the content types. If you do not have one of the above user rights, then the corresponding content type is not available in the **Content to Export** dialog box.

Exporting Content

Make sure you are familiar with these guidelines before exporting Logger content:

- The exported content is in XML format in a gzip file. For example, **allfilters.xml.gz**.
- The folder on the remote file system to which you are exporting Logger content needs to exist before you can export content to it.
- When exporting alerts, the query associated with the alert, match count, threshold, and status are included in the export. The export does not include e-mail, SNMP, ESM Destination information, or syslog destination information. Since alert destination (SNMP, Syslog, ESM Destination, and SMTP servers) information is not exported, you will need to set this information for alerts you import.
- When exporting dashboards, the content of any saved searches used in the exported dashboards is also exported.
- When exporting source types, the content of the parsers used in the exported source types is also exported.

To export Logger content:


1. Open the **Configuration | Advanced** menu and then click **Export Content**.
2. Select the radio button for the type of content that you want to export. The available objects menu changes with the type of content you select.
3. Select the objects to export from the menu.
To select one object, click its name. To select multiple objects, hold the Ctrl key down and click the names.
4. For Software Loggers, click **Export**. The content will be saved according to your browser settings. If you are using a Logger Appliance, continue to the next step.
5. For Appliance Loggers, choose where to save the exported content. **Save to local disk** is the default

option.

To save on the local disk of the computer from which you connect to the Logger, leave **Save to local disk** checked.

To export to a remote location:

- a. Uncheck **Save to local disk** to display options for exporting to a remote file system.



Save to local disk ☐

Export to remote file system

Mount Location SL_NFS1

Remote file path and name //168.124.10.160/loggerexport

Specify file path without extension

Overwrite if file exists ☒

Export

- b. Select the location to which you want to export the content in the **Mount Location** field. If the location you want is not in the drop-down list, you need to add it. For information about adding a network storage location, see ["Storage" on page 475](#).
- c. In the **Remote file path and name** field, enter the folder location in which the exported contents file will be created at the Mount Location you specified in the previous step. The folder location you specify in this step must already exist on the Mount Location. It is not created by the Logger.

Note: Specify the filename without using an extension.

6. Click **Overwrite if file exists** if you want to overwrite a file with the same name as the exported contents file in the folder location that you specified in the previous step.
7. Click **Export**.

How does EPS license differ from GB per day license?

EPS is a license that unlike the GB Standalone or managed by ArcMC (also known as SODP license), it allows the user to count all the events in EPS per day. Additionally, the license does not establish any restriction when exceeding the limit of violations per day.

Note: Once license is updated to EPS, GB Logger Standalone or managed by ArcMC license cannot be longer selected. This also applies during EPS trial version.

| Characteristics | GB | EPS |
|-------------------------|---|--|
| Trial version | Not available from ArcSight. | Available as default option in version 7.0 |
| Over limit restrictions | After 5 violations over the last 30 days. | No Logger enforcement. |
| License Usage Page | It shows the date and GB/day | It shows date, events received, MMEPS, and license capacity |
| Chart limit description | Blue: under the limit Yellow: warning Red: over the limit | Green: under the limit Yellow: warning Red: over the limit |
| Days displayed | 30 days | 45 days |
| Banner | Existent | Not existent |
| Report | Not available | Available in PDF format only |

Standalone License Information

This topic applies to standalone ArcSight Loggers, newly upgraded Loggers, and Trial Loggers.

Information regarding all licenses is available at **Configuration> License Information**. Based on the license supported, tables and columns display different information. The license screen shows information about the type of model, daily data or EPS as well as their correspondent limits.


GB licenses are continued to be supported with no significant changes in behavior. However, Logger recommends the user to transition to EPS license before GB Standalone is not longer supported. For more information, contact your sales representative.

Logger Standalone EPS License

EPS license does have a maximum limit of violations; however it does not issue a warning banner of X violations over Y days. The customer is considered to be in compliance with the license agreement as long as the MMEPS value indicators remain at the limit or below the purchased licensed capacity. If 3 or more consecutive MMEPS value indicators exceed their capacity based on the purchased license, they are considered to be out of compliance.

Graphic and table under **Configuration> License Usage** display the last 45 days of usage. The graphic shows the label number of violations, maximum EPS permitted per day, and the number of violations that Logger has in 45 days. You can download the last 45 days license report in PDF format. Export button is available in the **License Usage** page.


Note: Export in PDF functionality is not currently supported in IE browser.



1. **First 45 days:** Since it is only possible to calculate an approximate of MMEPS, the data is viewed in gray. During this period, no violations will be considered.






2. **After 45 days:** The graphic displays a different color based on license violation status.

- Green: Data is within the limit.
- Yellow: Data limit has been reached.
- Red: Data is over the limit.



Keystones:

1. **Events per Day (EPD):** is the total number of events generated in a 24 hour clock period. The clock is calculated based on UTC time starting at 00:00:00 and ending at 23:59:59, regardless of the local times used.
2. **Sustained EPS (SEPS):** is the event “constant” per second supported by the system within the 24 hour clock period. It stabilizes peaks and valleys and gives a better indication of use.
3. **Moving Median EPS (MMEPS):** is the license usage. It uses the 45 day period SEPS data shifting the calculation window 1 day every 24 hours after the first 45 days. The clock is calculated based on UTC time starting at 00:00:00 and ending at 23:59:59, regardless of the local times used.
4. **License Limit:** corresponds to the amount of EPS acquired in the license.

| Date | Events Received | License Usage (MMEPS) | License Capacity |
|----------|-----------------|---|------------------|
| 11/7/19 | 53,691,319 |  558 | 579 |
| 11/8/19 | 53,691,319 |  606 | 579 |
| 11/9/19 | 53,691,319 |  621 | 579 |
| 11/10/19 | 30 |  621 | 579 |
| 11/11/19 | 5,000 |  621 | 579 |

Calculating keystones:

- **To calculate SEPS:** divide EPD by 60 (seconds) by 60 (minutes) by 24 (hours).
- **To calculate MMEPS:** Calculate SEPS median average for the window period (current day – 1).

Note: MMEPS is calculated using a 45 day window. Kindly note an approximate value is retrieved before this period.

- Before 45 days: Calculate the median SEPS for the time period. If this period contains an odd number of SEPS, select the median value from the sorted array. If it contains an even number, compute an average from the 2 median values. If required, round value to the approximate integer.
- After 45 days: Select the median SEPS value from the window period line up.

Logger Standalone GB per day License

On GB standalone Logger, the License Usage page (**Configuration | Advanced > License Usage**) displays the daily ingested data volume, the licensed GB per day, and the number of license violations that have occurred using the size of raw events received by Logger. There is a limit of five data volume license violations in a 30 day period. Logger displays a "Licensed Data Volume Limit Exceeded" warning banner when your incoming data volume is greater than this limit.

In the data volume chart, a vertical line indicates your licensed daily data volume, a blue bar indicates you are below 90% of your license limit for that day, a yellow bar indicates that you have reached 90% of your license limit for that day, and a red bar indicates that you have exceeded your license limit for that day. Below the chart, the number of violations, maximum allowed violations, and licensed GB per day are listed and the table displays the data ingested for each of the past 30 days.

Caution: If the data-limit has been exceeded six times in 30 days, you cannot use any search-related features until the listed 30 days have five or fewer violations. The disabled search-related features include forwarders as well as all searching and reporting functionality.

You can view your license usage limit and other license information on Logger under **Configuration > License Usage**.

The data volume restriction function measures the daily data for the previous 24 hours at 00:00:00 UTC and posts that information on the license usage page. The time this functions uses is independent of the Logger's local time. The License Usage page (**Configuration | Advanced > License Usage**) shows the amount of data stored on your Software Logger for each of the last 30 days.

Caution: The disabled search features include forwarders as well as all searching and reporting functionality.

Managed by ArcMC License Information

This topic applies to SODP Logger licensed only.

Refer to [ArcSight Management Center Admin Guide](#) for further information on Licenses managed by ArcMC.

GB managed by ArcMC License Usage

There are no license usage restrictions in GB Software License managed by ArcMC as license usage information is calculated by the connectors managed by ArcMC. In the **License Usage** chart, a blue bar indicates that the Logger was managed by ArcSight Management Center for that day and an orange bar indicates the Logger was non managed for that day.


In **Configuration > Advanced > License Usage**, thanks to the tracking information in the agent.log , the user can view the daily ingested license usage and the management status of the Logger. Below the chart you can see the number of days non managed, maximum allowed non managed days, and last managed days as well as a table containing the data ingested for each during the last 30 days.

For more information regarding GB license managed by ArcMC, see [ArcSight Management Center Administrator's Guide](#) .

EPS managed by ArcMC License Usage

Just like GB License, EPS can be managed by ArcMC. This option is set as default in the Logger. To disable this functionality, uncheck the box located at: **System Admin > Options**.

In the **License Usage** page, the graphic does not display the license violation status. Only first 45 days (gray) and after 45 days (green) are displayed in the chart.



Note: Despite the ArcMC management option is enabled in the page, Logger will behave as Standalone license if no ArcMC information is added to the Logger.

For more information on EPS managed by ArcMC, see [ArcSight Management Center Administrator's Guide](#).

Trial Licenses

ArcSight Logger come with a trial license that you can use for a 90 day evaluation period. After the evaluation period is over, only **System Admin** page will be available to insert a valid license. To upload a new license, open **System Admin** in the menu bar, and then click **License & Update** in the **System** section. For instructions, see ["Updating Your Logger License" on page 466](#).

The trial license gives you access to the following:

- All Logger features except Reporting.
- 20 EPS per day ingested license usage.
- Up to 24 TB Storage Volume. (For upgraded systems, the license will display up to 24 TB or the appliance capacity, (whichever is lower).

Trial license is available both for EPS and GB per day licenses. You can manage both licenses both by ArcMC or as Standalone ArcSight Logger. After you upload either license, the Reporting feature is enabled, and the licensed daily license usage and storage volume are increased to the capacity of the license.

Note: EPS will appear as the default license during trial. However, you can transition to GB if required. To increase the data limit, follow the instructions in ["License & Update" on page 466](#).

Logger Software Installations and Licenses

In an effort to distant from GB / day based license, you can opt for a new license model named EPS. This license will count the events per second instead of GB/day and EPS. This license will be available in trial

version. For more information, see ["How does EPS license differ from GB per day license?" on page 444](#)

Guidelines for Software Installations and licenses

- On Fresh Install, Both GB and EPS can be selected as license options.
- When upgrading from Logger 6.7x to 7.0, both GB and EPS appear as license options. If the user selects EPS license, Logger cannot longer display GB data afterwards. Only EPS data is displayed under **License Usage** page.
- If a license is inserted, make sure to restart your Logger after the license update.

Peer Nodes

Logger can establish peer relationships with one or more Loggers or ArcSight Managers to enable distributed searches. To search other Loggers or Managers, you must define one or more peers.

When two systems peer with each other, one initiates the relationship. The initiator sends credentials to authenticate itself to the target system. If the authentication succeeds, a peer relationship is established between the two systems.

Overview Steps for Configuring Peers

The following steps are required to set up peer relationships:

1. Determine which Manager or Logger will initiate the peer relationship. Manager or Logger A is the initiator in this example, and Logger B is the target.
2. Decide on a peer authentication method, based on the information in ["Selecting a Peer Authentication Method" on page 452](#).
 - To authenticate with a user name and password:
Determine which user name and password Manager or Logger A should use to authenticate itself when peering with B, or set up a user, as described in ["Users/Groups" on page 495](#).
 - To authenticate with an Authorization ID and Code:
On Manager or Logger B, generate an Authorization ID and Code for A to use to authenticate itself when peering with B. For instructions, see ["Authorizing a Peer" on page 452](#).
3. On Manager or Logger A, add the authentication information from B, as described in ["Adding a Peer" on page 453](#).
 - If authenticating with a user name and password, use the user name and password that you determined.
 - If authenticating with an Authorization ID and Code, use the Authorization ID and Code that you generated.

Guidelines for Configuring Peers

Consider these guidelines when configuring peers:

- Logger 7.0 can peer with ESM 6.11, 6.9, 6.8c, 6.5c, and Logger 5.3 and above.
- A maximum of 100 peers can be configured for a Logger.
- The system time and date on each Manager or Logger must be set correctly for its time zone. Micro Focus recommends that you configure your system to synchronize its time with an NTP server regularly.
- If the remote Logger is configured for SSL Client authentication (SSL/CAC Authentication), you must configure an authorization ID and code on the initiator Logger.
- There are no special authentication requirements for FIPS-enabled Loggers. Such Loggers can use any of the allowed authentication methods.
- Peers cannot be edited, however you can delete and re-add a peer.
- If you are running distributed searches (searches across peers), follow these additional guidelines:
 - a. A user must belong to the Logger Search User Group with “Search for events on remote peers” privilege set to **Yes** and the Logger Rights Group with “View registered peers” privilege set to **Yes**. See ["Searching Peers \(Distributed Search\)" on page 115](#).
 - b. Users performing search operations on peers have the same privileges on the peer that they have on the Logger they are logged into. For example, User A is restricted by a search group filter to only search for events in which deviceVendor is set to “Cisco.” When User A performs a search operation across Logger A's peers, the same constraint (to search events where deviceVendor = “Cisco”) is applied on all peers.
- If you are running distributed reports (reports across peers), see ["Selecting Groups, Devices, and Peers" on page 190](#).
- Peer relationships are not being affected when username and password used for remote peer authentication change after establishing the peer relationship. However, if the peer relationship is deleted or broken, you will need to provide the changed credentials to re-establish the relationship.
- You cannot reestablish a peer relationship with an improper tear-down. For example, deleting the peering relationship on one Logger while the other is unavailable (powered down). Make sure to delete the existing peer information from the peer Loggers before re-initiating the relationship.

Authenticating Peers

Authentication happens only once, at the time the peer relationship is created. The authorization to use peer services is implicit each time a remote system receives peer requests from a system that previously authenticated as a peer.

You can authenticate a peer in one of two ways:

- **Peer Authorization ID and Code:** These credentials are generated on one Manager or Logger and used on another to configure peering between the two. When generating the Authorization ID and Code, enter the IP address of the Manager or Logger you will use to initiate peering in the Peer Authorization page of the one you want to peer with. The IP address is used to generate a unique ID and code that can be used only for peering from that address. Therefore, this method is more secure than using a user name and password.

Note: Micro Focus ArcSight recommends using Peer Authorization ID and Code for authentication.

- **User name and password:** A user name and password already configured on the target system is used for authentication.

Selecting a Peer Authentication Method

- When using a user name and password to configure peering, you must use the user password for local authentication, even if your system is configured to use LDAP or RADIUS authentication.
- If the peer Manager or Logger is configured for SSL Client authentication (CAC), you must configure an Authorization ID and Code on the target Manager or Logger. You cannot use a user name and password.
- FIPS-enabled systems are not limited to a specific authentication method.

Authorizing a Peer

Use the following procedure to generate the Authorization ID and Code on the target Manager or Logger with which you want to establish a peer relationship. (Manager or Logger B in the example in ["Peer Nodes" on page 450](#).) After that, use the ID and Code on the initiating Manager or Logger when configuring the peer relationship (Manager Logger A in that example).

To generate the Authorization ID and Code to use when configuring a peer relationship:

1. Open the **Configuration | Advanced** menu and click **Peer Authorizations**.
2. Click **Add**.
3. Enter the hostname or IP address and port for the Manager or Logger you want to peer with this system.
4. Click **Save**.
The authorization ID and authorization code display. Copy this information and use it on the other Manager or Logger when adding this system as a peer.
5. Click **Done** to return to the Peer Authorization list.

Adding and Deleting Peer Relationships

The **Peer Nodes** page displays the current peer relationships. From here, you can add and delete peers.

Adding a Peer

Adding a peer creates a peer relationship between two Loggers, two ArcSight Managers, or a Logger and a Manager. Once added, you can delete a peer, but you cannot edit it. See ["Guidelines for Configuring Peers" on page 451](#) for more information.

Adding a peer on a Logger is a bi-directional process. That is, when Logger A adds peer access for Logger B, Logger B automatically adds peer access for Logger A. Similarly, if you delete the peer access for B on A, the peer access for A is automatically deleted on B.

To add a peer:

1. Open the **Configuration | Advanced** menu and click **Peer Nodes**.

Add Peer Node

Peer Hostname/IP

Peer Port

☒ Peer Login Credentials

☐ Peer Authorization Credentials

Peer User Name

Peer Password

In most cases, the fields below will be pre-populated for you, and you do not need to change them. fields, please consult the Logger Administrator's Guide for specific instructions.

Local Hostname/IP

Local Port

Save

Cancel

- Click **Add** and enter the following parameters.


| Parameter | Description |
|--|---|
| Peer Hostname/IP | Enter the target Manager or Logger's hostname or IP address. |
| Peer Port | Use the port configured when installing or initially configuring the target system. See "Guidelines for Configuring Peers" on page 451 . By default, this is Port 443 for the Logger Appliances. |
| Peer Login Credentials | Select Peer Login Credentials for password-based authentication. |
| Peer Authorization Credentials | OR Select Peer Authorization Credentials to use an Authorization ID and Code. <ul style="list-style-type: none"> On systems using local or RADIUS authentication, you can use either authentication method, although peer Authorization ID and Code are recommended. On systems using SSL Client Authentication (CAC), Authorization ID and Code is the only way to authenticate a peer. You cannot use a user name and password. (See "SSL Client Authentication" on page 488.) FIPS-enabled systems are not limited to a specific authentication method. |
| If you selected Peer Login Credentials... | |
| Peer User Name | Enter a user name already configured on the target system. |
| Peer Password | Enter the password for the user specified in the Peer User Name field. |
| If you selected Peer Authorization Credentials... | |
| Peer Authorization ID | Enter the authorization ID generated on the target Manager or Logger. (See "To generate the Authorization ID and Code to use when configuring a peer relationship" on page 452 for more information.) |
| Peer Authorization Code | Enter the authorization code generated on the target Manager or Logger. (See "To generate the Authorization ID and Code to use when configuring a peer relationship" on page 452 for more information.) |
| Other Fields These fields need to be updated in rare circumstances. | |
| Local Hostname/IP | In most cases, the value in this field matches the IP address or host name you use to connect to this Logger from your browser, and you do not need to do anything. However, if the IP address does not match (for example, when the Logger is behind a VPN concentrator), change the value to match the IP address or host name with which you connect to this Logger. |
| Local Port | In most cases, the value in this field matches the port in your browser when you logged into this system (the initiating Manager or Logger), and you do not need to do anything. However, if the port here does not match the port in the IP address, (for example, when the Manager or Logger is behind a VPN concentrator), change the value to match the port in the IP address in your browser. |

- Click **Save** to add the new Logger, or **Cancel** to quit.

Deleting a Peer

Deleting a peer removes the peer relationship between two Loggers or two ArcSight Managers, or a Manager and a Logger. You can perform this process from either peer.

To delete a peer:

1. Open the **Configuration | Advanced** menu and click **Peer Nodes**.
2. Locate the peer you want to delete the peer relationship to and click the Delete icon () on that row.
3. Confirm the deletion by clicking **OK**, or click **Cancel** to retain the Peer.

Chapter 6: System Admin

System Administration tools enable you to create and manage users and user groups, and to configure security settings, SMTP, and other system settings.

Note: Some System Administration topics apply to Software Loggers, some to Logger appliances, and some to both types of Logger. The type of Logger to which the topic applies is noted at the top of each System Administration topic.

The following subjects are covered in this section:

| | |
|-------------------------------------|-----|
| • System | 457 |
| • System Locale | 457 |
| • System Reboot | 458 |
| • Network | 458 |
| • SMTP | 465 |
| • License & Update | 466 |
| • Process Status | 469 |
| • System Settings | 469 |
| • SNMP | 470 |
| • SSH Access to the Appliance | 473 |
| • Logs | 474 |
| • Audit Logs | 474 |
| • Audit Forwarding | 475 |
| • Storage | 475 |
| • Remote File Systems | 475 |
| • SAN | 478 |
| • RAID Controller | 483 |
| • Security | 483 |
| • SSL Server Certificate | 484 |
| • SSL Client Authentication | 488 |
| • FIPS 140-2 | 491 |
| • Users/Groups | 495 |
| • Authentication | 495 |
| • Login Banner | 506 |
| • User Management | 506 |
| • Change My Password | 513 |

| | |
|--|-----|
| • Other System Administration Information | 514 |
| • Monitoring System Health | 514 |
| • System Health Events | 515 |
| • Using the Appliance Command Line Interface | 517 |
| • Software Logger Command Line Options | 520 |
| • Firewall Rules | 522 |
| • Configuring the Firewall on Logger Appliance | 522 |

System

From the **System** tab, you can configure system-specific settings.

| | |
|-------------------------------------|-----|
| • System Locale | 457 |
| • System Reboot | 458 |
| • Network | 458 |
| • SMTP | 465 |
| • License & Update | 466 |
| • Process Status | 469 |
| • System Settings | 469 |
| • SNMP | 470 |
| • SSH Access to the Appliance | 473 |

System Locale

This topic applies to both Software Logger and the Logger Appliance.

The System Locale setting ensures that the user interface displays information such as date, time, numbers, and messages in the format and language appropriate for the selected country.

The System Locale is configured during the Logger installation process. Once configured it cannot be changed.

To view the System Locale:

1. Click **System Admin** from the top-level menu bar.
2. Click **System Locale** in the **System** section. The **System Locale Setting** dialog box displays the Locale.

System Reboot

This topic applies to Logger Appliances only.

You can reboot or shutdown your appliance. For related information for Software Logger, see ["Software Logger Command Line Options" on page 520](#)

To reboot or shutdown your system:

1. Click **System Admin** from the top-level menu bar.
2. Click **System Reboot** in the **System** section.
3. Select from the following options:

| Button | Description |
|---------------------|---|
| Reboot | Your system reboots in about 60 seconds. The reboot process normally takes 5-10 minutes, during which time the system is unavailable. |
| Reboot in 5 Minutes | Your system reboots after a 5-minute delay. The reboot process normally takes 5-10 minutes, during which time the system is unavailable. |
| Shutdown | Automatically shuts down (powers off) the system. |

Each of the above actions can be canceled. "Reboot" and "Shutdown" allow for cancellation within **60 seconds**. "Reboot in 5 Minutes" can be canceled within **300 seconds**.

4. Click **Reboot**, **Reboot in 5 Minutes**, or **Shutdown** to execute the chosen action.

Caution: During reboot, Logger is not able to receive events. Events may be lost while Logger reboots, unless SmartConnectors are used. SmartConnectors cache events when destinations like Logger are temporarily unavailable.

Network

This topic applies to Logger Appliances only.

On the Logger Appliance, you can configure the DNS, Hosts, NICs, static routes, and system time settings from the **Network** menu. For Software Loggers, these are configured through the operating system.

- [System DNS](#)459
- [Hosts](#) 459
- [NICs](#)460
- [Static Routes](#)461
- [Time/NTP](#)462

System DNS



This topic applies to Logger Appliances only.

The **System DNS** tab enables you to edit the DNS settings and to add DNS search domains.

Note: DNS must be properly configured before using a Kafka Service.

To change DNS settings:

1. Click **System Admin** from the top-level menu bar.
2. Click **Network** in the **System** section.
3. In the **System DNS** tab, enter new values for the IP address of the primary and secondary DNS servers, or edit the list of search domains.

To add a new domain, click the  icon. To remove a domain, click the  icon. To change the search order of domains, select a domain name, and click the up or down arrow until the domain is in the desired position.

4. Click **Save**.
5. Click **Restart Network Service** to put the changes into effect.

Hosts

This topic applies to Logger Appliances only.

The **Hosts** tab enables direct editing of your system's `/etc/hosts` file. You can enter data in the **System Hosts** text box or import it from a local file.

To change the Hosts information:

1. Click **System Admin** from the top-level menu bar.
2. Click **Network** in the **System** section, and then click the **Hosts** tab.
3. In the **System Hosts** text box, enter hosts information (one host per line) in this format:

<IP Address> <hostname1> <hostname2> <hostname3>

To import information from a file, click **Import from Local File**, and locate the text file on the computer from which you are accessing your system.

4. Click **Save**.

NICs

This topic applies to Logger Appliances only.

The **NICs** tab enables you to set the IP addresses for the network interface cards (NICs) on your system. Additionally, you can configure the hostname and default gateway for your system.

To set or change the NICs settings:

1. Click **System Admin** from the top-level menu bar.
2. Click **Network** in the **System** section.
3. In the **NICs** tab, enter the following settings. To edit the IP address, subnet mask, or speed/duplex of an NIC, select the NIC and click **Edit** above the NIC Name list.

| Setting | Description |
|---|---|
| Default Gateway | The IP address of the default gateway. |
| Hostname | <p>The network host name for this system. Make sure that your DNS can resolve the host name you specify to your system's IP address. Performance is significantly affected if DNS cannot resolve the host name.</p> <p>This name must be identical to the domain specified in the Certificate Signing Request, described in "Generating a Certificate Signing Request (CSR)" on page 486.</p> <p>Note: If you previously used a self-signed or CA-signed certificate on this system and are now changing its host name, you must regenerate a new self-signed certificate or CSR. A new certificate ensures that the connectors in FIPS mode which communicate with your system are able to validate the host name. For more information about generating a CSR, see "Generating a Certificate Signing Request (CSR)" on page 486.</p> |
| Automatically route outbound packets (interface homing) | <p>When this option is enabled (checked box), the response packets are sent back on the same system interface on which the request packets had arrived. Enabling this option can improve performance as the routing decisions do not need to be made (using the default gateway information and static routes) to send packets out from your system. If you have static routes configured, they are ignored when this feature is enabled.</p> <p>When this feature is disabled (unchecked box), the static routes (if configured) are used to determine the interface through which the response packets should leave your system.</p> <p>If you configure only one network interface, this setting does not provide any additional benefit.</p> |

| Setting | Description |
|--------------|---|
| IP Address | <p>The IP address for each network interface card (NICs) in your system. These IP addresses should be on separate subnets to avoid confusion and to allow load balancing between receivers and forwarders.</p> <p>Add NIC Alias</p> <p>You can create an alias for any listed NIC. To do so:</p> <ol style="list-style-type: none"> Highlight the NIC for which you want to create an alias. Click Add. Create an alternative IP address for the alias. Click Save. <p>You can identify the alias from its original by an appended colon alongside a digit indicating the number of aliases you have created on a particular NIC.</p> <div> <p>Note: You cannot alter the speed of an IP alias.</p> <p>You can create as many aliases as you choose.</p> </div> |
| Subnet Mask | The subnet mask associated with the IP address you entered for an NIC. |
| Speed/Duplex | <p>Choose a speed and duplex mode, or let your system determine the network speed automatically:</p> <ul style="list-style-type: none"> • Auto (recommended) • 10 Mbps - Half Duplex • 10 Mbps - Full Duplex • 100 Mbps - Half Duplex • 100 Mbps - Full Duplex • 1 Gbps - Full Duplex |

- Click **Save**.
- Click **Restart Network Service** to put the changes into effect.

Static Routes

This topic applies to Logger Appliances only.

You can specify static routes for the NICs on your system.

To add, edit, or delete a static route:

- Click **System Admin** from the top-level menu bar.
- Click **Network** in the **System** section.
- In the **Static Routes** tab:

- To add a new static route, click **Add**.
- To edit or delete an existing route, select the route first, then click **Edit** or **Delete**.

When adding or editing a static route, you need to configure these settings.

| Setting | Description |
|-------------|---|
| Type | Whether the static route is to a Network or a Host |
| Destination | The IP address for the static route destination |
| Subnet Mask | The subnet mask if you specify a network as the destination |
| Gateway | The IP address of the gateway for the route |

4. Click **Save**.

Time/NTP

This topic applies to Logger Appliances only.

You do not need to configure the time, date, or time zone for a Software Logger. Software Loggers use the operating system's settings for the time and time zone.

The **Time/NTP** tab enables you to configure system time, date, local timezone, and NTP servers. Micro Focus strongly recommends using an NTP server instead of manually configuring the time and date on your system.

Precise timestamping of events is also critical for accurate and reliable log management. The times displayed for Logger operations such as searches, reports, and scheduled jobs are in the Logger's local time zone.

To set or change the system time, date, or time zone manually:

1. Click **System Admin** from the top-level menu bar.
2. Click **Network** in the **System** section.
3. In the **Time/NTP** tab, configure these settings.



| Setting | Description |
|-------------------|--|
| Current Time Zone | <p>The time zones appropriate to your system's location. To change this setting, click Change Time Zone...</p> <p>Local times zones follow the Daylight Savings Time (DST) rules for that area. Greenwich Mean Time (GMT)+ and - time zones are DST-agnostic.</p> <p>For example, the America/Los Angeles time zone varies by an hour compared with GMT when DST goes into and out of effect.</p> <ul style="list-style-type: none">• Pacific Standard Time (PST) = GMT-8• Pacific Daylight Time (PDT) = GMT-7 |
| Current Time | <p>The current date and time at the system's location. To change this setting, click Change Date/Time...</p> |

4. The Time Zone change requires that you reboot the appliance. However, the Current Time change takes effect immediately.

Caution: If you manually set the date and time settings and are also using an NTP service, the date and time entered manually cannot be more than 16 minutes ahead of or behind the time that the NTP server is providing. If the manually entered time is more than 16 minutes different from the NTP server time, then the NTP service will fail to start.

To configure your system as an NTP server or for using an NTP server for your system:

1. Click **System Admin** from the top-level menu bar.
2. Click **Network** in the **System** section.
3. Click the **Time/NTP** tab.
4. Under **NTP Servers**, configure these settings.

To add a new NTP server, click the  icon. To remove a server, click the  icon. To change the order in which the NTP servers should be used, select a server and click the up or down arrow until the NTP server is in the desired position.

| Setting | Description |
|-------------------------|--|
| Enable as an NTP server | Check this setting if this system should be used as an NTP server. |
| NTP Servers | <p>Enter the host name of an NTP server. For example, time.nist.gov.</p> <p>Micro Focus recommends using at least two NTP servers to ensure precise time on your system. To enter multiple NTP servers, type one server name per line.</p> <p>Once you add servers to this list, you can click the “Click to Test” link to verify if the servers that you added are reachable from your system.</p> <ul style="list-style-type: none">• An ArcSight system can serve as an NTP server for any other ArcSight system.• If System A serves as an NTP server for System B, System B needs to list System A in its NTP Servers list.• Use the Test Servers button to verify the status of the servers entered into the NTP Servers box. |

5. Click **Save**.

Tip: You may need to scroll down to view the **Save** button and **Restart NTP Service**.

6. Click **Restart NTP Service** to put the changes into effect.

Impact of Daylight Savings Time Change on Logger Operations

This topic applies to both Software Logger and the Logger Appliance.

To search for events that occur between 1 a.m. to 2 a.m. when the time change due to the end of Daylight Savings Time (DST) takes place in the fall, (time is set back one hour), specify a start time of 12:59:59 or earlier and end time of 2:00:01 or later to ensure that all events are returned.

To search for events that occur between 1 a.m. to 2 a.m. when the time change due to the start of Daylight Savings Time (DST) takes place in the spring (time is set ahead one hour), specify an end time of 2:00:01 or later to ensure that all events are returned.

Scheduled operations on Logger such as reports, event archives, and file transfers are also impacted when system time is adjusted on the Logger at the start and end of the US Daylight Savings Time period (DST).

Operations scheduled for the hour lost at the start of DST (for example, on March 9, 2015) are not run on the day of time adjustment. Similarly, operations scheduled for the hour gained at the end of the DST (for example, on November 2, 2015) are run at standard time instead of DST time.

Examples:

- A report scheduled to run at 1 a.m. DST on November 2, 2015 will run at 1 a.m. standard time, which is an hour later than the DST time on that day.
- A report scheduled to run at 2 a.m. on November 2, 2015 will run at 2 a.m.; however, due to time adjustment, an hour later than it ran on the previous day (November 1, 2015).
- A report scheduled to run at 2 a.m. on March 9, 2015 will not run.

SMTP

This topic applies to both Software Logger and the Logger Appliance.

Your system uses the Simple Mail Transfer Protocol (SMTP) and you can choose to set authentication and TLS to send email notifications such as alerts and password reset emails.

To add or change SMTP settings:

1. Click **System Admin** from the top-level menu bar.
2. Click **SMTP** in the **System** section and enter values for these settings.

| Setting | Description |
|---|---|
| Enable SMTP AUTH Mode (Checkbox) | It enables or disables the use of authentication and TLS. |
| Primary SMTP Server | The IP address or hostname of the SMTP server that will process outgoing email. |
| Primary SMTP Server Port | Port for Primary SMTP Server. This field is required if "Primary SMTP server" has some data. |
| Primary SMTP Server Certificate | This certificate is used for TLS connections. This field is required if "Enable SMTP AUTH Mode " is checked. |
| Username and Password for Primary SMTP Server | Credentials to connect to the primary SMTP Server. These fields are required if "Enable SMTP AUTH Mode " is checked. |
| Backup SMTP Server | The IP address or hostname of the SMTP server that will process outgoing email in case the primary SMTP server is unavailable. |
| Backup SMTP Server Port | Port for Backup SMTP Server. This field is required if "Backup SMTP server" has some data. |
| Backup SMTP Server Certificate | This certificate is used for TLS connections. This field is required if "Enable SMTP AUTH Mode " is checked and any of the fields in "backup SMTP server" is populated. |
| Username and Password for Backup SMTP Server | Credentials to connect to the backup SMTP Server. These fields are required if "Enable SMTP AUTH Mode " is checked and any of the fields in "backup SMTP server" is populated. |
| Outgoing Email Address | The email address that will appear in the "From" field of outbound email. |
| Cert Already Updated | Indicates that the certificate was previously uploaded. |
| Clear Backup SMTP Data | Clears the Backup information. |

3. Click **Save**.

License & Update

This topic applies to both Software Logger and the Logger Appliance.

This page displays license information, the version of the components, and the elapsed time since Logger was last rebooted (Logger Appliance) or restarted (Software Logger).

On this page, you can apply a new license to your Logger. You can also update a Logger Appliance from here. However, to upgrade Software Logger, you must install an upgrade package. Refer to the Release Notes for the upgrade version for instructions.

To view details of your current license, open **Configuration** from the top-level menu bar, and then click **License Information**. For details, see "[Standalone License Information](#)" on page 445.

Note: Make sure to restart Logger if you encounter any of the following scenarios:

- The license is inserted.
- The **License information** page shows no available data. This may occur a few days after performing an upgrade or fresh install.
- There is a license error while executing reports with peers searches. Additionally, the **License information** page displays no data.

Updating Your Logger License

To update your Logger license:

1. Redeem your license on the Software Entitlements Portal, then download the license file to a computer from which you can connect to Logger. For more information, refer to the software delivery confirmation email you received from Micro Focus.

Note: Even though users can now choose between EPS and GB per day licenses, EPS is the only license offered by ArcSight. For more information, see "[How does EPS license differ from GB per day license?](#)" on page 444

2. From the computer to which you downloaded the update file, log in to Logger using an account with administrator (upgrade) privileges.
3. Click **System Admin** from the top-level menu bar.
4. Click **License & Update** in the **System** section.
5. Browse to the license file you downloaded earlier, and click **Upload Update**. The Update in Progress page displays the update progress.

Once the update has been completed, the **Update Results** page displays the update result (success/failure). After applying a new license, you may need to increase your Storage Volume. See ["Storage Volume Size Increase" on page 428](#) for instructions.

Note: After upgrade or when converting a trial Logger to the full version, be sure to increase the Storage Volume to take advantage of your full licensed capacity.

Upgrading a Logger Appliance

To upgrade Logger appliance:

1. Download the update file from the Software Entitlements Portal, to a computer from which you can connect to Logger. For more information, refer to the software delivery confirmation email you received from Micro Focus.
2. From the computer to which you downloaded the update file, log in to Logger using an account with administrator (upgrade) privileges.
3. Click **System Admin** from the top-level menu bar.
4. Click **License & Update** in the **System** section.
5. Click **Browse** to locate the file.
6. Click **Upload Update**. The **Update in Progress** page displays the update progress.
7. Once the update has completed, the Update Results page displays the update result (success/failure) and whether the update requires a reboot or restart. If it does, the Logger reboots/restarts automatically.

Standalone Logger with an SODP License

This topic applies both to EPS and GB per Day license

About

Users can disable the **ArcSight Management Center License Management** option when they apply a Managed by License to a Logger that, eventually, will not be managed by ArcSight Management Center.

Procedure

1. **From Admin > Options** unselect the **ArcSight Management Center License Management** checkbox.

The default preference is set as true.

Options

System

EPS input rate bar gauge max100K

EPS output rate bar gauge max100K

Default start page for all usersSummary

Upload a logo (PNG file)

Browse...

Show default logo☒

ArcMc License Management☒

Personal

Default start page for adminUse default for all users

Save

•If **ArcSight Management Center License Management** is set as true and Logger is able to communicate with ArcSight Management Center, no changes are required.

•If **ArcSight Management Center License Management** is set as true and Logger is unable to communicate with ArcSight Management Center, a message is displayed on the third day, indicating that Logger must be managed by ArcSight Management Center.

•If **ArcSight Management Center License Management** is set as false, the behavior of the License Usage page and the License Information Page (labels) continue to operate the same as if Logger had a Standalone License Applied.

Process Status

This topic applies to both Software Logger and the Logger Appliance.

The **Process Status** page lists all processes related to your system and enables you to view the details of those processes and start, stop, or restart them.

Important: Micro Focus recommends that you do not stop the **servers** process.


- To shut down Software Loggers, use the **loggerd stop** or **quit** commands. For more information, see ["Software Logger Command Line Options" on page 520](#).
- To shut down Logger Appliances, perform a Shutdown from the UI. For more information, see ["System Reboot" on page 458](#).

Never stop the Logger **servers** process while events are still coming in, this can cause data loss. If you must stop the **servers** process, be sure to stop the **receivers** process first, then stop the **servers** process.

To view the Process Status page:

1. Click **System Admin** from the top-level menu bar.
2. In the **System** section, click **Process Status**. A list of Logger processes display.

Tip: In this context, the "processors" listed in the **Processes** table refers to forwarders.

3. On the **Process Status** dialog, to toggle the view of the details of a process, click the  icon to the left of the process name.

To start, stop, or restart a process, select the process and click **Start**, **Stop**, or **Restart** at the top of the process list.

System Settings

This topic applies to Software Loggers only.

If you did not select Logger to start as service during the installation process, you can do so using the **System Settings** page. When you select this option Logger will use a service called **arcsight_logger**, enabled to run at levels 2, 3, 4, and 5.

To configure Logger to start as a service:

1. Click **System Admin** from the top-level menu bar.
2. Click **System Settings** in the left panel.
3. From under **Service Settings**, choose the appropriate option:

- **Start as a Service**
- **Do not start as a Service**

4. Click **Save**.

SNMP

This topic applies to Logger Appliances only.

You can use SNMP (Simple Network Management Protocol) to monitor the health of your appliance. Logger appliance supports SNMP v2c and SNMP v3.

You can configure SNMP polling and notifications (traps):

- If you configure SNMP polling, a manager station can query the SNMP agent residing on Logger. The information retrieved provides detailed information at the hardware and Operating System level.
- If you configure an SNMP destination, Logger can send notifications for the events below. These notifications differ from the ones sent by Alerts. (For more information on using Alerts to send event information as SNMP notifications, see ["Real Time Alerts" on page 383](#) and ["SNMP Destinations" on page 392](#).) Instead of a notification being for a generic event, the new notifications are specific to a single event, making more easily understood by a Network Management System (NMS) such as Micro Focus NMMi.

SNMP Metrics Supported

Hardware

Logger supports polling and notifications for the following hardware parameters.

- CPU Usage
- Memory Usage
- Disk Almost Full
- Fan Failure
- Power Supply Failure
- Temperature Out of Range
- Ethernet Link Down

Logger application

The following notifications are defined in the **ARCSIGHT - EVENT - MIB**.

- Login attempt failed
- Password change attempt failed

- User account locked
- Reboot command launched
- Manual backup failed
- Scheduled backup failed
- Enable FIPS mode successful
- Disable FIPS mode successful
- Enable FIPS mode failed
- Disable FIPS mode failed

Configuration on the Logger Appliance

To configure SNMP polling:

1. In the main menu bar, click **System Admin**.
 2. In the navigation tree, under **System**, click **SNMP**. The SNMP Poll Configuration tab displays.
 3. **Status**: Select **Enabled** or **Disabled**.
 4. **Port**: Enter a port number. The default is **161** (UDP) but can be any available port.
 5. **SNMP Version**: Select **V2c** or **V3**. The default is V2c.
 - **V2c** — Enter the following value:
Community String: 6–128 alphanumeric, underscore (_), and dash (-) characters.
 - **V3** — Enter values for the following fields:
Username: 4–16 alphanumeric, lower-case characters. The user name must begin with an alphabetic character and may include underscores.
Authentication Protocol: Select **MD5** or **SHA**.
Authentication Passphrase: Enter a password consisting of 8–256 characters.
Privacy Protocol: Select **DES** or **AES128**.
Privacy Passphrase: Enter a password consisting of 8–256 characters.
- Note:** To be valid, the values for Poll Configuration and Trap Configuration must match.
6. **System Name**: Enter a name for the system you want to poll.
 7. **Point of Contact**: Enter a valid notification contact.
 8. **Location**: Enter a location for the system you want to poll.
 9. Click **Save**.
 10. Configure the firewall to open the SNMP port, see ["Firewall Rules" on page 522](#).
- If an SNMP destination is configured, Logger can send notifications for a limited set of events (see ["SNMP Metrics Supported" on the previous page](#)).

SNMP notifications differ from those sent by SmartConnectors, which are for a generic ArcSight event. The notifications listed here are specific to a single event, making them easier for understanding by a network management system like Micro Focus NMMi.

To configure the destination for SNMP notifications:

1. In the main menu bar, click **System Admin**.
2. In the navigation tree, under **System**, click **SNMP**. The SNMP Poll Configuration tab displays.
3. Select the **SNMP Destination** tab to open the SNMP Trap Configuration menu.
4. **Status**: Select **Enabled** or **Disabled**.
5. **NMS IP Address**: Enter the IP address of the Network Management System (NMS) host.
6. **Port**: Enter a port number. The default is **162** (UDP) but can be any available port.
7. **SNMP Version**: Select **V2c** or **V3**. The default is V2c.

- **V2c** — Enter the following value:

Community String: 6–128 alphanumeric, underscore (_), and dash (-) characters.

- **V3** — Enter values for the following fields:

Username: 4–16 alphanumeric, lower-case characters. The user name must begin with an alphabetic character and may include underscores.

Authentication Protocol: Select **MD5** or **SHA**.

Authentication Passphrase: Enter a password consisting of 8–256 characters.

Privacy Protocol: Select **DES** or **AES128**.

Privacy Passphrase: Enter a password consisting of 8–256 characters.

Note: To be valid, the values for Poll Configuration and Trap Configuration must match.

8. Click **Save**.

Configuration on the NMS

1. Download ArcSight MIB file and other standard Net-SNMP MIB files using following URLs:
 - https://<system_name_or_ip>/platform-service/ARCSIGHT-EVENT-MIB.txt
 - https://<system_name_or_ip>/platform-service/DISMAN-EVENT-MIB.txt
 - https://<system_name_or_ip>/platform-service/HOST-RESOURCES-MIB.txt
 - https://<system_name_or_ip>/platform-service/IF-MIB.txt
 - https://<system_name_or_ip>/platform-service/UCD-SNMP-MIB.txt
2. Load the MIB.
3. Configure the node (appliance) in the NMS (or MIB browser) according to the protocol used, either v2c or v3.

MIB Contents

The standard MIB files contain the following types of notifications:

| Module | Notification Types |
|--------------------|---|
| DISMAN-EVENT-MIB | Event triggers and actions for standard network management. |
| IF-MIB | Objects for network interfaces. |
| IP-MIB | IP and ICMP implementations. |
| HOST-RESOURCES-MIB | Standard hardware parameters. |

SSH Access to the Appliance

This topic applies to Logger Appliances only.

Note: SSH access to Software Logger is controlled through the operating system.

When you report an issue to customer support that requires them to access your appliance for troubleshooting and diagnostics in situations such as an upgrade failure, unresponsive appliance, and so on, they will direct you to enable SSH access on it.

By default, SSH access (known as Support Login in previous releases) to your appliance is disabled. (This also includes Loggers upgraded to version 6.0 from previous versions.) However, you can select one of these options in the appliance's user interface to enable SSH:

- **Enabled:** SSH access is always enabled.
- **Enabled, only for 8 hours:** SSH access is disabled automatically eight hours after it was enabled.
- **Enabled, only during startup/reboot:** SSH access is enabled during the time the appliance reboots and is starting up. It is disabled once all processes on the appliance are up and running. This option provides a minimal period of SSH access for situations such as when the appliance does not start successfully after a reboot.

For optimal security, you should set a strong password for the root account. In addition, leave SSH access disabled and enable it only when necessary, such as for troubleshooting purposes.

Note: If SSH is disabled on your appliance, you can still access its console if you have it setup for remote access using the ProLiant Integrated Lights-Out (iLO) Advanced remote management card. For more information, refer to the Logger Installation Guide.

Enabling or Disabling SSH access:

1. Click **System Admin** from the top-level menu bar.
2. Click **SSH** in the **System** section.
3. On the SSH Configuration dialog, select an SSH configuration.
4. Confirm the new SSH configuration for it to take effect.

Once you have enabled SSH access on your appliance, follow these steps to connect to it using SSH.

Connecting to your appliance using SSH:

1. Connect to the appliance as “root” using an SSH client.
2. At the password prompt, type the root password and press **Enter**.

Note: For security purposes, SSH sessions time out after a 15 minute period of inactivity. To extend SSH connection, configure sending keepalive packets in the SSH client.

Logs

This topic applies to both Software Logger and the Logger Appliance.

Your system can generate audit logs at the application and platform levels. Use the Logs sub-menu to search audit logs.

Audit Logs

Your system's audit logs are available for viewing. Audit logs, as Common Event Format (CEF) audit events, can be sent to ArcSight ESM directly for analysis and correlation. For information about forwarding audit events, see ["Audit Forwarding" on the next page](#).

To view audit logs:


1. Click **System Admin** from the top-level menu bar.
2. Click **Audit Logs** in the **Logs** section.
3. Select the date and time range for which you want to obtain the log.
4. (Optional) To refine the audit log search, specify a string in the **Description** field and a user name in the **User** field. When a description string is specified, only logs whose Description field contains the string are displayed. Similarly, when a user is specified, only logs whose User field contains the username are displayed.
5. Click **Search**.


Note: Entries that did not require the user interaction are labeled as system in the username column.

Audit Forwarding

You can forward audit events to an ArcSight ESM for correlation and analysis. For a list of audit events that you can forward, see ["Application Events" on page 579](#).

To forward audit events to specific ESM destinations:

1. Click **System Admin** from the top-level menu bar.
2. Click **Audit Forwarding** in the **Logs** section.
3. Select destinations from the **Available Destinations** list and click the right arrow icon () to move the selected destination to the **Selected Destinations** list.

You can select multiple destinations at the same time and move them, or you can move all available destinations by clicking the () icon.

The destinations are ESM destinations that you configure on the ESM Destinations page (**Configuration > Data > ESM Destinations**).

4. Click **Save Settings**.

Storage

This topic applies to Logger Appliances only.

Use the **Storage** sub-menu to add an NFS mount or a CIFS mount, or SAN (if applicable) and to view the status of the hard disk array (RAID) controller and specific system processes.

- [Remote File Systems](#)475
- [SAN](#)478
- [RAID Controller](#)483

Remote File Systems

This topic applies to Logger Appliances only.

Your system can mount Network File System (NFS) and CIFS (Windows) shares. As a result, it can read log files and event data from UNIX, Linux, Windows remote hosts, and any Network Attached Storage (NAS) solutions based on these operating systems. In addition, you can use the NFS and CIFS mounts for archiving data such as events, exported filters and alerts, and saved searches. Loggers with Storage Area Network (SAN) capability can also interface with a SAN.

Logger appliance supports NFSv4. However, using a NFS for primary storage of Logger events is not recommended. Using a CIFS share for primary storage is not supported.

- [Managing a Remote File System](#)476

Managing a Remote File System

This topic applies to Logger Appliances only.

Make sure the following requirements are met before you mount a share.

| File System Type | Requirements |
|------------------|--|
| CIFS (Windows) | <ul style="list-style-type: none">• A user account that has access to the shared drive exists on the Windows system.• The folder to which you are establishing the mount point is configured for sharing. |
| NFS | <ul style="list-style-type: none">• Grant your ArcSight system read and write permission on the NFS system.• The account used for mounting must use the numeric ids 1500 for uid, or 750 for gid. |

Note: A location of the Remote Path must be used for one system only. If multiple systems mount the same remote path and write to it, the location data will be corrupted or deleted.

To add a Remote File System mount:

1. Click **System Admin** from the top-level menu bar.
2. Click **Remote File Systems** in the **Storage** section in the left panel.
The **Remote File Systems** table is displayed.
3. Click **Add** from the top left side of the page and enter values for the following fields in the resulting form.

| Parameter | Description |
|-------------------------|--|
| Select File System Type | Whether you want to mount an NFS or a CIFS share. |
| NFS Settings | |
| Name | A meaningful name for the mount point. This name is used locally on your system to refer to the mount point, and needs to be specified when configuring archive settings for data that will be stored on the share. Tip: The mount name cannot contain spaces. |
| Hostname / IP Address | The name or IP address of the host to which you are creating the mount. |
| Remote Path (for NFS) | The folder on the remote host that will act as the root of the network file system mount. For example, /public/system_logs. |

| Parameter | Description |
|-----------------------------|---|
| Mount Options | <p>AutoFS options. For example, ro for read-only from the remote host, rw for read-write, or hard to keep retrying until the remote host responds.</p> <p>Note: Even if you configure rw permission at your mount point, read-write permission is not granted to the remote host if the host is configured to allow read-only access.</p> |
| Description | A meaningful description of the mount point. |
| CIFS Settings | |
| Name | <p>Name is used locally on your system to refer to the mount point, and needs to be specified when configuring archive settings for data that will be stored on the share.</p> <p>Note: The mount name can include alpha-numeric, dash (-), and underscore (_) characters. It must begin with an alpha-numeric character.</p> |
| Location | <p>Enter the share name in one of the following ways:</p> <ul style="list-style-type: none"> Share name in this format: <code><IP Address> or <Hostname>:<share_name></code> For example, 198.0.2.160:myshare This folder needs to be configured for sharing. (Typically, to configure a Windows folder for sharing, right click on the folder name > Properties > Sharing) <p>Caution: When mounting from a Windows Server 2008 in cluster, you must use the Hostname and not the IP address for a successful mount.</p> UNC path: For example, //198.0.2.160/myshare |
| Mount Options | <p>Autofs options: For example, ro for read-only from the remote host, rw for read-write, or hard to keep retrying until the remote host responds.</p> <p>Note: Even if you configure the rw at your mount point, read- write permission is not granted if the host is configured to allow read-only access.</p> <p>Further mount options might be required depending on the remote host configuration. For example: "vers=2.1,sec=ntlmv2i" for SMB 2 and NTML v2 auth.</p> |
| Description | A meaningful description of the mount point. |
| Credentials for CIFS | |
| Username | <p>The name of the user account with read-write privileges to the Windows share. Make sure the username is prefixed with the domain information. For example, tahoe\arcsight.</p> |
| Password | The password for the user name specified above. |

4. Click **Add**.

All mount points are created under `/opt/mnt`.

To edit a Remote File System mount:

Note: You cannot edit a mount point if it is in use. The **Edit** link is displayed only if the mount point can be edited.

If you rename a mount point, access to the archives that were made using the original name is lost until you revert the mount point name to the original name.

1. Click **System Admin** from the top-level menu bar.
2. Click **Remote File Systems** in the **Storage** section in the left panel.
3. Select the mount point you want to edit, and click **Edit** from the top left side of the page.
4. Change the field values.
5. Click **Save**.

To delete a Remote File System mount:

Note: You cannot delete a mount point that is in use. The **Delete** link is displayed only if the mount point can be deleted.

1. Click **System Admin** from the top-level menu bar.
2. Click **Remote File Systems** in the **Storage** section in the left panel.
3. Select the mount point you want to delete, and click **Delete** from the top left side of the page.

SAN

This topic applies to Logger Appliances only.


Some models of the Logger Appliance include the ability to connect to a Storage Area Network (SAN). SANs contain Logical Units (LUNs), identified by their World Wide Name.

- [Managing a LUN](#)478
- [Restoring a SAN](#)480
- [Creating Multiple Paths to a LUN](#)481

Managing a LUN

This topic applies to Logger Appliances only.

A LUN can be in "available," "attached," or "detached" state, which determines what actions are available within Logger.



The following table summarizes the LUN states and possible actions.

| Attachment Status | Actions | Description |
|-------------------|----------------------|--|
| available | attach | LUNs detected on a SAN are initially available for attachment. |
| attached | detach | Attached LUNs can be accessed by Logger. The "detach" action is only available if a storage volume has not been configured on the LUN. Once a storage volume has been configured, you cannot "detach" the LUN unless you follow the factory reset instructions, described in "Restoring Factory Settings" on page 658 . |
| detached | re-attach destroy | When an attached LUN is detached, its data is preserved, but it cannot be accessed by Logger. To make it available again, use the "re-attach" action. The "destroy" action releases the LUN back to the "available" state. When you detach, the only action available immediately is "re-attach" . The "destroy" state takes a few minutes to appear because it takes a few minutes for the LUN to detach on the system. Destroying a LUN puts it into a state in which a subsequent attach will erase any data stored on the LUN. If a LUN is accidentally destroyed, customer support may be able to recover the data, provided there has been no subsequent attempt to attach the LUN. |

Logger can attach to only one LUN at a time for primary storage. You can attach an additional LUN for event archiving, configuration backup, and export.

The L7500-SAN has two HBAs. This enables you to use one for multipathing and one for event archival, configuration backup, and export. For information about multipathing, see ["Creating Multiple Paths to a LUN" on page 481](#).

To attach a LUN:

1. Click **System Admin** from the top-level menu bar.
2. Click **SAN** in the **Storage** section in the left panel.
3. Under **SAN Configuration**, locate and select the LUN in the LUN Name List.
4. Click **Attach** from the top left of the SAN Configuration page. If you do not see the **Attach** menu option, no LUNs can be attached to the Logger at this time.

Note: You can attach a LUN only if the LUN is in the "Available" status.

The LUN's Attachment Status will change to "Attached" when the LUN is ready for use.

To detach a LUN:

1. Click **System Admin** from the top-level menu bar.
2. Click **SAN** in the **Storage** section in the left panel.
3. In the LUN Name List, locate the LUN to be detached.
4. Click **Detach** from the top left of the SAN Configuration page. If you do not see the Detach menu option, no LUNs can be detached from the Logger at this time.

Note: You cannot detach a LUN if a storage volume is configured on it.

To re-attach a LUN:

1. Click **System Admin** from the top-level menu bar.
2. Click **SAN** in the Storage section in the left panel.
3. In the LUN Name List, locate the LUN to be re-attached. The LUN must be in the **Detached** state.
4. Click **Re-attach** from the top left of the SAN Configuration page.

If you do not see the Re-attach menu option, no LUNs can be re-attached from the Logger at this time.

To destroy a LUN:

1. Click **System Admin** from the top-level menu bar.
2. Click **SAN** in the **Storage** section in the left panel.
3. In the LUN Name List, locate the LUN to be destroyed. The LUN must be in the 'detached' state.
4. Click **Destroy** in the top left corner of the SAN Configuration page.

Caution: Destroying a Logical Unit (LUN) that has been detached, puts that LUN into a state in which a subsequent attach will erase any data stored on the LUN. If a LUN is accidentally destroyed, customer support may be able to recover the data, provided there has been no subsequent attempt to attach the LUN.

Restoring a SAN

This topic applies to Logger Appliances only.

You can restore a SAN to either the Logger to which it was formerly attached, or to a new Logger (in the case of disaster recovery).

To restore a SAN:

1. With Logger powered off, attach the SAN physically.
2. Turn on Logger.
3. Restore the configuration to Logger. Micro Focus recommends backing up the configuration regularly so that a backup file will be available for this purpose. If no backup file is available, skip this step and manually add receivers, forwarders, users, and so on, after the SAN has been restored. For more information, see ["Configuration Backup and Restore" on page 436](#).
4. Enable SSH access to your Logger (see ["SSH Access to the Appliance" on page 473](#)).
5. Contact customer support at <https://www.microfocus.com/support-and-services/contact-support/>
6. Customer support will log in remotely, stop all Logger processes, and migrate the internal database to the SAN.
7. When customer support has finished, reboot Logger.

Creating Multiple Paths to a LUN

This topic applies to Logger Appliances only.

The HBA card on your Logger has two ports. You can connect both of those ports to the same LUN. Using those ports to create two different paths between the Logger and the LUN (multipathing) reduces the possibility of a single point of failure causing the LUN to become unavailable.

Note: Although any SAN vendor that supports multipathing can work with Logger, ArcSight specifically tests with Micro Focus 3PAR SANs.

Logger provides a default multipath configuration as a starting point. However, make sure that you consult your SAN documentation for information specific to your environment.

A multipath user interface (UI) is available by default on Logger models that support SAN. However, you must connect the LUN to both HBA ports and configure multipath configuration in the UI for it to function. Once enabled, **multipath cannot be disabled** on Logger.

You do not need to enable multipath in order to connect to two different LUNs on different SANs, since there are no duplicate paths. To connect to two different LUNs on the same SAN, or to have two connections to the same LUN, you must configure multipathing. Otherwise, the OS will see duplicate paths to the same LUN, and will be unable to resolve which path to use.

To enable multipath for a new Logger installation, configure multipathing before attaching the LUN.

To enable multipath:

1. Ensure that a LUN is **not** attached to the Logger, as described in ["SAN" on page 478](#).
2. Click **System Admin** from the top-level menu bar.

3. Click **Multipath** in the **Storage** section in the left panel.
4. Select a SAN multipathing configuration from the pull-down menu.
5. If you chose **Custom**, or if the displayed configuration does not meet your needs, customize the parameters.
6. Click **Test** to ensure that the configuration you chose or the changes you made are valid.
If the test fails, make additional changes, or click **Reset** to start over.
7. Click **Save**.

When you configure multipath SAN connectivity to the appliance, you must also make sure that the **multipathd** service is configured to start on boot.

To verify that the multipathd service is configured to start on boot:

1. Run `chkconfig --list multipathd`
Make sure `#:on` is shown for your run level. The current run level can be displayed with the `'runlevel'` command.
2. If the service is not enabled, do so with:
`chkconfig multipathd on`
3. Reboot the appliance or start the multipath daemon with:
`/sbin/service multipathd start`

Note: Be sure to also configure any vendor-specific multipath configuration accordingly in the `/etc/multipath.conf` file.

To convert a single path LUN to multipath:

1. Connect to your Logger using SSH, as described in ["SSH Access to the Appliance" on page 473](#).
2. Run these commands:

```
cd /opt/arcsight/aps/mpath
./mpath_prepare.sh
```

3. Connect the second fiber cable to the second port on the HBA card.
4. Create the **multipath.conf** file for your SAN.

The contents of this file will vary depending on your SAN vendor and configuration. The Logger user interface includes a default multipath configuration for EMC CLARiiON SANs that can be used as a starting point to populate the **multipath.conf** file. However, consult your SAN documentation for information specific to your setup and environment.

To view the default multipath configuration for EMC CLARiiON SAN, connect to the Logger UI, go to System Admin > Multipath, copy the configuration from the UI, and then paste the copied configuration in the `/opt/arcsight/aps/mpath/multipath.conf` file.

5. Run this test command:

```
./mpath_test.sh <path_to_your_multipath.conf >
```

Review the output of the test command to ensure that multipath devices that will be created are listed at the bottom of the output.

6. If test output is not correct, repeat the steps ["Create the multipath.conf file for your SAN." on the previous page](#) and ["Run this test command:" above](#) until the multipath devices are correctly listed.
7. Run this command:

```
./mpath_enable.sh <path_to_your_multipath.conf >
```

8. Reboot your appliance.

RAID Controller

This topic applies to Logger Appliances only.

You can view information about the RAID controller in the General Controller Information screen. This information is not needed during normal system operations, but it can be helpful for diagnosing specific hardware issues. Due to the redundant nature of RAID storage, a single drive failure will not disable your system. Instead, performance degrades. Use this report to determine whether a performance issue is caused by a disk failure. Customer support can also use this information to diagnose problems.

To view the General Controller Information screen:

1. Click **System Admin** from the top-level menu bar.
2. Click **RAID Controller** in the **Storage** section in the left panel.
3. The information displayed depends on the hardware model of your system. Click the arrows to toggle the information displays.

Security

This topic applies to both Software Logger and the Logger Appliance.

Security settings enable you to configure SSL server certificates, enable and disable FIPS (Federal Information Processing Standards) mode on your system, and configure SSL client authentication for client certificate and Common Access Card (CAC) support.

Tip: For steps on how to create a user DN, see ["Creating and Activating Users" on page 507](#), and refer to the section "Use Client DN" in the parameters table.

- [SSL Server Certificate](#) 484

| | |
|---|-----|
| • SSL Client Authentication | 488 |
| • FIPS 140-2 | 491 |

SSL Server Certificate

This topic applies to both Software Logger and the Logger Appliance.

Your system uses Secure Sockets Layer (SSL) technology to communicate securely over an encrypted channel with its clients, such as SmartConnectors, when using the SmartMessaging technology and other ArcSight systems. Your system ships with a self-signed certificate so that an SSL session can be established the first time you use the appliance. For more information on this option, see ["Generating a Self-Signed Certificate" below](#).

Although a self-signed certificate is provided for your use, Micro Focus strongly recommends using a certificate authority (CA) signed certificate. Additionally, ensure that the root certificate of the CA that signed your system's certificate is trusted on the SmartConnector. If the CA's root certificate is not trusted on the SmartConnector, follow instructions in ["Installing or Updating a SmartConnector to be FIPS-Compliant" on page 493](#).

To facilitate obtaining a CA-signed certificate, your system can generate a Certificate Signing Request. Once a signed certificate file is available from the CA, it can be uploaded to your system for use in a subsequent authentication. For detailed instructions, see ["Generating a Certificate Signing Request \(CSR\)" on page 486](#).

Your system generates an audit event when the installed SSL certificate is going to expire in less than 30 days or has already expired. The event with Device Event Class ID **"platform:407"** is generated periodically until you replace the certificate with one that is not due to expire within 30 days.

| | |
|--|-----|
| • Generating a Self-Signed Certificate | 484 |
| • Generating a Certificate Signing Request (CSR) | 486 |
| • Importing a Certificate | 487 |
| • Enabling HTTP Strict Transport Security | 487 |

Generating a Self-Signed Certificate

This topic applies to both Software Logger and the Logger Appliance.

Your appliance ships with a self-signed certificate so that an SSL session can be established the first time you connect. This type of certificate does not require signing from another entity and can be used immediately.

To generate a self-signed certificate:

1. Click **System Admin** from the top-level menu bar.
2. Click **SSL Server Certificate** from the **Security** section in the left panel to display the **Generate Certificate/Certificate Signing Request** page.
3. Click the **Generate Certificate** tab.
4. From the **Enter Certificate Settings** field, enter new values for the following fields:

| Parameter | Description |
|---------------------|---|
| Country | A two-letter country code, such as 'US' for the United States. |
| State/Province | State or province name, such as 'California.' |
| City/Locality | City name, such as 'Sunnyvale'. |
| Organization Name | Company name, governmental entity, or similar overall organization. |
| Organizational Unit | Division or department within the organization. |
| Hostname | <p>The host name or IP address of this system.</p> <p>When specifying the host name, make sure that this name matches the name registered in the Domain Name Service (DNS) server for the system. On the Logger Appliance, this name must be identical to the host name specified in "NICs" on page 460.</p> <p>Note: If the host name or IP address of this system changes in the future, you must generate a new self-signed certificate or CSR. Once a new certificate is obtained, you must upload it to ensure that the connectors (in FIPS mode) which communicate with the system are able to validate the host name.</p> |
| Email Address | The email address of the administrator or contact person for this CSR. |
| Private Key Length | Select the length (in bits) of the private key: 1024 , 2048 , 4096 , or 8192 . |

Use the first two buttons to generate a CSR or a self-signed certificate. The **View Certificate** button is only used to view the resulting certificate.

| Button | Description |
|----------------------|--|
| Generate CSR | Click to generate a Certificate Signing Request (CSR). |
| Generate Certificate | Click to generate a self-signed certificate. |
| View Certificate | Click to view the generated certificate. |

5. Click the **Generate Certificate** button to generate the self-signed certificate.

Note: The Apache server restarts while generating the certificate. You may get an error communicating to the web server while this is happening. This is expected behavior, and communication is automatically restored once Apache is back up.

6. Click **Ok** to confirm generation.
7. Click the **View Certificate** button to view the PEM-encoded self-signed certificate.

Generating a Certificate Signing Request (CSR)

This topic applies to both Software Logger and the Logger Appliance.

Generating a Certificate Signing Request (CSR) is the first step to obtain a certificate signed by a 3rd party Certificate Authority (CA), for example, VeriSign. The resulting CSR must be sent to a CA, such as VeriSign, which responds with a signed certificate file. The CSR must be generated on the system for which you are requesting a certificate. That is, you cannot generate a CSR for System A on System B or use a third-party utility for generation.

To generate a certificate signing request:

1. Click **System Admin** from the top-level menu bar.
2. Click **SSL Server Certificate** from the **Security** section in the left panel to display the **Generate Certificate/Certificate Signing Request** page.
3. Click the **Generate Certificate** tab.
4. From the **Enter Certificate Settings** field, enter new values for the following fields:

| Parameter | Description |
|---------------------|---|
| Country | A two-letter country code, such as 'US' for the United States. |
| State / Province | State or province name, such as 'California.' |
| City / Locality | City name, such as 'Sunnyvale'. |
| Organization Name | Company name, governmental entity, or similar overall organization. |
| Organizational Unit | Division or department within the organization. |
| Hostname | <p>The host name or IP address of this system.</p> <p>When specifying the host name, make sure that this name matches the name registered in the Domain Name Service (DNS) server for the system. For Logger Appliances, this name must be identical to the host name specified in "NICs" on page 460.</p> <p>Note: If the host name or IP address of this system changes in the future, you must generate a new self-signed certificate or CSR. Once a new certificate is obtained, you must upload it to ensure that the connectors (in FIPS mode) which communicate with the system are able to validate the host name.</p> |
| Email Address | The email address of the administrator or contact person for this CSR. |
| Private Key Length | Select the length (in bits) of the private key: 1024 , 2048 , 4096 , or 8192 . |

5. Use the first two buttons to generate a CSR or a self-signed certificate. The **View Certificate** button is only used to view the resulting certificate.

| Button | Description |
|----------------------|--|
| Generate CSR | Click to generate a Certificate Signing Request (CSR). |
| Generate Certificate | Click to generate a self-signed certificate. |
| View Certificate | Click to view the generated certificate. |

6. Choose **Generate CSR** to generate a certificate signing request.
7. If the CSR was successfully generated, a pop-up window is shown, enabling you to either download the CSR file or to copy/paste its content.
To copy/paste, copy all the lines (inclusive) from `-----BEGIN CERTIFICATE REQUEST-----` to `-----END CERTIFICATE REQUEST-----`.
8. Send the CSR file to your certificate authority to obtain the CA-signed certificate.
9. Once the CA-signed certificate file is obtained, continue on to ["Importing a Certificate" below](#).

Importing a Certificate

This topic applies to both Software Logger and the Logger Appliance.

After you have obtained a certificate from your certificate authority (CA), you can follow the steps below to import it onto your system.

To import a certificate:

1. Click **System Admin** from the top-level menu bar.
2. Click **SSL Server Certificate** under the **Security** section in the left panel.
3. Click the **Import Certificate** tab.
4. Click the **Browse** button to locate the signed certificate file on your local file system.

Note: The imported certificate must be in Privacy Enhanced Mail (PEM) format.

5. Click **Import and Install** to import the specified certificate.
6. If using **HTTPS** and depending on your browser, you may need to close and restart the browser for the new certificate to take effect. If you are unsure of your browser's requirements, close and restart it.

Enabling HTTP Strict Transport Security


HTTP Strict Transport Security (HSTS) is a simple and widely supported standard to ensure that browsers always connect to a website over HTTPS. Using it, you can remove the need for the insecure practice of redirecting users from **http://** to **https://** URLs.

Connecting to the Logger Web UI requires an HTTPS URL:

- **https://<hostname or IP address>** for Logger Appliances.
- **https://<hostname or IP address>:<configured_port>** for Software Loggers.

However, you may accidentally try to connect to Logger over HTTP instead of HTTPS, leaving you vulnerable to a man-in-the-middle attack. You can leverage Logger's support for HSTS to ensure that your browser always connects to Logger over HTTPS.

To enable HSTS:

1. On Logger, generate a Certificate Signing Request (CSR). See ["Generating a Certificate Signing Request \(CSR\)" on page 486](#) for the steps to generate the CSR.
 - Do not use a self-signed certificate.
 - Do use the fully-qualified domain name (FQDN) when creating the certificate, for example, **n192-0-2-h24.server.yourco.com**.
2. Have the CSR signed by a Certificate Authority(CA), such as Verisign, who will return the CA-signed certificate back to you.
3. Import the CA-signed certificate into Logger. See ["Importing a Certificate" on the previous page](#) for the steps to import the certificate.
4. In the browser, import the CA-signed certificate in your browser's trust store. Refer to your browser's help for instructions on importing a trusted certificate.
For example, in Firefox 47.x, you would select **Options** from the  menu, click **Advanced**, click the **Certificates** tab, click **View Certificate**, click the **Authorities** tab, and click the **Import** button.
5. Close and restart the browser. You should now be able to connect to Logger using the following HTTP addresses:
 - **http://<Logger FQDN>** for Logger Appliances.
 - **http://<Logger FQDN>:<configured_port>** for Software Loggers.

Note: Be sure to use the Logger FQDN and not an IP address or hostname in the URL.

SSL Client Authentication

This topic applies to both Software Logger and the Logger Appliance.

Your system supports client authentication using SSL certificates. SSL client authentication is a form of two-factor authentication that can be used *as an alternate* or *in addition to* local password authentication. As a result, your system can be configured for SmartCards, such as Common Access Card (CAC) based authentication. CAC is a standard identification card for active duty members of the Uniformed Services, Selected Reserve, DOD civilian employees, and eligible contractor personnel.

Note: CAC is a form of client certificate authentication. Information on client certificate authentication

applies to CAC.

Your system also supports LDAPS authentication. The SSL certificate for the LDAPS server must be uploaded into the trusted store. After uploading the SSL certificate, the aps process must be restarted (**System Admin > Process Status > aps > Restart**).

- [Configuring Logger to Support SSL Client Authentication](#)489
- [Uploading Trusted Certificates](#)490
- [Uploading a Certificate Revocation List](#)490

Configuring Logger to Support SSL Client Authentication

This topic applies to both Software Logger and the Logger Appliance.

Perform the following steps to configure Logger to support SSL client authentication.

To configure Logger to support SSL client:

On the Logger:

1. If the Logger uses the default signed certificate it shipped with from ArcSight, replace it with a **FIPS-compliant**, signed SSL server certificate. Follow instructions at ["Uploading Trusted Certificates" on the next page](#) to load the certificate.

Caution: All SSL client certificates used for authentication must be FIPS-compliant (that is, hashed with FIPS-compliant algorithms) even if FIPS is not enabled on your Logger.

2. Enable client certificate authentication, as described in ["Client Certificate Authentication" on page 501](#).
3. Choose one of the following:
 - If the client certificates are **CA-signed**, upload the root certificate of the authority who signed the certificates that will be used for authenticating clients, as described in ["Uploading Trusted Certificates" on the next page](#).
 - If the client certificates used to authenticate with Logger are signed by different CAs, make sure you upload root certificates of **all** CAs.
 - If the client certificates are **self-signed**, upload the public portion of the client certificate.
4. Configure a user name for each user who will be connecting to the Logger using a client certificate, as described in ["User Management" on page 506](#).
5. (Optional) Upload a certificate revocation list (CRL), as described in ["Uploading a Certificate Revocation List" on the next page](#).
6. (Optional) If this Logger is configured to use **only** SSL Client Authentication, make sure this Logger's Authorization ID and Code are appropriately configured on other Loggers that with it. For more information, see ["Peer Nodes" on page 450](#).

On the Client (Web browser):

Configure your browser to provide the SSL client certificate when accessing Logger. (Upload the private key in PKCS 12 format in your browser.)

Uploading Trusted Certificates

This topic applies to both Software Logger and the Logger Appliance.

A trusted certificate is used to authenticate users that log in to your system. Uploading a trusted certificate is required if you are using LDAPS authentication. The trusted certificate is used to authenticate the remote LDAPS server. The certificate needs to be in Privacy Enhanced Mail (PEM) format.

To upload a trusted certificate:

1. Click **System Admin** from the top-level menu bar.
2. Click **SSL Client Authentication** in the **Security** section in the left panel.
3. On the **Trusted Certificates** tab, click **Browse** to find the trusted certificate on your local file system.
4. Click **Upload**. The trusted certificate is uploaded and listed in the **Certificates in Repository** list.

To view details about a trusted certificate, click the link displayed in the Certificate Name column.

To delete a trusted certificate, select the certificate and click **Delete**.

Uploading a Certificate Revocation List

This topic applies to both Software Logger and the Logger Appliance.

A certificate revocation list (CRL) is a computer-generated record that identifies certificates that have been revoked or suspended before their expiration dates. To support CAC, you need to upload a CRL file to your ArcSight system. The CRL file needs to be in PEM format.

To upload a CRL file:

1. Click **System Admin** from the top-level menu bar.
2. Click **SSL Client Authentication** in the **Security** section in the left panel.
3. In the **Certificate Revocation List** tab, click **Browse** to find the CRL file on your local file system.
4. Click **Upload**. The CRL is uploaded and listed in the **Certificate Revocation** list.

To view details about a CRL, click the link displayed in the **Issuer Name** column.

To delete a CRL file, select it and click the **Delete** button.

Note: To enable client certificate authentication, see ["Client Certificate Authentication" on page 501](#).

FIPS 140-2

This topic applies to both Software Logger and the Logger Appliance.

Your system supports the Federal Information Processing Standard 140-2 (FIPS 140-2). FIPS 140-2 is a standard published by the National Institute of Standards and Technology (NIST) and is used to accredit cryptographic modules in software components. The US Federal government requires that all IT products dealing with Sensitive, but Unclassified (SBU) information meet these standards.

- [FIPS Compliance](#)491
- [Enabling and Disabling FIPS Mode on Logger](#)492
- [Installing or Updating a SmartConnector to be FIPS-Compliant](#) 493

FIPS Compliance

If your system needs to be FIPS 140-2 compliant, you can enable FIPS. Once you do so, the system uses the cryptographic algorithms defined by the NIST for FIPS 140-2 for all encrypted communication between its internal and external components.

Note: To be fully FIPS 140-2 compliant, all components of your Logger deployment need to be in FIPS 140-2 mode. For example, if you enable FIPS 140-2 on your Logger but the SmartConnectors that send events to it are not running in FIPS 140-2 mode, your deployment is not fully FIPS 140-2 compliant.

In a typical deployment, your Logger will communicate with the following components. To be fully FIPS-compliant, all of these components should be FIPS-enabled:

- SmartConnectors that send events to the Logger: Follow instructions in ["Installing or Updating a SmartConnector to be FIPS-Compliant" on page 493](#) to ensure that your connector is FIPS-compliant.
- Logger forwarders, such as ArcSight Managers to which Logger forwards events and alerts: The system to which your FIPS-compliant Logger forwards events should be FIPS-compliant as well. Additionally, you need to import that system's SSL server certificate on the Logger so that Logger can communicate with it. If you forward events and alerts to an ArcSight Manager, it needs to run ESM 4.0 SP2 or later to enable FIPS 140-2 on it. For more information, see the ArcSight ESM Installation and Configuration Guide for the ESM version you are running. Additionally, follow instructions in ["ESM Destinations" on page 395](#) to complete configuration of this setup.
- Loggers: Logger automatically uses FIPS 140-2 compliant algorithms. Therefore, no action is required on Logger, except enabling FIPS as described in this section. When enabling FIPS on a Software Logger, make sure that the machine on which Logger is installed is used exclusively for Logger.

Note: Enabling FIPS 140-2 on Software Logger does not make the system on which it is installed FIPS 140-2 compliant. Consult your system's documentation to determine the requirements for

making the entire system FIPS 140-2 compliant.

- A Logger must use a CA-signed certificate if it is a destination of a software-based SmartConnector. Additionally, ensure that the root certificate of the CA that signed Logger's certificate is trusted on the SmartConnector. If the CA's root certificate is not trusted on the SmartConnector, follow instructions in ["Installing or Updating a SmartConnector to be FIPS-Compliant" on the next page](#).

Enabling and Disabling FIPS Mode on Logger

This topic applies to both Software Logger and the Logger Appliance.

You can enable or disable FIPS mode on Logger to suit your needs; however, you will need to reboot (Logger Appliance) or restart (Software Logger) before the new mode will be effective.

Things to be Aware of When Enabling FIPS Mode on Logger:

- Your Logger must be set up with a CA-signed SSL certificate. For more information, see ["SSL Server Certificate" on page 484](#).
- A Logger, even when in non-FIPS mode, must use a CA-signed certificate if it is software-based SmartConnector. Additionally, ensure that the root certificate of the CA that signed Logger's certificate is trusted on the SmartConnector. If the CA's root certificate is not trusted on the SmartConnector, follow instructions in ["Installing or Updating a SmartConnector to be FIPS-Compliant" on the next page](#).

To enable or disable FIPS mode:

Note: Make sure you are familiar with the configuration requirements on your Logger as described in ["Things to be Aware of When Enabling FIPS Mode on Logger:" above](#).

1. Click **System Admin** from the top-level menu bar.
2. Click **FIPS 140-2** in the Security section in the left panel.
3. Click **Enable** or **Disable** for the Select FIPS Mode option.
4. Click **Save**.
5. Do one of the following:
 - Use the following command to restart Software Logger:
`<install_dir>/current/arcsight/logger/bin/loggerd restart`
 - Reboot your Logger Appliance.

The FIPS Status Table shows which processes and components of the Logger are FIPS-enabled.

Installing or Updating a SmartConnector to be FIPS-Compliant

This topic applies to both Software Logger and the Logger Appliance.

The information in this section is same as that in the ArcSight Installing FIPS-Compliant SmartConnectors document except that the information in that document is generally applicable, while information in this section is in the context of Logger.

FIPS mode is supported on SmartConnectors running version 4.7.5.5372 or later.

| If you are... | Then... |
|--|---|
| Installing a new SmartConnector to send events to a Logger in FIPS-compliant mode | Follow the installation prompts. No additional steps are necessary. |
| Updating a SmartConnector to be FIPS-compliant and the SmartConnector is not running version 4.7.5.5372 or later. | <ol style="list-style-type: none">1. Upgrade the SmartConnector to a FIPS-supported version. Follow instructions in the SmartConnector User's Guide to upgrade the SmartConnector.2. Create an agent.properties file (see Step 2a, below). No additional steps are necessary. |
| Updating a SmartConnector to be FIPS-compliant and the SmartConnector is running version 4.7.5.5372 or later. | Create an agent.properties file (see Step 2a , below). No additional steps are necessary. |

To make a SmartConnector FIPS-compliant:

1. Follow device configuration steps provided in the SmartConnector's configuration guide (available from the Micro Focus Customer Support site (SSO) at <https://www.microfocus.com/support-and-services/contact-support/>), then follow the installation procedure through installation of the core Connector software (SmartConnector Installation Step 2).

At Step 3 of the Connector setup, click **Cancel** to exit the setup. You must then configure the NSS DB, which is necessary for installing the connector in FIPS-compliant mode.

Once the NSS DB is configured, continue to the next step.

2. To enable FIPS Mode on the SmartConnector:
 - a. Create an **agent.properties** file at the following location if it does not exist already:

\$ARCSIGHT_HOME/current/user/agent


- b. Enter the following property, then save and close the file.

fips.enabled=true

3. Import Logger's certificate on the SmartConnector:
 - a. In a command window on your SmartConnector machine, from **\$ARCSIGHT_HOME/current/bin**, enter the following command to turn off FIPS mode:

```
./arcsight runmodutil -fips false -dbdir $ARCSIGHT_HOME/current/user/agent/nssdb.client
```

- b. Export the Logger certificate file and import it to the SmartConnector's NSS DB as follows:

- Export Logger's certificate file from the browser you use to connect to it. Refer to your browser's Help for instructions. For example, to export a Logger's certificate file on Firefox v.44, click  to open the **Options** menu, then select **Advanced > Certificates > View Certificates > Servers > your Logger Appliance** and click **Export...** Save the certificate file with a **.crt** or **.cer** extension.
- Copy the certificate file you exported in the previous step (in this example, **loggercert.crt**) to the **\$ARCSIGHT_HOME/current/bin** directory on the SmartConnector. From **\$ARCSIGHT_HOME/current/bin**, enter the following:

```
./arcsight runcertutil -A -n mykey -t "CT,C,C" -d $ARCSIGHT_HOME/current/user/agent/nssdb.client -i bin/loggercert.crt
```

- c. Enter the following command to re-enable FIPS mode that you turned off in Step 1:

```
./arcsight runmodutil -fips true -dbdir $ARCSIGHT_HOME/current/user/agent/nssdb.client
```

- d. Ensure that the SmartConnector can resolve the name specified in the **CN** value of the Logger certificate's **Subject** field. If the name is not resolvable, add it to the SmartConnector system's **Hosts** file.
- e. If you are installing a new SmartConnector, continue to the next step.

If you are updating your SmartConnector to be FIPS-compliant, ensure that the Connector's Logger destination host name is same as the **CN** value in the certificate's **Subject** field, and **exit this procedure**.

4. To return to the SmartConnector configuration wizard, enter the following from **\$ARCSIGHT_HOME/current/bin**:

```
./arcsight connectorsetup
```

5. When prompted whether you want to start in Wizard Mode, click **Yes**.

The **Destination** selection window is again displayed. Return to **Installation Step 4** of your **SmartConnector Configuration Guide** to continue the Connector configuration.

Note: When configuring the connector, ensure that the connector's Logger destination host name is same as the **CN** value in the certificate's **Subject** field.

For the remainder of the configuration process, see the Configuration Guide for the SmartConnector you are installing. The specific configuration guide provides information about how to configure the device for event collection, specific installation parameters required during the configuration process, and a table of vendor-specific field mappings to ArcSight events.

Users/Groups

This topic applies to both Software Logger and the Logger Appliance.

Use the **Users/Groups** sub-menu to configure users and user groups, and to set authentication options.

| | |
|----------------------------|-----|
| • Authentication | 495 |
| • Login Banner | 506 |
| • User Management | 506 |
| • Change My Password | 513 |

Authentication

This topic applies to both Software Logger and the Logger Appliance.

Authentication Settings enable you to specify the settings and policies for user log in sessions, password rules and lockouts, and external authentication options.

| | |
|---|-----|
| • Sessions | 495 |
| • Local Password | 496 |
| • Users Exempted From Password Expiration | 498 |
| • Enabling Forgot Password | 498 |
| • External Authentication | 500 |

Sessions

This topic applies to both Software Logger and the Logger Appliance.

The **Session** tab lets you specify the maximum number of simultaneous sessions for a single user account, and the length of time after which a user session is automatically logged out or a user account disabled. By default, a single user account can have up to 15 simultaneous active sessions, and a user account is logged out after 15 minutes of inactivity.

To change session settings:

1. Click **System Admin** from the top-level menu bar.
2. Click **Authentication** in the **Users/Groups** section.

3. On the **Sessions** tab, update the parameters described in the following table.

| Parameters | Description |
|--------------------------------|---|
| Max Simultaneous Logins/User | The maximum number of simultaneous sessions allowed for a single user account. The default is 15 sessions . |
| Logout Inactive Session After | The length of time, in minutes, after which an inactive session is automatically ended. The default is 15 minutes . |
| Disable Inactive Account After | The number of days after which an inactive user account is disabled. The default is 0 , meaning the account is never disabled. |

4. Click **Save** to make the changes, or click another tab to cancel.

Local Password

This topic applies to both Software Logger and the Logger Appliance.

The **Local Password** tab enables you to set password policies, such as the minimum and maximum number of characters and other password requirements.

Tip: For better security, if the configured authentication method is "Local Password", ensure that the Account Lockout policy is enabled.

To change the password settings:

1. Click **System Admin** from the top-level menu bar.
2. Click **Authentication** in the **Users/Groups** section.
3. Choose the **Local Password** tab.

Use the parameters described in the following table to customize your password settings.

| Parameter | Description |
|------------------------------|--|
| Lockout Account | |
| Enable Account Lockout | Select the checkbox to enable user accounts to be locked out as defined by the following settings. By default, the policy is disabled . Note: You should enable this if you will be using the "Local Password" authentication method. |
| Lockout Account After | Number of failed login attempts after which a user account is locked out. The default is 3 . |
| Remember Failed Attempts For | The length of time, in minutes, for which a failed login attempt is remembered. The default is 1 . |
| Lockout Account For | The length of time, in minutes, for which a locked out account cannot be unlocked. The default is 15 . |

| Parameter | Description |
|--|--|
| Password Expiration | |
| Enable Password Expiration | Select the checkbox to enable user passwords to expire as defined by the following settings. By default, the policy is disabled . |
| Password Expires in | Number of days after which the password expires. The default is 90 . |
| Notify User | Number of days before expiration to notify the user. Select this option to allow users to update their password before expiration. The default is 5 . |
| Users Exempted From Password Expiration Policy | Click the link to set the users whose password should never expire. For information on how to use this feature, see "Users Exempted From Password Expiration" on the next page . |
| Password Strength Rules | |
| Enforce Password Strength | Select the checkbox to enforce password policy as defined by the following settings. By default, the policy is disabled . |
| Minimum Length | Minimum number of characters that a password must contain. The default is 10 . |
| Maximum Length | Maximum number of characters that a password can contain. The default is 20 . |
| Password Character Rules | |
| Password character rules define additional character requirements to ensure password strength. | |
| Numeric | Minimum number of numeric characters (0-9) in a password. The default is 2 . |
| Uppercase | Minimum number of uppercase characters (A-Z) in a password. The default is 0 . |
| Special | Minimum number of non-digit and non-letter characters that are required in a password. The default is 2 . |
| Lowercase | Minimum number of lowercase characters (a-z) in a password. The default is 0 . |
| Password Must be At Least N Characters Different From Old Password | Minimum number of characters by which the new password must differ by from the previous one. The default is 2 . |
| Include "Forgot Password" link on Login Screen | <ul style="list-style-type: none"> Select the checkbox to enable users to reset their local password using a "Forgot Password" link on the login page. By default, the option is disabled. An SMTP server must be configured on the system, and the username must have a correct email address for this feature to work successfully. If an SMTP server is not set, you will not be able to reset the password because the email containing the temporary password cannot be sent. An email address must be specified in the user settings for the user name. The temporary password is sent to that email address. If no email address is specified or if the email address is incorrect, the user will not receive the email. <p>For information on how to use this feature, see "Enabling Forgot Password" on the next page.</p> |



- Click **Save** to save the changes, or click another tab to cancel.

Users Exempted From Password Expiration

This topic applies to both Software Logger and the Logger Appliance.

Even though you have set a password expiration policy for most users, you may want to have a user whose password does not expire automatically.

To exempt a user from the password expiration policy:

1. Click **System Admin** from the top-level menu bar.
2. Click **Authentication** in the **Users/Groups** section.
3. Choose the **Local Password** tab, and then click **Users Exempted From Password Expiration Policy**.
4. The **Exempt Users From Password Expiration** page is displayed.
5. Select users from the **Non-exempted Users** list and click the right arrow icon  to move the selected users to the **Exempted Users** list. Do the reverse to remove users from the list of exempted users.
You can select multiple users at the same time and move them over. Or you can move all users by clicking the  icon.
6. Click **Save** to save the policy or **Cancel** to exit.

Enabling Forgot Password

About

This topic applies to both Software Logger and the Logger Appliance.

This feature is disabled by default, to enable it:

- All servers must be SMTP configured. For more information on Simple Mail Transfer Protocol, see ["Local Password" on page 496](#).
- A SSL certificate must be uploaded by the user. For more information on SSL certificates, see ["SSL Server Certificate" on page 484](#)

Users can reset their own password from a **Forgot Password?** link accessible from the login screen. Logger sends the user a temporary password to the email address on file.

Procedure

1. From **System Admin > Authentication > Local Password** tab, scroll down to the bottom of the page,
2. Check **Include "Forgot Password" link on Login Screen**
3. Click **Save**.

Authentication Settings

SessionsLocal PasswordExternal Authentication

Local Password Settings

Lockout Account

☐ Enable Account Lockout

Lockout Account After3Failed Attempts

Remember Failed Attempts For0hours1minutes0seconds

Lockout Account For0hours15minutes

Password Expiration

☐ Enable Password Expiration

Password Expires in90days

Notify User5Days Before Expiration

[Users Exempted From Password Expiration Policy \(0\)](#)

Password Strength Rules

☐ Enforce Password Strength

Minimum Length10characters

Maximum Length20characters

Password Character Rules

Password must have a minimum of the following characters

Numeric [0-9]2Uppercase [A-Z]0

Special [!\$%^&*...]2Lowercase [a-z]0

Password Must be At Least2Characters Different From Old Password

☒ Include "Forgot Password" link on Login Screen

Save

The next time a user logs in, the link is enabled.

To reset your password:

1. On the Login dialog box, click the **Forgot Password** link.
2. The Reset Password screen displays.

3. Enter a user name on the Reset Password screen. Use only alphanumeric characters, spaces and **._-@** for the username. Otherwise, the operation fails.
4. Click **Reset Password**.

An automated email with a temporary password is sent to the email address specified for that user. After logging in with the temporary password, Logger redirects you to the Change Password page, where you can reset your password.

Tip: The temporary password is valid until the time specified in the email. The default is five hours. If you do not log in within the specified time, only an administrator can reset the password to generate another temporary password.

Note: Admin password cannot be reset. If an attempt is made, a message displays indicating the action has been successfully completed even though it is not.

See also

- ["Authentication" on page 495](#)

External Authentication

This topic applies to both Software Logger and the Logger Appliance.

Besides providing a local password authentication method, your system supports Client Certificate/CAC, LDAP, and RADIUS authentication. It is not possible to enable all authentication methods simultaneously.

To enable external authentication:

1. Click **System Admin** from the top-level menu bar.
2. Click **Authentication** in the Users/Groups section.
3. Click the **External Authentication** tab.
4. Select an authentication method from the menu.
5. Click **Save**.

Note: CAC is a form of client certificate authentication. Information on client certificate authentication applies to CAC.

Local Password Authentication

This topic applies to both Software Logger and the Logger Appliance.

Local Password Authentication is the default authentication method. It implements the local password policies set in the **Local Password** tab. For more information, see ["Local Password" on page 496](#).

To configure local password authentication:

1. Click **System Admin** from the top-level menu bar.
2. Click **Authentication** in the **Users/Groups** section.
3. Choose the **ExternalAuthentication** tab.
4. From the pull-down menu, choose **Local Password Authentication**
5. Click **Save**.

Client Certificate Authentication

This topic applies to both Software Logger and the Logger Appliance.

This authentication method requires that users authenticate using a client certificate. For each client certificate, a user account with a Distinguished Name (DN) matching the one in the client certificate must exist on your system.

Caution: All SSL client certificates used for authentication must be FIPS-compliant (hashed with FIPS-compliant algorithms) even if FIPS is not enabled on your system.

To configure client certificate authentication:

1. Click **System Admin** from the top-level menu bar.
2. Click **Authentication** in the **Users/Groups** section.
3. Choose the **External Authentication** tab.
4. From the pull-down menu, choose **Client Certificate**.
5. **Allow Local Password Fallback** provides two options:

- **Allow Local Password Fallback for Default Admin Only**

Select this option to allow the default admin user to log in using only a username and password if the client certificate is not available or invalid. This privilege is restricted to the default admin user only—other users must have a valid client certificate to gain access to the system. This option is enabled by default.

- **Allow Local Password Fallback for All Users**

Select this option to allow all users to log in using their local user name and password if their client certificate is invalid or unavailable.

For more information, see ["Local Password Fallback" on page 505](#).

6. Click **Save**.

Client Certificate and Local Password Authentication

This topic applies to both Software Logger and the Logger Appliance.

This authentication method requires that users authenticate using an SSL client certificate and a valid local password. **Local Password** refers to the password associated with the user credentials created in **User Management** in the **Users/Groups** section. See ["Creating and Activating Users" on page 507](#) for details.

A user account on your system must be defined with a Distinguished Name (DN) that matches the one in the client certificate.

For instructions on how to create a user DN, see ["Creating and Activating Users" on page 507](#) and refer to the section called "Use Client DN" in the parameters table.

Caution: All SSL client certificates used for authentication must be FIPS-compliant (hashed with FIPS-compliant algorithms) even if FIPS is not enabled on your system.

To configure client certificate and password authentication:

1. Click **System Admin** from the top-level menu bar.
2. Click **Authentication** in the **Users/Groups** section.
3. Choose the **External Authentication** tab.
4. From the pull-down menu, choose **Client Certificate AND Local Password**
5. **Allow Local Password Fallback** provides two options:
 - **Allow Local Password Fallback for Default Admin Only**

This option, always enabled, enables the default admin user to log in using only a username and password.
 - **Allow Local Password Fallback for All Users**

This option is always disabled. You cannot enable it when using the **Client Certificate AND Local Password** authentication method.

For more information, see ["Local Password Fallback" on page 505](#).
6. Click **Save**.

RADIUS Authentication

This topic applies to both Software Logger and the Logger Appliance.

This authentication method enables users to authenticate against a RADIUS server. Even when RADIUS authentication is enabled, each user account must exist locally on your system. The username must match the one in the RADIUS server, although the password can be different. A user must present a valid username and (RADIUS) password to be successfully authenticated.

To configure RADIUS authentication settings:

1. Click **System Admin** from the top-level menu bar.
2. Click **Authentication** in the **Users/Groups** section.
3. Choose the **External Authentication** tab.
4. From the pull-down menu, choose **RADIUS**.
5. **Allow Local Password Fallback** provides two options:

- **Allow Local Password Fallback for Default Admin Only**

Select this option to allow the default admin user to log in using only a username and password if RADIUS authentication fails. This privilege is restricted to the admin user only—all others must be authenticated by RADIUS. This option is enabled by default.

- **Allow Local Password Fallback for All Users**

Select this option to allow all users to log in using their local user name and password, if RADIUS authentication fails. For more information, see ["Local Password Fallback" on page 505](#).

6. **Update the RADIUS Server** parameters as necessary:

| Parameter | Description |
|--|--|
| Server Hostname[:port] | Enter the host name and port of the RADIUS server. |
| Backup Server hostname [:port] (optional) | (Optional) Enter the backup RADIUS server to use if the primary server does not respond. If the server returns an authentication failure (bad password, unknown username, etc), then the backup server is not tried. The backup server is tried only when the primary server has a communication failure. Use the same format as the primary server to specify the host name and port. |
| Shared Authentication Secret | Enter a RADIUS passphrase. |
| NAS IP Address | The IP address of the Network Access Server (NAS). |
| Request Timeout | The length of time, in seconds, to wait for a response from the RADIUS server (in seconds). The default is 10 . |
| Retry Request | Number of times to retry a RADIUS request. The default is 1 . |
| RADIUS Protocol | Use the pull-down menu to choose a protocol option. The default is None . |

7. Click **Save**.

LDAP/AD and LDAPS Authentication

This topic applies to both **Software Logger** and the **Logger Appliance**.

This authentication method authenticates users against an LDAP server. Even when LDAP is enabled, each user account must exist locally on your system. Although the user name specified locally can be different from the one specified on the LDAP server, the Distinguished Name (DN) specified for each user account must match the one in the LDAP server.

Tip: For steps on how to create a user DN, see ["Creating and Activating Users" on page 507](#), and the parameter ["Use Client DN" on page 508](#)."

To set up LDAP authentication:

1. Click **System Admin** from the top-level menu bar.
2. Click **Authentication** in the **Users/Groups** section.
3. Choose the **ExternalAuthentication** tab.
4. From the pull-down menu, choose **LDAP**.
5. **Allow Local Password Fallback** provides two options:

- **Allow Local Password Fallback for Default Admin Only**

Select this option to allow the default admin user to log in using only a username and password if LDAP authentication fails. This privilege is restricted to the default admin user only—all others must be authenticated by LDAP. This option is enabled by default.

- **Allow Local Password Fallback for All Users**

Select this option to allow all users to log in using their local user name and password if LDAP authentication fails. For more information, see ["Local Password Fallback" on the next page](#).

LDAP Server has the following parameters:

| Parameter | Description |
|--|---|
| Server Hostname[:port] (optional) | (Optional) Enter the host name or IP address and port of the LDAP server in the following format: <code>ldap://<hostname or IP address>:<port></code> <code>ldaps://<hostname or IP address>:<port></code> Additional steps are required for the use of LDAPS. See . |
| Backup Server Hostname [:Port] (optional) | (Optional) Enter the backup LDAP server to use if the primary server does not respond. If the server returns an authentication failure (bad password, unknown username, etc), then the backup server is not tried. The backup server is tried only when the primary server has a communication failure. Use the same format as the primary server to specify the host name and port. |

| Parameter | Description |
|-----------------|---|
| Request Timeout | The length of time, in seconds, to wait for a response from the LDAP server. The default is 10 . |

6. When finished, click **Save**.

To set up LDAP Over SSL authentication:

1. Verify that an SSL certificate for the LDAPS server has been uploaded into the trusted store. See ["Uploading Trusted Certificates" on page 490](#).
2. Follow the steps for ["To set up LDAP authentication:" on the previous page](#).
3. Enter the URL for the LDAPS server(s), starting with **ldaps://**.
4. From the System Admin **System** menu, click **Process Status**.
5. From the Processes table, select **aps**.
6. Click **Restart**.

Caution: You must restart the aps process, or attempts to authenticate through LDAPS will fail.

Local Password Fallback

This topic applies to both Software Logger and the Logger Appliance.

You can use this feature to log in using your local user name and password if the external authentication (Certificate, LDAP, or RADIUS) fails, if you forgot your password to the authentication server, or if the authentication server is not available.

The **Use Local Authentication** feature enables the default admin to log in even when the remote authentication server is not available, by adding a **Use Local Authentication** checkbox to the login screen. Out-of-box, this option is enabled only for the default administrator. However, it is possible to allow local password fallback for all users. For example, you could configure the RADIUS authentication method to allow users to log in using local authentication instead of RADIUS should they fail to authenticate to any configured external RADIUS servers.

For information on how to allow local password fallback for all users for all users, see ["Client Certificate Authentication" on page 501](#), ["LDAP/AD and LDAPS Authentication" on the previous page](#), or ["RADIUS Authentication" on page 503](#).

To log in when authentication fails:

1. On the **ArcSight Logger Login** dialog, select the **Use Local Authentication** checkbox.

Note: This option is only available to the default admin unless it has been enabled for other users.

2. Enter your user name and password and click **Login**.

Login Banner

This topic applies to both Software Logger and the Logger Appliance.

You can customize the message on the login screen to suit your needs. The text you enter in the **Content** and **confirmation** fields are displayed in a first page. After the user acknowledges the message, a second page with Username and Password fields will appear. You must have the "Configure Login Settings" permission enabled for your user account to edit the login banner.

To customize the login banner:

1. Click **System Admin** from the top-level menu bar.
2. Click **Login Banner** in the **Users/Groups** section.
3. Enter the text you want to display as the login banner in the **Content** field

You can enter only unformatted text in this field; however, you can apply standard HTML tags to display formatted text. Loading images in this field is not allowed.

4. (Optional) Enter text in the **confirmation field**

If you enter text in this field, it will be converted to a link that the user must acknowledge to transition to the Username and Password page. For example, if you enter "Are you sure?", "Do you want to proceed?" or "I agree" in this field, the user must click on the text in order to continue. Otherwise, if no text was added, the user must click **ok** to enable the next page.

5. Click **Save**.

User Management

This topic applies to both Software Logger and the Logger Appliance.

The **Users** and **Groups** tabs enable you to manage users and user groups on your system. User groups are a way to enforce access control to various sections of your system.

- [Creating and Activating Users](#)507
- [Setting Logger User Permissions](#)510
- [Reset a User's Password](#)510
- [User Groups](#) 511
- [Managing User Groups](#) 512

Creating and Activating Users

This topic applies to both Software Logger and the Logger Appliance.

Open the **Users** tab to manage the users that can log in to your system. You can add a new user, edit user information, or delete a user at any time. You must have the appropriate System Admin group rights to perform these functions.

Adding a User

To add a new user:

1. Click **System Admin** from the top-level menu bar.
2. Click **User Management** in the **Users/Groups** section in the left panel.
3. In the **Users** tab, click **Add**.

4. Enter the following parameters.

| Parameter | Description |
|---|--|
| Credentials | |
| Login | The user's login name. |
| Password | The user's password. |
| Confirm Password | Reenter the users' password. |
| Contact Information | |
| Use Client DN | <p>If you enabled SSL client certificate or LDAP authentication, click this link to enter user's the Distinguished Name (Certificate Subject) information. The Distinguished Name should be similar to this format:</p> <p>CN=UserA,OU=Engg Team,O=ArcSight\, Inc., L=Cupertino,C=US,ST=California</p> <p>To determine the DN, use this URL to display the certificate:</p> <p>https://<hostname or IP address>/platform-service/DisplayCertificate</p> <p>OR</p> <p>Obtain the DN information for a user from the browser that the user will open to connect to the system. For example, in Firefox, click Tools > Options > Advanced > Encryption > View Certificates > Your Certificates > Select the certificate > View.</p> |
| First Name | The user's first name. |
| Last Name | The user's last name. |
| Email | The user's email address. |
| Phone Number | (Optional) The user's phone number. |
| Title | (Optional) The user's title. |
| Department | (Optional) The user's department. |
| Fax | (Optional) The user's fax number. |
| Alternate Number | (Optional) The user's alternate phone number. |
| Notes | (Optional) Other information about the user. |
| Assign to Groups | |
| <p>This setting controls the privileges a user has on this Logger. Select the groups to which this user belongs. See "Setting Logger User Permissions" on page 510.</p> | |
| System Admin | Permissions to all System Admin operations. |

| Parameter | Description |
|---------------|---|
| Logger Rights | Permissions to read and edit all logger operations except System Admin. |
| Logger Report | Permissions to view, run, schedule, edit, and delete all reports. |
| Logger Search | Permissions to run both local and distributed searches. |

5. Click **Save and Close**.

Editing and Deleting Users

To edit a user:

1. Click **System Admin** from the top-level menu bar.
2. Click **User Management** in the **Users/Groups** section in the left panel.
3. In the **Users** tab, select the user (or users) you want to edit.
4. Click **Edit**.
5. Update the user information as necessary.
6. Click **Save User**.

To delete a user:

1. Click **System Admin** from the top-level menu bar.
2. Click **User Management** in the **Users/Groups** section in the left panel.
3. In the **Users** tab, select the user (or users) you want to delete.
4. Click **Delete** from the top left side of the page.

Note: Deleting a user does not delete their reports. See ["Managing Reports of Deleted Users" on page 286](#).

Activating Users

To activate a user:

1. Click **System Admin** from the top-level menu bar.
2. Click **User Management** in the **Users/Groups** section in the left panel.
3. In the **Users** tab, select the user (or users) that you want to activate.
4. Choose **Edit**.
5. Check the **Active** box.
6. **Save** the changes.

Setting Logger User Permissions

Logger installs with a default Administrator user, who has full permissions to create other users and assign them access permissions. When users require a specific set of permissions, you can create a custom User Group with those permissions. To do this, see ["Creating a New User Group" on page 512](#).

To assign Logger permissions to a user:

1. Click **System Admin** from the Logger navigation bar.
2. From the User/Groups menu, click **User Management**. The Manage Users page opens.
3. Select the check box for the user to whom you want to assign privileges.
4. Click **Edit**. The Edit User page opens.
5. From the Assign to Groups section, select one option from each group type. For new users, the default selection is "Unassigned." A user must be a member of at least one User Group to use Logger.
6. Click **Save and Close**.

Reset a User's Password

This topic applies to both Software Logger and the Logger Appliance.

The Reset Password feature enables you to reset a user's password without knowing their password. If you are using an SMTP-configured server and have permissions to create and update users, you can reset a user's password by clicking the **Reset Password** button. An automated email is sent to the user with the new password string.

To reset a user's password:

1. Click **System Admin** from the top-level menu bar.
2. Click **User Management** in the **Users/Groups** section in the left panel.
3. In the **Users** tab, select the user (or users) whose passwords you want to reset.
4. Click **Reset Password** from the top left side of the page.

The user must use the temporary string to log in within the time specified in the email. If the user does not log in within the specified time, the account becomes deactivated. If the account has been deactivated, the admin must re-activate it before resetting the password.

User Groups

This topic applies to both Software Logger and the Logger Appliance.

User groups define privileges to specific functions on your system and serve to enforce access control to these functions. For example, if you want User A to be able to run searches but not reports, assign that user to the Search group but not to the Reports group.

User groups are organized by the following types: System Admin, Read Only System Admin, Logger Rights, Logger Search, and Logger Reports. Each type has a pre-defined, default user group in which all privileges for the type are enabled. To authorize a subset of the privileges for a specific group type, create a new user group and enable only the privileges you want to provide for that group. Then, assign restricted users to the newly created group.

System Admin Group

The System Admin Group controls the system administration operations for your system, such as configuring network information, setting storage mounts, installing SSL certificates, and user management.

Read Only System Admin Group

In addition to the default System Admin Group that enables all system administration rights (privileges), a Read Only System Admin Group is available on your system. Users assigned to this group can view System Admin settings, but cannot change them.

Logger Rights Group

This applies to both Classic Search and Search page

The Logger Rights Group controls the Logger application operations for your system, such as viewing the Logger dashboards and configuring all the settings in the Configuration menu (including event archives, storage groups, alerts, filters, saved searches, and scheduling tasks.)

Refer to your system's user interface for a complete list of privileges available to this group.

Logger Search Group

The Logger Search Group controls local and peer searches through the following privileges:

- Search for events
- Search for events on remote peers

If the group is configured to allow users to run local and peer searches, users assigned to this group can perform those operations. Conversely, if the group is configured to prevent users from running local and peer searches, users assigned to this group cannot perform those operations.

Note: These users have access to the lookup page, the navigation bar displays this option.

Logger Reports Group

The Logger Reports group controls all report operations on Logger such as run, edit, delete, schedule, and view published reports.

Note: Once a Report Category is deleted, click the Reports tab and check if the changes in the Admin module are reflected.


Refer to your system's user interface for a complete list of privileges available to this group.

Managing User Groups

This topic applies to both Software Logger and the Logger Appliance.

Creating a New User Group

To create a new user group:

1. Click **System Admin** from the top-level menu bar.
2. Click **User Management** in the **Users/Groups** section in the left panel.
3. Click the **Groups** tab.
4. Click **Add**.
5. Define the new group:
 - a. In the **Group Name** field, provide a name for the group.
 - b. In the **Description** field, provide a description for the group.
 - c. From the Group Type drop-down box, select the group type.
 - d. Click the down arrow icon () next to the group type name to view and select privileges that you want to assign to the users in this group.
6. Click **Save and Close** to save the settings of the group, or click **Save and Edit Membership** to add users to this group.

Editing and Deleting User Groups

To edit a user group:

1. Click **System Admin** from the top-level menu bar.
2. Click **User Management** in the **Users/Groups** section in the left panel.
3. Click the **Groups** tab.
4. Select the group that you want to edit, and click **Edit**.
5. Update the user group information.

If you need to edit the group's membership:

- a. Click **Save and Edit Membership** to display the Edit Group Membership page.
- b. Click **Add** from the top left of the Edit Group Membership page.
- c. Select users you want to add. By default, you can add only users who do not belong to other groups of the type that you are editing. To add such users, click **Show users that belong to other <group_type> groups**.

When you add a user who belongs to another group of the same group type as the one you are updating, that user is automatically removed from the previous group.

- d. Click **OK**.
- e. Click **Back to Group List**.
6. Click **Save and Close**.

To delete a user group:

1. Click **System Admin** from the top-level menu bar.
2. Click **User Management** in the **Users/Groups** section in the left panel.
3. Click the **Groups** tab.
4. Select the group (or groups) that you want to delete.
5. Click **Delete** at the top left side of the page.

Change My Password

This topic applies to both Software Logger and the Logger Appliance.

You can use the **Change Password** menu to change your password. This feature is available to all users for changing their passwords, unlike the Reset Password feature that enables a system administrator to reset the password of users without knowing the password. Passwords are subject to the password policy specified by the Admin user.

To change your password:

1. Click **System Admin** from the top-level menu bar.
2. Click **Change Password** in the **Users/Groups** section in the left panel to display the **Change Password for <User Name>** page.
3. Enter the Old Password, the New Password, and enter the New Password a second time to confirm.
4. Click **Change Password**.

Other System Administration Information

This topic applies to both Software Logger and the Logger Appliance.

This section contains information related to system administration that you will need to fully administer your Logger, including starting and stopping Software Logger, system health events, and SNMP polling.

- [Monitoring System Health](#)514
- [System Health Events](#)515
- [Using the Appliance Command Line Interface](#)517
- [Software Logger Command Line Options](#)520
- [Firewall Rules](#)522
- [Configuring the Firewall on Logger Appliance](#)522

Monitoring System Health

This topic applies to both Software Logger and the Logger Appliance.

You can monitor your Logger's health in these ways:

- By using a pre-defined system filter, as listed in ["System Filters/Predefined Filters" on page 140](#). The pre-defined system health filters are based on the system health events listed in ["System Health Events" on the next page](#).
- By searching for system health events in Logger's Internal Storage Group, as listed in ["System Health Events" on the next page](#). If a pre-defined system health filter does not suit your needs, you can create alerts based on the system health events.
- By polling system health events (Logger Appliance only), as explained in ["SNMP" on page 470](#). You can poll system health information from your system by using SNMP version 2c or 3 from any standard network management system.

To set up notification of system health events:

1. Configure the Logger's SMTP settings (see ["SMTP" on page 465](#)) or create an SNMP Destination (see ["SNMP Destinations" on page 392](#)) or Syslog Destination (see ["Syslog Destinations" on page 393](#)).
2. Create an Alert that uses one or more System Alert Filters or define a query that searches for the system health events in Logger's Internal Storage Group, and specify match count and threshold (see ["Logger Alert Types" on page 388](#)).
3. Enable the new Alert.

System Health Events

This topic applies to both Software Logger and the Logger Appliance.

The following table lists the system health events that Logger generates. These events are also referred as Logger Internal Events because they are stored in Logger's Internal Storage Group. See ["System Health Events" on page 598](#) for examples of these events.

The pre-defined System Filters that provide system health status are based on some of these events. If a pre-defined filter does not suit your needs, create an alert using one of these events.

Starting with Logger 5.1, the format in which system health events are generated was changed to provide more meaningful information. These changes include:

- Addition of new events (for example, Current and Voltage).
- Instead of referring to all system health events as Logger Internal Event in the **name** field, meaningful names are used (for example, Fan OK, Temperature OK).
- Three severity levels for each event have been added to the **agentSeverity** field—1 (OK), 5 (Degraded), and 8 (Severe).
- The **deviceCustomString** and **deviceCustomStringLabel** field mappings have changed. Refer to a specific event to see the changes.
- Device Event Class ID (**deviceEventClassId**) and Device Event Category (**deviceEventCategory**) of the events have changed. An updated list is available in the following table.
- All hardware-related events are classified as **hardware:nnn** events, where nnn is a three-digit number that identifies the hardware component (for example, **hardware:13x** identifies the fan events.)

Keep the following in mind when working with System Health Events.

- The sensor names in each event are hardware specific; therefore, they are not consistent across various Logger platforms. Use the event name (Name) and status (CustomString3) fields to determine the status of a sensor. The raw status (CustomString4), location (CustomString5), and sensor name (CustomString6) fields are for informational use when diagnosing a hardware problem and are not consistent across appliance types.
- Micro Focus recommends that you develop custom alerts for certain System Health Events to prevent users from being alerted too often. Some of the conditions that your system alerts on may be self-clearing or warnings that you do not want to be alerted about until a specific number of warnings have been generated.

System Health Events for Both Types of Logger

| Group | Device Event Category | Device Event Class ID |
|---------------|---|-----------------------|
| CPU | /Monitor/CPU/Usage | cpu:100 |
| Disk | /Monitor/Disk/Read | disk:102 |
| | /Monitor/Disk/Write | disk:103 |
| EPS | /Monitor/Receiver/EPS/All | eps:100 |
| | /Monitor/Receiver/EPS/Individual | eps:102 |
| | /Monitor/Forwarder/EPS/All | eps:101 |
| | /Monitor/Forwarder/EPS/Individual | eps:103 |
| Memory | /Monitor/Memory/Usage/Platform | memory:100 |
| Network | /Monitor/Network/Usage/In | network:100 |
| | /Monitor/Network/Usage/Out | network:101 |
| Search | /Monitor/Search/Performed | search:100 |
| Storage Group | /Monitor/StorageGroup/Space/Used | storagegroup:100 |
| | Note: The size of the storage group, indicated by the “ fsize ” field is in GB. | |

System Health Events for Logger Appliances Only

| Group | Device Event Category | Device Event Class ID |
|----------------------|------------------------------------|-----------------------|
| Battery | /Monitor/Sensor/Battery/OK | hardware:121** |
| | /Monitor/Sensor/Battery/Degraded | hardware:122** |
| | /Monitor/Sensor/Battery/Failed | hardware:123** |
| Current (Electrical) | /Monitor/Sensor/Current/OK | hardware:101** |
| | /Monitor/Sensor/Current/Degraded | hardware:102** |
| | /Monitor/Sensor/Current/Failed | hardware:103** |
| Disk | /Monitor/Disk/Space/Remaining/Root | disk:101 |
| Fan | /Monitor/Sensor/Fan/OK | hardware:131 |
| | /Monitor/Sensor/Fan/Degraded | hardware:132 |
| | /Monitor/Sensor/Fan/Failed | hardware:133 |
| Power Supply | /Monitor/Sensor/PowerSupply/OK | hardware:141 |

| Group | Device Event Category | Device Event Class ID |
|-------------|--------------------------------------|-----------------------|
| | /Monitor/Sensor/PowerSupply/Degraded | hardware:142 |
| | /Monitor/Sensor/PowerSupply/Failed | hardware:143 |
| RAID | /Monitor/RAID/Controller/OK | raid:101 |
| | /Monitor/RAID/Controller/Degraded | raid:102 |
| | /Monitor/RAID/Controller/Failed | raid:103 |
| | /Monitor/RAID/BBU/OK | raid:111 |
| | /Monitor/RAID/BBU/Degraded | raid:112 |
| | /Monitor/RAID/BBU/Failed | raid:113 |
| | /Monitor/RAID/Disk/OK | raid:121 |
| | /Monitor/RAID/Disk/Rebuilding | raid:122 |
| | /Monitor/RAID/Disk/Failed | raid:123 |
| Temperature | /Monitor/Temperature/OK | hardware:151 |
| | /Monitor/Temperature/Degraded | hardware:152 |
| | /Monitor/Temperature/Failed | hardware:153 |
| Voltage | /Monitor/Sensor/Voltage/OK | hardware:111** |
| | /Monitor/Sensor/Voltage/Degraded | hardware:112** |
| | /Monitor/Sensor/Voltage/Failed | hardware:113** |

Note: In the table, the notation ** indicates an event generated only on older non-Micro Focus model appliances.

Using the Appliance Command Line Interface

This topic applies to Logger Appliances only.

The Logger appliance CLI enables you to start and stop the appliance as well as issue commands for the Logger application.

Use one of the following methods to connect to the appliance Command Line Interface (CLI):

- Log into Micro Focus ProLiant Integrated Lights-Out (iLO) and launch the remote console feature. For more information, refer to the Logger Installation Guide.
- Connect a keyboard and monitor to the ports on the rear panel of the appliance.
- Connect a terminal to the serial port on the appliance using a null modem cable with DB-9 connector. The serial port expects a standard VT100-compatible terminal: **9600 bps, 8-bits, no parity, 1 stop bit (8N1), no flow control**.

Once you are connected to the CLI, a Login prompt displays.

The following commands are available at the CLI prompt:

| Category | Command | Description |
|---------------------------------|--------------------------|--|
| System Commands | | |
| | exit | Logout |
| | halt | Stop and power down the Logger Appliance |
| | help | Opens the command line interface help |
| | reboot | Reboot the Logger Appliance |
| Admin Commands | | |
| | show admin | Show the default administrator user's name |
| Authentication Commands | | |
| | reset authentication | Reset to local authentication |
| Config Commands | | |
| | show config | Show host name, IP address, DNS, and default gateway for the Logger |
| Date Commands | | |
| | show date | Show the date and time currently configured on the Logger |
| | set date | Set the date and time on Logger. The date/time format is yyyyMMddhhmmss. Example date: 20101219081533 |
| Default Gateway Commands | | |
| | set defaultgw <IP> [nic] | Set the default gateway for one or all network interfaces |
| | show defaultgw [nic] | Display the default gateway for all or the specified network interface |
| DNS Commands | | |
| | show dns | Show the currently configured DNS servers on the Logger |

| Category | Command | Description |
|--------------------------|---|---|
| | set dns <sd> <ns> set dns <sd1>,<sd2> <ns1> <ns2> | Set DNS name server(s). sd=search domain, ns = name server You can add up to three name servers and six search domains. Note: When using multiple search domains, separate them with a comma, but no space. When using multiple name servers separate them with a space but no comma. |
| Hostname Commands | | |
| | show hostname | Show the currently configured hostname on the Logger |
| | set hostname <host> | Set Logger's host name |
| IP Commands | | |
| | show ip [nic] | Show the IP addresses of all or the specified network interface |
| | set ip <nic> <IP> [/prefix] [netmask] | Set Logger's IP address for a specific network interface |
| NTP Commands | | |
| | set ntp <ntp server> <ntp server> <ntp server> ... | Sets the NTP server addresses. This entry overwrites the current NTP server setting. You can specify as many NTP servers as you like. If you specify multiple NTP servers, they are each checked in turn. The time given by the first server to respond is used. Example: logger> set ntp ntp.arcsight.com time.nist.gov 0.rhel.pool.org |
| | show ntp | Show the current NTP server setting. Example: logger> show ntp ntp.arcsight.com time.nist.gov 0.rhel.pool.org |
| Password Commands | | |
| | set password | Set the password the current user's account |

| Category | Command | Description |
|---|-----------------|---|
| Process Commands | | |
| <p>Important: Micro Focus recommends that you do not stop the servers process. To shut down Logger Appliances, use the halt or reboot commands, or perform a system reboot from the UI. For more information, see "System Reboot" on page 458.</p> <p>Never stop the Logger servers process while events are still coming in, this can cause data loss. If you must stop the servers process, be sure to stop the receivers process first, then stop the servers process.</p> | | |
| | restart process | Restart a process |
| | start process | Start a process |
| | status process | Show process status |
| | stop process | Stop a process |
| SSL Certificate Commands | | |
| | show sslcert | Show the currently loaded SSL certificate on Logger |
| | reset sslcert | Creates and installs a new self-signed certificate with the original default information, then restarts the HTTPS server. |
| | diag sslcert | Display the SSL session information |
| Status Commands | | |
| | show status | Show the Logger configuration |

Software Logger Command Line Options

This topic applies to Software Loggers only.

The **loggerd** command enables you to start or stop the Logger software running on your machine. In addition, the command includes a number of subcommands that you can use to control other processes that run as part of the Logger software.

Note: If your Logger is installed to run as a system service, you can use your operating system's **service** command to start, stop, or check the status of a process on Logger. The default service name is **arcsight_logger**.

```
<install_dir>/current/arcsight/logger/bin/loggerd
{start|stop|restart|status|quit}
```

```
<install_dir>/current/arcsight/logger/bin/loggerd {start <process_name> |
stop <process_name> | restart <process_name>}
```

To view the processes that can be started, stopped, or restarted with **loggerd**, click **System Admin** from the top-level menu bar. Then, under **System**, pick **Process Status**. The processes are listed on the right under **Processes**.

The following table describes the subcommands available with **loggerd** and their purpose.

| Command | Purpose |
|---|--|
| loggerd start | Start all processes listed under the System and Process sections. Use this command to launch Logger. |
| loggerd stop | <p>Stop processes listed under the Process section only. Use this command when you want to leave loggerd running but all other processes stopped.</p> <div> <p>Important: Micro Focus recommends that you do not stop the servers process. To shut down Logger, use the loggerd stop or quit commands.</p> <p>Never stop the Logger servers process while events are still coming in, this can cause data loss. If you must stop the servers process, be sure to stop the receivers process first, then stop the servers process.</p> </div> |
| loggerd restart | <p>This command restarts processes listed under the Process section only.</p> <div> <p>Note: When the loggerd restart command is used to restart Logger, the status message for the "aps" process displays this message:</p> <p>Process 'aps' Execution failed.</p> <p>After a few seconds, the message changes to:</p> <p>Process 'aps' running.</p> </div> |
| loggerd status | Display the status of all processes. |
| loggerd quit | Stops all processes listed under the System and Process sections. Use this command to stop Logger. |
| loggerd start <process_name> | Start the named process. For example, loggerd start apache |
| loggerd stop <process_name> | Stop the named process. For example, loggerd stop apache |
| loggerd restart <process_name> | Restart the named process. For example, loggerd restart apache |

Firewall Rules

This topic applies to both Software Logger and the Logger Appliance.

Before Logger can receive data, some ports must be opened through the firewall.

- For Software Logger, you are responsible for setting up the firewall. After you first install or upgrade to Logger 7.0, configure the firewall to be open only for the ports described in ["Default Inbound Ports" below](#), and any other ports required for your configuration.

Caution: Micro Focus ArcSight strongly recommends that you configure your firewall so that only the required ports are open.

- For the Logger Appliance, the firewall is preconfigured. Micro Focus ArcSight provides a script you can use to update the firewall. See ["Configuring the Firewall on Logger Appliance" below](#) for more information.

Tip: Be sure to update the firewall configuration whenever you add or remove any service that requires an open port for incoming traffic, such as a Logger receiver or SNMP polling.

You can configure the firewall on your Logger as you would on any server, by white-listing the appropriate ports in **iptables** (for CentOS and RHEL 6.X) or **firewalld** (for CentOS and RHEL 7.X).

Default Inbound Ports

| Service | Logger Appliance | Software Logger root install | Software Logger non-root install |
|----------------------------------|------------------|---------------------------------|-------------------------------------|
| SSH | 22/TCP | — | — |
| HTTPS | 443/TCP | 443/TCP | 9000/TCP * |
| ArcSight Management Center agent | 7913/TCP | 7913/TCP | 7913/TCP |
| NTP | 123/UDP | — | — |
| UDP receiver | 514/UDP * | 514/UDP * | 8514/UDP * |
| TCP receiver | 515/TCP * | 515/TCP * | 8515/UDP * |

* Configured port may vary.

Configuring the Firewall on Logger Appliance

This topic applies to Logger Appliances only.

Your Logger Appliance includes a script that you can use to configure the firewall. This script looks at your current Logger configuration and decides what ports to keep open. Alternatively, you can configure the

firewall on your Logger as you would on any server, by white-listing the appropriate ports in **iptables** (for CentOS and RHEL 6.X) or **firewalld** (for CentOS and RHEL 7.X).

When called without arguments, the **/usr/sbin/arcfirewall** script displays the ports that it will keep open, but takes no action to alter the firewall configuration. To alter firewall configuration, use the **--set** option.

To preview the list of ports the script would open:

1. Log into the appliance as root.
2. Run the following command:

```
/usr/sbin/arcfirewall.
```

The script displays the ports that it would open if run with the **--set** option.

To configure the firewall:

1. Log into the appliance as root.
2. Run the following command:

```
[root@myserver ~]# /usr/sbin/arcfirewall --set.
```

The script configures the firewall leaving only the necessary ports open.

Appendix A: Search Operators

The following topics describe the operators you can specify in the Search box (**Analyze >Classic Search**) and give examples of their use. Logger supports queries using top, tails, sort or head operator combined with a lookup operator.

Note: Aggregation operators return the combined results of more than one field, and include ["chart" on the next page](#), ["head" on page 538](#), ["keys" on page 538](#), ["rare" on page 545](#), ["sort" on page 551](#), ["tail" on page 552](#), ["top" on page 553](#). For more information, see ["Aggregation Functions" on page 527](#).

| | |
|--------------------------|-----|
| • CEF (Deprecated) | 524 |
| • chart | 525 |
| • dedup | 529 |
| • eval | 530 |
| • extract | 535 |
| • fields | 537 |
| • head | 538 |
| • keys | 538 |
| • lookup | 539 |
| • parse | 544 |
| • rare | 545 |
| • regex | 546 |
| • rename | 546 |
| • replace | 547 |
| • rex | 549 |
| • sort | 551 |
| • tail | 552 |
| • top | 553 |
| • transaction | 554 |
| • where | 556 |

CEF (Deprecated)

Prior to Logger 5.2, you needed to use the cef operator to extract CEF fields from CEF events that matched the indexed search filter (the query portion before the first pipeline in the query expression) before you could use other search operators to act upon those fields. However, starting with Logger 5.2, you do not

need to explicitly extract the CEF fields and then apply other search operators to those fields. You can specify the event fields directly in queries.

Extracts values for specified fields from matching CEF events. If an event is non-CEF, the field value is set to NULL.

Synopsis

```
...| cef <field1> <field2> <field3> ...
```

Usage Notes

If multiple fields are specified, separate each field name with a white space or a comma.

To identify the name of a CEF field, use the Search Builder tool (click Advanced Search under the Search text box), which lists the names of all fields alphabetically.

The extracted fields are displayed as additional columns in the All Fields view (of the System Fieldsets). To view only the extracted columns, select **User Defined Fieldsets** from the System Fieldsets list.

Examples

```
...| cef categorySignificance agentType
```

```
...| cef deviceEventCategory name
```

chart

Displays search results in a chart form of the specified fields.

Synopsis

```
...| chart count by <field1> <field2> <field3> ... [span [<time_<br>field>]=<time_bucket>]
```

```
...| chart {{sum | avg | min | max | stdev | perc<N>}} (<field>))+ by<br><field1>, <field2>, <field3> ...[span [<time_field>]= <time_bucket>]
```

```
...| chart {<function> (<field>)} as <new_column_name> by <field> [span<br>[<time_field>]=<time_bucket>]
```

where <field>, <field1>, <field2> are the names of the field that you want to chart. The fields can be either event fields available in the Logger schema or a user-defined fields created using the **rex** or **eval** operator prior in the query.

<time> is the bucket size for grouping events. Use d for day, h for hour, m for minute, s for seconds. For example, 2h, 5d, 1m. (See Usage Notes for details.)

<function> is one of these: **count**, **sum**, **avg (or mean)**, **min**, **max**, **stdev**, **percN**

<new_column_name> is the name you want to assign to the column in which the function's results are displayed. For example, **Total**.


<N> is the percentile, and so can be a number between 0 and 100, inclusive.

Deprecated: The following deprecated usage contains “_count”. The recommended usage, as shown above, is “count”.

```
...| chart _count by <field1> <field2> <field3> ...
```

Usage Notes

By default, a column chart is displayed. Other chart types you can select from: bar chart, line chart, donut chart, area chart, stacked column, or stacked bar.

To change the chart settings (including its type), click  in the upper right corner of the Result Chart frame of the screen. You can change these settings:

- **Title:** Enter a meaningful title for the chart.
- **Type:** Column, Bar, Donut, Area, Line, Stacked column, Stacked Bar. The last two types create stacked charts in which multiple values are plotted in a stack form. These charts are an alternate way of representing multi-series charts, which are described below.
- **Display Limit:** Number of unique values to plot. Default: 10

If the configured Display Limit is less than the number of unique values for a query, the top values equal to the specified Display Limit are plotted. That is, if the Display Limit is 5, and seven unique values are found, only the top five values will be plotted.

All chart commands except “**count by**” accept only *one field* in the input. The specified field must contain numeric values.

If multiple fields are specified, separate the field names with a white space or a comma.

You can click on a charted value to quickly filter down to events with specific field values. For more information, see ["Chart Drill Down" on page 129](#).

Percentile Function

The **perc<N>** function returns the **<N>** percentile. **<N>** can be a number between 0 and 100, inclusive.

...| chart perc by field list" (with no specified **<N>**) returns all results generated by **...| chart count by field list**.

...| chart perc50 by field list returns the median value of all the results generated by **...| chart count by field list**.

...| chart perc90 by field list returns the 90 percentile value of all the results generated by **...| chart count by field list**.

The percentile value is derived based on the increasing order of the field values. The derived value of string fields rely on alphabetical order (ASCII value).

Aggregation Functions

Note: Aggregation functions only work on numeric fields. The specified fields must contain numeric values. If a field you specify is of the wrong data type, you will receive an error message like the following: **"java.lang.NumberFormatException"**.

If an aggregation function such as **count**, **sum**, or **avg** is specified, a chart of the aggregated results is displayed along with the tabular results of the aggregation operation in a Results Table. For example, for the aggregation function **sum(deviceCustomNumber1)**, the **sum_deviceCustomNumber1** column in the Results Table displays the sum of unique values of the **deviceCustomNumber1** field.

If this field had two unique values 1 and 20, occurring 2 times each, the **sum_deviceCustomNumber1** column displays sum of those two values.

Note: When a chart displays too many events, it can be difficult to read. Therefore, the number of events returned is limited to 500 by default. If you need to change that default number, please contact Customer Support.

The mathematical operators **avg** and **mean** are equivalent.

You can include multiple functions in the same **chart** command. When doing so, separate each function with a comma, as shown in this example:

```
...| chart count, sum(deviceCustomNumber3) by deviceEventClassId
```

When you include multiple functions, one column per function is displayed in the search Results Table. The Results Chart, however, plots the chart for the field specified in the "by" clause.

You can use the "as new_column_name" clause to name any column resulting from the aggregation functions, as shown in this example:

```
...| chart sum(deviceCustomNumber3) as TotalStorage, avg(deviceCustomNumber3) as AverageStorage by deviceCustomNumber3
```

Once defined, the newly defined column can be used in the pipeline as any other field. For example,

```
...| chart sum(deviceCustomNumber3) as TotalStorage, avg(deviceCustomNumber3) as AverageStorage by deviceCustomNumber3 | eval UpdatedStorage = TotalStorage + 100
```

When you export the search results of a chart operator, the newly defined column name (using the **chart function as new_column_name** command) is preserved.

Multi-Series Charts

A multi-series chart can plot the values of multiple aggregation functions in a single chart. If you include multiple aggregation functions in a **chart** command, Logger generates a multi-series chart that plots the values of the specified aggregation functions along the Y-axis, as illustrated in ["chart" on page 525](#). Multi-series charts can be any of the chart types except Donuts. For example, you can choose to plot a multi-series chart as a stacked chart—Stacked column or Stacked Bar—in which multiple values are plotted in a stack form.

The Span Function

In addition to grouping events by the Logger schema fields (or the ones defined by the **rex** or **eval** operators), the **span** function provides an additional way to group events by a time field (such as `EventTime` or `deviceReceiptTime`) and a time bucket. In the following example, `deviceReceiptTime` is the time field and `5m` (5 minutes) is the time bucket:

```
...| chart count by deviceEventCategory span (deviceReceiptTime) = 5m
```

If a time field is not specified for the **span** function, **EventTime** is used as the default. For example, the following query uses `EventTime` by default:

```
...| chart count by deviceEventCategory span = 5m
```

By default, the **chart** command displays the first 10 unique values. If the **span** function creates more than 10 unique groups, not all of them will be displayed. If you want to view all of the unique groups, increase the Display Limit value under Chart Settings. (Click in the upper right corner of the Result Chart frame of the screen.)

Grouping with **span** is useful in situations when you want to find out the number of occurrences in a specific time span.

If you want to find out the total number of incoming bytes every 5 minutes on a device, you can specify a span of `5m`, as shown in this example:

```
...| chart sum(deviceCustomNumber1) span=5m
```

The above example assumes that `deviceCustomNumber1` field provides the incoming bytes information for these events.

The **span** field can be used for grouping in conjunction with or without the event fields that exist in Logger schema or user-defined fields using the **rex** or **eval** operators. When a **span** field is specified in conjunction with an event field, the unique sets of all those fields is used for grouping. The following example uses **deviceCustomNumber3** and **deviceAddress** in conjunction with **span** to find out the number of events (using `deviceCustomNumber3`) from a specific source (using `deviceAddress`) in one hour:

```
...| chart sum(deviceCustomNumber3) by deviceAddress span=1h
```

When **span** is included in a query, search results are grouped by the specified time bucket. For example, if `span=5m`, the search results will contain one row for each 5-minute span. If there are no events within a specific 5-minute span, that row will be empty.

Additionally, the **span** function assumes a 24-hour day, all year long. If `span=1d` or `24h`, on the day of daylight savings time change, the event time indicated by the `span_eventTime` field in the search results will be different from the previous day by one hour. On the day when there are 23 hours in a day (in March), the span bucket will still include events from the last 24 hours. Similarly, on the day when there are 25 hours in the day (in November), the span bucket will include events from the last 24 hours.

dedup

Removes duplicate events from search results. That is, events that contain the same value in the specified field. The first matching event is kept, and the subsequent events with the same value in the specified field are removed.

Synopsis

```
... | dedup [N] <field1>,<field2>, ... [keepevents=(true|false)] [keepempty=(true|false)]
```

N is an optional number that specifies the number of duplicate events to keep. For example, “`dedup 5 deviceEventClassId`” will keep the first five events containing the same `deviceEventClassId` values for each `deviceEventClassId`, and remove the events that match after the first five have been kept. Default: **1**

field1, **field2** is a field or a comma-separated field list whose values are compared to determine duplicate events. If a field list is specified, the values of the unique sets of all those fields are used to remove events. For example, if `name` and `deviceCustomNumber1` are specified, and two events contain “Network Usage - Outbound” and “2347896”, only the first event is kept in the search results.

keepevents specifies whether to set the fields specified in the field list to NULL or not. When this option is set to `True`, the values are set to NULL and events are not removed from search results. However, when this option is set to `False`, duplicate events are removed from the search results. Default: `False`.

keepempty specifies whether to keep events in the search results whose specified fields contain NULL values. When this option is set to `True`, events with NULL values are kept, however if this option is set to `False`, events with NULL values are removed. Default: `False`.

Example One

To view events from unique devices:

```
... | dedup deviceAddress
```

Example Two

To view unique deviceEventClassId events from unique devices:

```
... | dedup deviceEventClassId deviceAddress
```

Example Three

To view the className in events with Java exceptions in the **message** field:

```
exception | <rex_expression> | dedup 5 className
```

In the example above, **<rex_expression>** is not shown in detail; however this expression extracts the class name in a field called className, which the dedup operator acts upon.

eval

Displays events after evaluating the result of the specified expression. The expression can be a mathematical, string, or Boolean operation and is evaluated when the query is run. The resulting value of the expression is assigned to a field name (specified in the expression). Once a new field has been defined by the eval operator in a query, this field can be used in the query for further refining the search results (see ["Example Three" on page 535](#) below, in which a new field "Plus" is defined by the eval operator; this field is then used by the sort operator.)

Synopsis

```
...|eval <type> <newField>=function([<field>|<value>]*)
```

Where:

<newField> is a derived field displayed in the search results.

<type> is the datatype of the new field and can be **int**, **bigint**, **long**, **float** or **double**. If you do not include a data type, the default is string. Including a **<type>** is optional; include when you need some data type other than string. For example, if you do not include a type, the sort will be alphabetical. If you want to sort numerically, make **<type>** one of the number data types. The datatype you specify should match the data that will be displayed in the **<newField>**, according to standard datatype definitions. The temporary field is not part of the Logger schema and its data type does not have to match the Logger schema data type of **<field>**.

<function> is one of these: **abs(X)**, **case(X,"Y",...)**, **ceil(X)**, **ceiling(X)**, **exp(X)**, **floor(X)**, **if(X,Y,Z)**, **isfalse(X)**, **istrue(X)**, **len(X)**, **ln(X)**, **log(X)**, **lower(X)**, **tolower(X)**, **mod(x,y)**, **rand()**, **replace(X,Y,Z)**, **round(X)**, **sqrt(X)**, **substr(X,Y,Z)**, **sum(x,y,z,...)**, **trim(X)**, **ltrim(X)**, **rtrim(X)**, **upper(X)**, **toupper(X)**, **urldecode(X)**.

Note: These functions are described in detail in the usage notes below.

<field> is the name of the field that you want to evaluate. It can be either an event field available in the Logger schema or a user-defined field created using the `rex` or `eval` operator earlier in the query.

<value> can be a string or a number.

Operators supported for eval expressions

| Operation | Symbol |
|---|-----------|
| Addition, Subtraction | +, - |
| Multiplication, Division | *, / |
| Boolean And, Or, Not | &&, , ! |
| Equal, Not Equal | ==, != |
| Less Than, Greater Than | <, > |
| Less Than or Equal, Greater Than or Equal | <=, >= |
| Modulus, Power | %, ^ |
| Unary Plus, Unary Minus | +x, -x |

Usage Notes

Typically, a `cef` or `rex` operator (to extract fields from matching events) precedes the `eval` operator, as shown in the examples below. However, you can use the `eval` operator on a field that has been defined by a previous `eval` operator in a query.

Keep the following in mind when working with eval functions:

- Functions can accept either the literal value of a string or a field.
- To indicate that X is a literal string, surround it with double quotes ("X"). If there are no double quotes, the function assumes that X is a field.
- The derived value of string fields rely on alphabetical order (ASCII value).

Functions supported for eval operations

| Function | Description | Example |
|---------------------|--|---|
| <code>abs(X)</code> | Takes a number, X, and returns its absolute value. | The function assigns the evaluated value to the new field. If the value of X is 3 or -3, the function assigns the evaluated value of 3 to the field <code>absnum</code> . <code>... eval absnum=abs(number)</code> |

Functions supported for eval operations, continued

| | | |
|---------------------|--|---|
| case(X,"Y",...) | <p>Takes pairs of arguments, X and Y.</p> <p>The X arguments are Boolean expressions that are evaluated from first to last. When case encounters the first X expression that evaluates to true, it returns the corresponding Y. Subsequent arguments are ignored. If none are true, it returns NULL.</p> | <p>The following example returns outcome =Success or outcome =Failure, depending on whether deviceCustomNumber1 is 200.</p> <pre>... eval outcome=case(deviceCustomNumber1==200, "Success", deviceCustomNumber1 != 200, "Failure")</pre> |
| ceil(X), ceiling(X) | <p>Rounds a number, X, up to the next highest integer.</p> | <p>The following example returns n=2.</p> <pre>... eval n=ceil(1.9)</pre> |
| exp(X) | <p>Takes a number, X, and returns eX.</p> | <p>The following example returns y=e3.</p> <pre>... eval y=exp(3)</pre> |
| floor(X) | <p>Rounds a number, X, down to the nearest whole integer.</p> | <p>The following example returns 1.</p> <pre>... eval n=floor(1.9)</pre> |
| if(X,Y,Z) | <p>Takes three arguments. The first argument, X, must be a Boolean expression. If X evaluates to TRUE, the result is the second argument, Y. If X evaluates to FALSE, the result evaluates to the third argument, Z.</p> | <p>The following example looks at the values of deviceCustomNumber1 and returns outcome=Succeeded if outcome=200, otherwise returns outcome=Failed.</p> <pre>... eval outcome=if(deviceCustomNumber1 == 200, "Succeeded", "Failed")</pre> |
| isfalse(X) | <p>Checks whether expression X is false. Returns true if expression X is false, otherwise returns false.</p> <p>Note: If X > 0, results are false. If X <=0, results are true.</p> | <p>The following example returns true because 4+4 is not equal to 9.</p> <pre>... eval newField = isfalse(4+4==9)</pre> |
| istrue(X) | <p>Checks whether expression X is true. Returns true if expression X is true, otherwise returns false.</p> <p>Note: If X > 0, results are true, If X <=0, results are false.</p> | <p>The following example returns true because 8 is greater than 0.</p> <pre>... eval newField = istrue(8)</pre> |

Functions supported for eval operations, continued

| | | |
|------------------------|--|--|
| len(X) | Returns the character length of a string, X. | <p>The following example returns the length of (field). If the field is 256 characters long, it returns n=256,</p> <pre>... eval n=len(field)</pre> <p>The following example returns n=3. (abc is a literal string, surrounded by double quotes.)</p> <pre>... eval n=len("abc")</pre> |
| ln(X) | Takes a number, X, and returns its natural log. | <p>The following example returns the natural log of the value of "bytes". If "bytes" contains 100, it returns 4.605170186.</p> <pre>... eval lnBytes=ln(bytes)</pre> |
| log(X) | Evaluates the log of number X with base 10. | <p>The following example returns 4.</p> <pre>... eval num=log(10000)</pre> |
| lower(X) tolower(X) | Takes a string argument, X, and returns the lowercase version. | <p>The following example returns the value of the field username in lowercase. If the username field contains FRED BROWN, it returns name=fred brown.</p> <pre>... eval name=lower("username")</pre> |
| mod(X,Y) | Returns the modulo of X and Y. (X%Y; the remainder of X divided by Y.) | <p>The following example returns 5.</p> <pre>... eval newField = mod(25,10)</pre> |
| rand() | Returns a random number between 0 and 1, inclusively. | <p>The following example might return a number like 0.56789.</p> <pre>... eval newField = rand()</pre> |
| replace(X,Y,Z) | Returns a string formed by substituting string Z for every occurrence of regex string Y in string X. The third argument, Z, can also reference groups that are matched in the regex. | <p>The following example replaces instances of the value "ArcSight" with the value "Micro Focus" in the deviceVendor field.</p> <pre>... eval n=replace(deviceVendor, "ArcSight", "Micro Focus")</pre> |
| round(X) | Rounds X to the nearest integer. | <p>The following example returns 1.</p> <pre>... eval n=round(1.4)</pre> <p>The following example returns 2.</p> <pre>... eval n=round(1.5)</pre> |
| sqrt(X) | Takes one numeric argument, X, and returns its square root. | <p>The following example returns 3.</p> <pre>... eval n=sqrt(9)</pre> |

Functions supported for eval operations, continued

| | | |
|---------------------------------|--|---|
| substr(X,Y,Z) | <p>This function returns a new string that is a substring of string X. The substring begins with the character at index Y and extends up to the character at index Z-1.</p> <p>Note: The index is a number that indicates the location of the characters in string X, from left to right, starting with zero.</p> | <p>The following example returns "g".</p> <pre>... eval n=substr("ArcSight",5,6)</pre> <p>The following example returns "cSig".</p> <pre>... eval n=substr("ArcSight",2,6)</pre> <p>The following example returns "ght".</p> <pre>... eval n=substr("ArcSight",5,8)</pre> <p>The following example returns "ArcSight".</p> <pre>... eval n=substr("ArcSight",0,8)</pre> <p>The following example returns "Sight".</p> <pre>... eval n=substr("ArcSight",3,8)</pre> <p>The following example returns "Arc".</p> <pre>... eval n=substr("ArcSight",0,3)</pre> |
| sum(X,Y,Z,...) | Adds all the numbers together. | <p>The following example returns the sum of the values in the baseEventCount, deviceCustomNumber1, and deviceCustomNumber2 fields.</p> <pre>... eval newnum = sum(baseEventCount, deviceCustomNumber1, deviceCustomNumber2)</pre> |
| trim(X) ltrim(X) rtrim(X) | <p>trim(X) removes all spaces from both sides of the string X.</p> <p>ltrim(X) removes all spaces from the left side of the string X.</p> <p>rtrim(X) removes all spaces from the right side of the string X.</p> | <p>For the sake of the example, assume that X is a literal string and _ represents any number of space characters.</p> <p>The following example returns trimmed="string_".</p> <pre>... eval trimmed=ltrim("_string_")</pre> <p>The following example returns trimmed="_string".</p> <pre>... eval trimmed=rtrim("_string_")</pre> <p>The following example returns "string".</p> <pre>... eval trimmed=trim("_string_")</pre> |
| upper(X) toupper(X) | Takes one string argument and returns the uppercase version. | <p>The following example returns the value of the field username in uppercase. If username contains fred brown, it returns name=FRED BROWN.</p> <pre>... eval name=upper("username")</pre> |
| urldecode(X) | Takes one URL string argument X and returns the unescaped or decoded URL string. | <p>The following example returns "http://www.microfocus.com/download?r=header".</p> <pre>... eval n=urldecode("http%3A%2F%2Fwww.microfocus.com%2Fdownload%3Fr%3Dheader")</pre> |

Example One

If the Category Behavior is "Communicate", then assign the value "communicate" to a new field "cat"; otherwise, assign the value "notCommunicate" to it.

```
_storageGroup IN ["Default Storage Group"] | cef categoryBehavior | eval  
cat=if(categoryBehavior== "/Communicate", "communicate", "notCommunicate")
```

Example Two

Append the word, "END", at the end of extracted event name. For example, if event name is "Logger Internal Event", after the eval operation it is "Logger Internal EventEND" and is assigned to a new field, "fullname".

```
logger | cef msg name | eval fullname=name + "END"
```

Example Three

Add 100 to the value of bytesIn and assign it to a new field, "Plus". Then, sort the values assigned to "Plus" in ascending order.

```
_storageGroup IN ["Default Storage Group"] | cef bytesIn bytesOut name | eval  
Plus=bytesIn +100 | sort Plus
```

Example Four

Find the longest URLs from the vendor ArcSight.

```
deviceVendor = ArcSight |eval (int)urllength=len(requestUrl) |sort urllength
```

extract

Extracts key value pairs from raw events.

Synopsis

```
...| extract [pairdelim="<delimiters>"] [kvdelim="<delimiters>"] [maxchars=<n>]  
fields="key1,key2,key3..."
```

Where:

- **pairdelim** is a delimiter (or a list of delimiters) that separates one key-value pair from another key-value pair in an event. By default, semi colon, pipe, and comma (; |,) are used.
- **kvdelim** is a delimiter (or a list of delimiters) that separates a key from its value. By default, "=".
- **maxchars** is the maximum number of characters in an event that would be scanned for extracting key value pairs. By default, 10240.
- **fields** is a key (or a list of comma-separated keys) whose values you want to display in the search results.

For example, if you want to display the Name Age, and Location values from this event:

Name:Jane | Age:30 | Location:LA

extract the “Name”, “Age”, and “Location” keys and list them in the **fields** list.

Understanding How the Extract Operator Works

The key represents a field in the raw event and its value consists of the characters that appear after the key until the next key in the event. The following raw event is used to illustrate the concept:

```
[Thu Jul 30 01:20:06 2009] [error] [client 69.63.180.245] PHP Warning:  
memcache_pconnect() [pconnect</a>]: Can't connect to 10.4.31.4:11211
```

To extract the URL from the above event, you can define these key-pair delimiters, which separate the key-value pairs in the event:

- Greater than sign (>)
- Square bracket ([)

And, define this key delimiter, which separates the key from its value:

- Equal to sign (=)

Thus, the following command will extract the URL:

```
... | extract pairdelim= ">\" kvdelim= "=" fields="<a href"
```

The key value pairs in the event will be: [

The key in the event will be: <a href

The extracted URL will be: 'function.memcache-pconnect'

Usage Notes

This operator only works on raw events. That is, you cannot extract key value pairs from CEF events or the fields defined by the **rex** operator.

You can specify the **pairdelim** and **kvdelim** delimiters in the extract operator command to extract keys and their values. However, if you want to determine the key names that these delimiters will generate, use the **keys** operator as described in ["keys" on page 538](#). The **keys** operator can only be used to determine keys; you cannot pipe those keys in the **extract** operator. That is, ...| **keys | extract fields=field1** is incorrect.

The keys specified in the fields list can be used further in the pipeline operations. For example, ...| **extract pairdelim= "|" kvdelim= ":" fields= "count" | top count**

If none of the specified **pairdelim** characters exists in an event, the event is not parsed into key value pairs. The whole event is skipped. Similarly, if the specified **kvdelim** does not exist, values are not separated from the keys.

To specify double quotes (") as the delimiter, enter it within the pair of double quotes with backslash(\) as the escape character. For example, "\"". Similarly, use two backslashes to treat a backslash character literally. For example, "\\".

Example

```
... | extract pairdelim= "|" kvdelim= ":" fields= "Name, Age, Location"
```

Extracts values from events in this format:

Name:Jane | Age:30 | Location:LA

fields

Includes or excludes specified fields from search results.

Synopsis

```
... | fields ([(+ | -)] <field>)+
```

Where:

- + includes only the specified field or fields in the search results. This is the default.
- excludes only the specified field or fields from the search results.

Usage Notes

Typically, the <field> list contains event fields available in the Logger schema or user-defined fields created using the **rex** operator prior in the query, as shown in the examples below. However, fields might also be defined by other operators such as the **eval** operator.

The + and - can be used in the same expression when multiple fields are specified. For example:

```
| fields + name - agentType
```

Tip: A complete field name must be specified for this operator; wildcard characters in a field name are not supported.

When this operator is included in a query, select **User Defined Fieldsets** from the System Fieldsets list to view the search results.

Example One

```
... | fields - agentType + categorySignificance
```

Example Two

```
... | fields - name
```

head

Displays the first **<N>** lines of the search results.

Synopsis

```
... | head [<N>]
```

<N> is the number of lines to display. Default: **10**, if **<N>** is not specified.

Usage Notes

When this operator is included in a query, the search results cannot be previewed. That is, the query must finish running before search results are displayed.

Example

```
... | head
```

keys

Identifies keys in raw events based on the specified delimiters.

Synopsis

```
... | keys [pairdelim= "<delimiters>"] [kvdelim= "<delimiters>"] [limit=<n>]
```

Where:

- **pairdelim** is a delimiter (or a list of delimiters) that separates one key-value pair from another key-value pair in an event. By default, semi colon, pipe, and comma (; | ,) are used.
- **kvdelim** is a delimiter (or a list of delimiters) that separates a key from its value. By default, "=".
- **limit** is the maximum number of key value pairs to find. There is no default or maximum number for this parameter.

Usage Notes

This operator only works on raw events. That is, you cannot identify key value pairs from CEF events or fields defined by the **rex** operator.

Although this operator is not required to determine keys, it is recommended that you use it to first determine the keys whose values you want to obtain using the **extract** operator. This operator returns aggregated results. Therefore, the search results list the keys found in the matching events and their counts.

The **keys** operator can only be used to determine keys; you cannot pipe those keys in the **extract** operator. That is, **| keys | extract fields=field1** is incorrect.

If a key value is blank (or null), it is ignored and not counted toward the number of hits.

For example, for the following event data:

```
Date=3/24/2011 | Drink=Lemonade
Date=3/23/2011 | Drink=
Date=3/22/2011 | Drink=Coffee
```

Search Query `keys pairdelim= "|" kvdelim= "="`

Search Result: Date, 3 hits and Drink, 2 hits

If none of the specified **pairdelim** characters exists in an event, the event is not parsed into key value pairs. The whole event is skipped. Similarly, if the specified **kvdelim** does not exist, values are not separated from the keys.

To specify double quotes (") as the delimiter, enter it within the pair of double quotes with backslash (\) as the escape character. For example, `"=\\|"`. Similarly, use two backslashes to treat a backslash character literally. For example, `"\\"`.

Example One

```
...| keys pairdelim= "|" kvdelim= "="
```

Identifies keys (Date and Drink) in event of this format:

```
Date=3/24/2011 | Drink=Lemonade.
```

Example Two

```
...| keys pairdelim= "," kvdelim= ">="
```

Identifies keys (Path and IPAddress) in the event of this format:

```
Path>c:\usr\log, IPAddress=1.1.1.1
```

lookup

Returns an augmented or filtered set of events based on whether they have identical values in the corresponding fields in an uploaded Lookup file.

Before you can use this operator, you must upload a Lookup file to Logger. You can add a Lookup file by uploading a CSV file from the **List Lookup** configuration page.


- For information on when to use the **lookup** operator, see ["Enriching Logger Data Through Static Correlation" on page 146](#).
- For information about creating Lookup files and uploading them to Logger, see ["Lookup Files" on page 336](#).

Synopsis

```
... | lookup [+/-/*] lookupTableName externalField1 [as loggerField1] [,  
externalField2 [as loggerField2] ...] [output [ * | externalField1,  
externalField2... ] ]
```

The plus sign (+) selects events where the value in the Lookup field (loggerField1, loggerField2) is identical with that in the uploaded Lookup file (externalField1, externalField2). When the output clause is used, it augments the search results with the specified output columns from in the uploaded Lookup file. + is the default **lookup** operator. If you do not specify +, -, or *, + is used.


Logger Events "AND" External Events



When a Lookup field value matches multiple rows in the uploaded Lookup file, only the first matched row is used. Logger displays an alert message indicating that the Lookup field contains multiple matches in the Lookup file, and that only the first match is included.


The minus sign (-) selects events where the value in the Lookup field is not in the uploaded Lookup file. When you do a lookup with negation, the results will not display the external fields in the UI fields. The output clause is not applicable for negative lookup. This is because the negative lookup **excludes** matches from the uploaded lookup file.

Logger Events "NOT IN" External Events



The asterisk (*) includes all events regardless of whether they are in the uploaded Lookup file. (Performs a left-outer join between the Logger events table and the Lookup file.) When the output clause is used, the output fields will be empty (null) for Logger events that do not have a match in the Lookup file.

Logger Events “LEFT JOIN” External Events



If +, -, or * is not provided, the default is +.

loggerField1 and **loggerField2** are valid field names in Logger search results.

externalField1 and **externalField2** are valid column names from the Lookup file.

loggerField1 as externalField1 looks up values between **loggerField1** in Logger search results and **externalField1** in the uploaded Lookup file.

In the first **lookup** operator in a search pipeline, **loggerField1**, must be a valid field name in a Logger event, otherwise, this field can be a Logger field or a search-generated field in the search results from the previous pipeline operator.

loggerField1 as externalField1, loggerField2 as externalField2 performs value lookup on multiple fields between Logger search results and uploaded Lookup file.

[output [* | externalField1, externalField2...]] if you specify one or more external fields, augments the search results with the indicated fields. If you use **output ***, all fields from uploaded Lookup file are added. When the output clause is not used, no fields from uploaded Lookup file are added to the search results.

Usage Notes

The lookup operator supports specific date/time formats. Logger event fields can be of three different data types, string, integer, and date/time. The **lookup** operator converts values in the Lookup fields to a value of the same data type as the corresponding Logger event field.

The lookup operator supports the following formats for date/time fields:

MM/dd/yyyy HH:mm:ss z
MM/dd/yyyy HH:mm:ss
yyyy/MM/dd HH:mm:ss z
dd/MMM/yyyy HH:mm:ss Z
dd MMM yyyy HH:mm:ss z
yyyy-M-d H:mm:ss

`yyyy-MM-dd'T'HH:mm:ss`
`yyyy-MM-dd'T'HH:mm:ssZ`

Logger allows about 1GB system memory for all lookup searches. Running multiple lookup searches simultaneously on large lookup tables could use up the 1GB memory. When this limit is reached, some lookup searches may run more slowly or may time out. If a user starts a lookup search when other lookup searches are running and the memory is full, Logger will display a message that suggests that the user runs the lookup search after the current lookup searches finish and the memory is released.

Choose Lookup fields that have unique values in the uploaded Lookup file. The lookup operation only uses the first row that matches and ignores any subsequent matches. Therefore, it is best to have unique values in the lookup column and avoid having duplicate matches ignored.

As an example, look at the following search.

| lookup testLU deviceVendor output status

where the Lookup file "testLU" contains four rows with same deviceVendor value, "ArcSight", as shown below.

testLU

| deviceVendor | dept | org |
|--------------|-------------|-------------|
| ArcSight | sales | Micro Focus |
| ArcSight | marketing | Micro Focus |
| BlueCoat | sales | BlueCoatINC |
| ArcSight | engineering | Micro Focus |
| ArcSight | marketing | ESP |

When the lookup operation finds duplicates in the Lookup field, ("deviceVendor=ArcSight" in testLU and "deviceVendor=ArcSight" in the Logger events table), the search results use only the first entry, "status_testLU=ok" to augment the matching Logger event, while subsequent matches, such as "status_testLU=alert", are NOT used.

Tip: In some rare situations, a blank page may be returned after you upload a Lookup File from the Add Lookup File page. If this happens, refresh the page manually. After the refresh, you are returned to the loading page and the process tries to load the Lookup File again. Since the file was already uploaded, you get an error message. You can safely ignore the error.

Using IP Addresses in Lookup Files

The Lookup process automatically determines whether the Lookup file consists of IP addresses, and if so treats them as IP addresses rather than strings. When performing a search using a Lookup file, Logger checks the first ten rows of each Lookup column to determine whether it contains only IP addresses.

- If a Lookup column contains only IP addresses in the first ten rows, Logger assumes that the rest of rows in that column contain IP addresses.

Note: Including non-IP address data later in the same column may cause an exception.

- If the first ten rows contain strings that are not IP addresses, Logger uses the field type of the corresponding Logger event column to determine the data type.
- If the Lookup process determines that it's an IP address lookup based on the above rule, the search will find matching IP addresses in any equivalent IP address format.

For example, if your Lookup column has some things that are not IP addresses in the first ten rows:

- Searching for the string "2001:db8:250:0:0:fefe:0:1" would find only events where the target field is the exact string "2001:db8:250:0:0:fefe:0:1"
- Searching for the string "192.168.10.100" would find only events where the target field is the exact string "192.168.10.100".

Whereas, if your Lookup file has only IP addresses in the first ten rows:

- Searching for the address "192.0.2.010" could find events with addresses such as: "192.0.2.010" and "192.0.2.10".
- Searching for the address "2001:db8:250:0:0:fefe:0:1" could find events with addresses such as: "2001:db8:250:0:0:fefe:0:1" and "2001:db8:250::fefe:0000:1".

Note: For more information about including IPv6 address data in Logger and searching for it, see ["Sending IPv6 Data to Logger" on page 32](#) and ["Searching for IPv6 Addresses" on page 120](#).

Example One

The following example looks up events where the sourceAddress comes from the IP address listed in a lookup file named "maliciousIP" under the column named "ip".

```
lookup maliciousIP ip as sourceAddress
```

Example Two

The following example looks up access events with a sourcePort different from the sourcePort in day_x, where day_x is the lookup file generated from the exported Logger events on a day before.

```
access | lookup - day_x sourcePort
```

parse

Applies the named parser to the matching events of a search query.

Synopsis

```
... | parse <parser_name>
```

Where **<parser_name>** is the name of the parser to use. For information on how to create a parser, see ["Working with Parsers" on page 373](#).

Tip: The parser must exist before it can be used in a query.

The **parse** operator is useful in parsing the non-CEF (unstructured textual) data stored on Logger and parsing it into specific fields according to the parser's definition.

Once parsed into fields, this data can be used further in search operations. For example, the following **parse** operator parses the events using a user-defined parser "Web Server Access Logs" such that "username", "login_status", "num_attempts" fields are created.

You can use these created fields further in a pipeline query to display the top 10 user names that resulted in the maximum failed login attempts and the number of attempts they made.

```
... | parse Web Server Access Log | where login_status = "failed" | top  
username num_attempts
```

Because the parser definitions are **rex** or **extract** expressions, they create additional fields to contain values that match the specified expression. These fields are displayed in the Search Results just like the results of any **rex** or **extract** expression. Therefore, in the above example, three additional fields will be added to the Search Result: username, login_status, num_attempts.

An additional field called "parser" is also added to the Search Results when the **parse** operator is used in a search query.

This field contains the name of the parser when the parser is able to parse one or more fields specified in the definition for the matching events. If the event was not parsed successfully, if no parser is defined for the source type, or if there is no source type, this field displays, this field contains "Not parsed". Similarly, the field contains the value "not parsed" when the parser definition is not able to parse any fields of the matching event.

Example

You can also use this field to find out events that were successfully parsed or did not parse:

```
... | parse Web Server Access Log | where parser = "not parsed"
```

Usage Notes

When to use the parse operator: When non-CEF events are received through TCP or UDP receivers on Logger, they are not associated with a source type and thus a parser definition. Therefore, such events not parsed automatically. Similarly, non-CEF events stored on Logger version 5.2 or earlier are not parsed since the parser feature did not exist in those versions. If you need such events parsed when they match a query, use the **parse** operator.

When an event for which a defined source type exists on Logger is parsed through the **parse** operator, it can result in the creation of multiple user-defined fields—through the parser associated with the source type and through the parser you specified in the **parser** pipeline command. If both parsers create unique field names, all those fields are created when a query that matches the event is run. If the parsers specify one or more same name fields, the field names specified in the **parse** operator parser take precedence as this parser is applied last.

Example

```
...| parse Web Server Access Log | where url CONTAINS ".org" | top url
```

rare

Lists the search results in a tabular form of the least common values for the specified field. That is, the values are listed from the lowest count value to the highest.

When multiple fields are specified, the count of unique sets of all those fields is listed from the lowest to highest count.

Synopsis

```
...| rare <field1> <field2> <field3> ...
```

Sorts the matching results from least to most common for the specified fields.

Usage Notes

Typically, the <field> list contains event fields available in the Logger schema or user-defined fields created using the **rex** or **eval** operators prior in the query, as shown in the examples below. However, fields might also be defined by other operators such as the **eval** operator.

A chart of the search results is automatically generated when this operator is included in a query. You can click on a charted value to quickly filter down to events with specific field values. For more information, see ["Chart Drill Down" on page 129](#).

If multiple fields are specified, separate the field names with a white space or a comma.

Example

```
... | rare deviceEventCategory
```

regex

Selects events that match the specified regular expression.

Synopsis

```
...| regex <regular_expression>
```

OR

```
...| regex <field> (=|!=) <regular_expression>
```

Usage Notes

Regular expression pattern matching is case insensitive.

The first usage (without a field name) is applied to the raw event. While the second usage (with a field name), is applied to a specific field.

If you use the second usage (as shown above and in the second example, below), either specify an event field that is available in the Logger schema or a user-defined field created using the **rex** or **eval** operators.

Examples

```
... | regex "failure"
```

```
... | regex deviceEventCategory != "fan"
```

rename

Renames the specified field name.

Synopsis

```
...| rename <field> as <new_name>
```

Where:

- **<field>** is the name of an event field that is available in the Logger schema or a user-defined field created using the **rex** or **eval** operator.

- **<new_name>** is the new name you want to assign to the field.

Usage Notes

An additional column is added to the search results for each renamed field. The field with the original name continues to be displayed in the search results in addition to the renamed field. For example, if you rename `deviceEventCategory` to `Category`, two columns are displayed in the search results: `deviceEventCategory` and `Category`.

You can include the wildcard character, `*`, in a field name. However, you must enclose the field that contains a wildcard character in double quotes (`" "`). For example:

```
...| rename "*IPAddress" as "*Address"
```

OR

```
...| rename "*IPAddress" as Address
```

If a field name includes a special character (such as `_`, a space, `#`, and so on), it should be included in double quotes (`" "`) in the **rename** operator expression. For example:

```
...| rename src_ip as "Source IP Address"
```

If the resulting field of a **rename** operation includes a special character, it must be enclosed in double quotes (`" "`) whenever you use it in the pipeline operator expression. For example,

```
...| rename src_ip as "Source IP Address" | top "Source IP Address"
```

The internal field names (that start with `"_raw"`) cannot be renamed.

The renamed fields are valid only for the duration of the query.

The resulting field of a **rename** operation is case sensitive. When using such a field in a search operation, make sure that you use the same case that was used to define the field.

When you export the search results of a search query that contains the **rename** expression, the resulting file contains the renamed fields.

Example

```
...| rename src_ip as IPAddress
```

```
...| rename src_ip as "Source IP Address"
```

replace

Replaces the specified string in the specified fields with the specified new string.

Synopsis

`<orig_str> with <new_str> [in <field_list>]`

Where:

- `<orig_str>` is the original string you want to replace.
- `<new_str>` is the new string you want to replace with.
- `<field_list>` is the optional, however highly recommended.

Usage Notes

Tip: Even though the field list is optional for this command, Micro Focus strongly recommends that you specify the fields on which the **replace** operator should act in this command.

If you skip the field list, the **replace** operator acts on the fields that have been either explicitly defined using the **cef**, **rex**, and **eval** operators preceding the **replace** command, or any fields that were used in other operator commands that preceded the **replace** operator command.

For example, the **replace** command acts on **deviceEventCategory** in all of the following cases and replaces one instance of “EPS” with “Events”:

```
...| replace *EPS* with *Events* in deviceEventCategory
...| cef deviceEventCategory | replace *EPS* with *Events*
...| top deviceEventCategory | replace *EPS* with *Events*
```

To replace the entire string, specify it in full (as it appears in the event). For example, “192.168.35.3”. To replace part of the string, include wildcard character (*) for the part that is not going to change. For example, if the original string (the string you want to replace) is “192.168*”, only the 192.168 part in an event is replaced. The remaining string is preserved. As a result, if an event contains 192.168.35.3, only the first two bytes are replaced. The rest (35.3) will be preserved. Similarly, if the event contains 192.168.DestIP, DestIP will be preserved. However, if the event contains the string 192.168, it will not be replaced.

If both, the original and the new strings contain wildcard characters, the number of wildcard characters in the **original** string must match the number of wildcard characters in the **new** string.

```
...| replace “*.168.*” with “*.XXX.*”
```

If the original or the new string includes a special character such as / or ?, enclose the string in double quotes (“”):

```
...| replace “/Monitor” with Error
```


You can replace multiple values for multiple fields in a single operation by separating each expression with a comma (,). Note that you must specify the field list after specifying the “with” expression for all values that you want to replace, as shown in the following example:

```
...| replace "Arc*" with Micro Focus, "cpu:100" with EPS in deviceVendor,  
deviceEventClassId
```

The original string is case-insensitive. Therefore, the string “err” will replace an event that contains “Err”.

Example One

Replace any occurrence of “a” with “b” but the characters preceding “a” and succeeding it are preserved.

```
...| replace *a* with *b*
```

Example Two

Replace any occurrence of “a” with “b” without retaining any characters preceding or succeeding “a”.

```
...| replace *a* with b in name
```

rex

Extracts (or capture) a value based on the specified regular expression or extract and substitute a value based on the specified “sed” expression. The value can be from a previously specified field in the query or a raw event message.

Synopsis

```
... | rex <regular_expression containing a field name>
```

Or

```
... | rex field = <field> mode=sed “s/<string to be  
substituted>/<substitution value>”
```

Understanding How Extraction Works

When the value is extracted based on a regular expression, the extracted value is assigned to a field name, which is specified as part of the regular expression. The syntax for defining the field name is

?<fieldname>, where **fieldname** is a string of alphanumeric characters. Using an underscore (“_”) is not recommended.

For example, use the following event to illustrate the power of rex.

```
[Thu Jul 30 01:20:06 2009] [error] [client 69.63.180.245] PHP Warning: Can't  
connect to 10.4.31.4:11211
```

If you want to extract any IP address from the above event and assign it to a field called **IP_Address**, specify the following rex expression:

```
| rex "(?<IPAddress>\d{1,3}\.\d{1,3}\.\d{1,3}\.\d{1,3})"
```

However, if you wanted to extract the IP address after the word "client" from the following event and assign it to a field called **SourceIP**, you will need to specify a start and end point for IP address extraction, so that the second IP address in the event is not captured. The starting point in this event can be **[client** and the end point can be **]**. Thus, the rex expression will be:

```
| rex "\[client (?<SourceIP>[^\]]*)"
```

In this rex expression **?<SourceIP>** is the field name defined to capture IP address and **client** specifies the text or point in the event AFTER which data will be extracted. The **[^\]]*** expression will match every character that is not a closing right bracket, therefore, for our example event, the expression will match until the end of the first IP address and not the second IP address that appears after the word "to" in the event message.

Understanding How Substitution Works

When the **rex** operator is used in **sed** mode, you can substitute the values of extracted fields with the values you specify. For example, if you are generating a report of events that contain credit card numbers, you might want to substitute the credit card numbers to obfuscate the real numbers.

The substitution only occurs in the search results. The actual event is not changed.

In the following example, the credit card numbers in the CCN field are substituted with "xxxx", thus obfuscating sensitive data:

```
| rex field=CCN mode=sed "s/*/xxxx/g"
```

The **/g** at the end of the command indicates a global replace, that is, all occurrences of the specified pattern will be replaced in all matching events. If **/g** is omitted, only the first occurrence of the specified pattern in each event is replaced.

Multiple substitutions can be performed in a single command, as shown in the following example. In this example, the word "Authentication" is substituted with "xxxx" globally (for all matching events), the first byte of the agent address that start with "192" is substituted with "xxxx" and an IP address that starts with "10" is substituted with "xxxx".

```
| rex field=msg mode=sed "s/Authentication/xxxx/g" | rex field=agentAddress  
mode=sed "s/192/xxxx/g" | rex field=dst mode=sed "s/10.*/xxxx/g"
```

Usage Notes

A detailed tutorial on the **rex** operator is available at ["Using the Rex Operator" on page 563](#).

A Regex Helper tool is available for formulating regular expressions of fields in which you are interested. The Regex Helper parses an event into fields. Then, you select the fields that you want to include in the rex

expression. The regular expression for those fields is automatically inserted in the Search box. For detailed information on the Regex Helper tool, see ["Regex Helper Tool" on page 103](#).

The extracted values are displayed as additional columns in the All Fields view (of the System Fieldsets). To view only the extracted columns, select **User Defined Fieldsets** from the System Fieldsets list. In the above example, an additional column with heading "SourceIP" is added to the All Fields view; IP address values extracted from events are listed in this column.

If you want to use other search operators such as fields, sort, chart, and so on to refine your search results, you must first use this operator to extract those fields.

Example One

The following example extracts name and social security number from an event that contains data in **name:John ssn:123-45-6789** format and assigns them to **Name** and **SSN** fields:

```
... | rex "name: (?<Name>.*) ssn: (?<SSN>.*)"
```

Example Two

The following example extracts URLs from events and displays the top 10 of the extracted URLs:

```
... | rex "http://(?<URL>[^\ ]*)" | top URL
```

Example Three

The following example substitutes the last four digits of social security numbers extracted in the first event with xxxx:

```
... | rex field=SSN mode=sed "s/-\d{4}/-xxxx/g"
```

sort

Sorts search results as specified by the sort criteria.

Synopsis

```
... | sort [<N>] ((+ | -) field)+
```

Where:

- The plus sign (+) sorts the results by specified fields in ascending order. This is the default.
- The minus sign (-) sorts the results by specified fields in descending order.
- <N> keeps the top **N** results, where **N** can be a number between 1 and 10,000. Default: 10,000.

Usage Notes

Typically, the **<field>** list contains event fields available in the Logger schema or user-defined fields created using the **rex** operator prior in the query. However, fields might also be defined by other operators such as the **eval** operator.

Sorting is based on the data type of the specified field.

When multiple fields are specified for a sort operation, the first field is used to sort the data. If there are multiple same values after the first sort, the second field is used to sort within the same values, followed by third field, and so on. For example, in the example below, first the matching events are sorted by “cat” (device event category). If multiple events have the same “cat”, those events are further sorted by “eventId”.

When multiple fields are specified, you can specify a different sort order for each field. For example, `| sort + deviceEventCategory - eventId`.

If multiple fields are specified, separate the field names with a white space or a comma.

Sorting is case-sensitive. Therefore, “Error:105” will precede “error:105” in the sorted list (when sorted in ascending order).

When a sort operator is included in a query, only the top 10,000 matches are displayed. This is a known limitation and will be addressed in a future Logger release.

When this operator is included in a query, the search results cannot be previewed. That is, the query must finish running before search results are displayed.

Example

```
... | sort deviceEventCategory eventId
```

tail

Displays the last <N> lines of the search results.

Synopsis

```
...| tail [<N>]
```

Where:

<N> is the number of lines to display. Default: **10**, if **<N>** is not specified.

Usage Notes

When this operator is included in a query, the search results cannot be previewed. That is, the query must finish running before search results are displayed.

Example

```
... | tail 5
```

top

Lists the search results in a tabular form of the most common values for the specified field. That is, the values are listed from the highest count value to the lowest.

Synopsis

```
...| top [<N>] <field1> <field2> <field3> ...
```

<N> limits the matches to the top *n* values for the specified fields. Default: 500, if <N> is not specified.

Usage Notes

The fields can be either event fields available in the Logger schema or user-defined fields created using the **rex** or **eval** operators prior in the query. If multiple fields are specified, separate the field names with a white space or a comma.

When multiple fields are specified, the count of unique sets of all those fields is listed from the highest to lowest count.

A chart of the search results is automatically generated when this operator is included in a query. You can click on a charted value to quickly filter down to events with specific field values. For more information, see ["Chart Drill Down" on page 129](#).

To limit the matches to the top *n* values for the specified fields, specify a value for *n*.

The value you specify overrides the default value of 500. For example, the following query:

```
...| top 1000 deviceEventCategory
```

charts the events with the 1000 most common values in the deviceEventCategory field.

Examples

```
... | top deviceEventCategory
```

```
... | top 5 categories
```

transaction

Groups events that have the same values in the specified fields.

Synopsis

```
... | transaction <field1> <field2>... [maxevents=<number>] [maxspan=<number>  
[s|m|h|d]] [maxpause=<number>[s|m|h|d]] [startswith=<reg_exp>]  
[endswith=<reg_exp>]
```

Where:

field1, **field2** is a field or a comma-separated field list whose values are compared to determine events to group. If a field list is specified, the values of the unique sets of all those fields are used to determine events to group. For example, if host and portNum are specified, and two events contain “hostA” and “8080”, the events are grouped in a transaction.

maxevents specifies the maximum number of events that can be part of a single transaction. For example, if you specify 5, after five matching events have been found, additional events are not included in the transaction. Default: 1000

maxspan specifies the limit on the duration of the transaction. That is, the difference in time between the first event and all other events in a transaction will never be more than the specified maxspan limit. For example, if you specify maxspan=30s, the event time of all events within the transaction will be at most 30 seconds more than the event time of the first event in the transaction. Default: Unlimited

maxpause specifies the length of time by which consecutive events in a transaction can be apart. That is, this option ensures that events in a single transaction are never more than the maxpause value from the previous event in the transaction. Default: Unlimited

startswith specifies a regular expression that is used to recognize the beginning of a transaction. For example, if a transaction operator includes **startswith= “user [L|l]login”**, all events are scanned for this regular expression. When an event matches the regular expression, a transaction is created, and subsequent events with matching fields are added to the transaction.

Note: The regular expression is applied to the raw event, not to a field in an event.

endswith specifies a regular expression that is used to recognize the end of an existing transaction. That is, an existing transaction is completed when an event matches the specified “endswith” regular expression. For example, if a transaction operator includes **endswith= “[L|l]logout”**, any event being added to a transaction is checked, and if the regular expression matches the event, the transaction is completed.

Note: The regular expression is applied to the raw event, not to a field in an event.

Usage Notes

Several of the above options specify conditions to end a transaction. Therefore, when multiple end conditions are specified in a transaction operator, the first end condition that occurs will end the transaction even if the other conditions have not been satisfied yet. For example, if **maxspan** is reached but **maxevents** has not been reached, or if the **endswith** regular expression is matched but **maxevents** has not been reached.

Understanding How the Transaction Operator Works

A transaction is a set of events that contain the same values in the specified fields. The events may be further filtered based on the options described above, such as **maxspan**, **maxpause**, and so on. In addition to grouping events, the transaction operator adds these fields to each event: **transactionid**, **duration**, and **eventcount**. These fields are displayed in the Search Results as separate columns.

A **transactionid** is assigned to each transaction when the transaction completes. Transaction IDs are integers, assigned starting from 1 for the transactions (set of events) found in the current query. All events in the same transaction will have the same transaction ID.

If an event does not belong to any transaction found in the current query, it is assigned the transaction ID 0. For example, in a **transaction** operator with a **startswith** regular expression, if the first event in the pipeline does not match the regular expression, that event is not part of the transaction, and is assigned transaction ID 0.

The **duration** is the time in milliseconds of the duration of a transaction, which is the difference between the event time of the last event in the transaction and the first event in the transaction. The **duration** field for all events in a transaction is set to the duration value of the transaction.

The **eventcount** displays the number of events in a transaction.

Example One

To view source addresses accessed within a 5-minute duration:

```
... | transaction sourceAddress maxspan=5m
```

Example Two

To group source addresses by source ports and view 5 events per group:

```
...| transaction sourceAddress sourcePort maxevents=5
```

Example Three

To group users and URLs they accessed within a 10-minute duration:

```
... | transaction username startswith= "http://" maxspan=10m
```

Example Four

To view login transactions from the same session ID and source address in a 1-hour duration:

```
... | transaction sessionId sourceAddress maxspan=1h startswith= "user  
[L|l]login"
```

where

Displays events that match the criteria specified in the “where” expression.

Synopsis

```
... | where <expression>
```

<expression> can be any valid field-based query expression, as described in ["Indexed Search Portion of a Query" on page 79](#).

Usage Notes

<expression> can only be a valid field-based query expression. Arithmetic expressions or functions are not supported.

Examples

```
... | where eventId is NULL
```

```
... | where eventId=10006093313 OR deviceVersion CONTAINS "4.0.6.4924.1"
```

```
... | where eventId >=10005985569 OR categories= "/Agent/Started"
```


Appendix B: Reporting Cheatsheet

The following table serves as a useful guide for the most common activities in the Reports Section:

Business User

| Action | Step |
|---|--|
| View or execute an existing Report | <ol style="list-style-type: none"> 1. Navigate to Explorer. 2. Select the Report in specific Category. 3. Double click Quick Run the Report with the default options (default format, etc.). |
| Create a New Report | <ol style="list-style-type: none"> 1. Navigate to Design > New Report. 2. Select Query from the Select Query Object dialog. 3. Once Report is rendered with default properties, edit the Properties as needed. |
| Execute long running Reports (using background option) | <ol style="list-style-type: none"> 1. Right click report name in Explorer menu. 2. Select Run in Background operation. <p>To get the status of reports that ran in background or report's output, go to Report Status> Other Reports section.</p> |
| Run a classic report in smart format | <ol style="list-style-type: none"> 1. Right click report name in Explorer. 2. Select Run in Smart Format operation. |
| Verify Report design with limited records from DB | <ol style="list-style-type: none"> 1. From Classic > New Report, execute the Report in Preview mode. 2. From Design > New Report, execute the report. * <p>* only 200 rows with 10 columns are fetched while report creation. Actual data set is returned after the report is saved and viewed from Explorer.</p> |
| Create a Dashboard Widget | <ol style="list-style-type: none"> 1. Navigate to Design > Dashboards 2. Drag any Report on the dashboard widget. |
| Create a Report using specific Template | <ol style="list-style-type: none"> 1. Navigate to Classic > New Report. 2. Select the required template from template drop down in Data source tab. |
| Add logo in Report | <ol style="list-style-type: none"> 1. Navigate to Design > Template Style and select the desired template. 2. Click Images under Items section. 3. Upload image/logo and set position. 4. Click Save. 5. Get the logo in Report Output from the template to create report. |
| Create inbound chart | <ol style="list-style-type: none"> 1. Navigate to Design > New Report. 2. Select Query Object. 3. Add chart. 4. Uncheck Use Parent's box under Chart Properties 5. Select another query object from query object selector. 6. Use desired field from Available Fields |
| Search a specific Report object in Reporting Repository | <ol style="list-style-type: none"> 1. Open Explorer 2. Type the name or pattern in Search box and click Search |

Business User , continued

| Action | Step |
|---|--|
| View last few executed reports | 1. Navigate to Home > Recent Reports section. Note: Only the 10 most recent executed reports are displayed. |
| View scheduled reports execution status | 1. Navigate to Administration > Job Execution Status Page. |
| Create schedule | 1. Navigate to Schedule Reports 2. Click Add button. 3. Fill details and Save . |
| Disable Schedule | 1. Open Schedule Reports 2. Click green box to disable schedule. |

Administration

| Action | Step |
|---|--|
| Change log level of Reporting server | 1. Navigate to Reports > Administration > Report Configuration . 2. Change the log level and Save . |
| Copy/move/delete multiple Report Objects | 1. Navigate to Explorer . 2. Select those objects using Ctrl key and then right click for Copy/Cut/Delete operation. 3. Select destination category and right click to select Paste operation. |
| Start/Stop/Restart report process | 1. Navigate to System Admin > System > Process Status 2. Select Web/reportengine process and select button to Start/Stop/Restart . |
| Give rights to user on category or report | 1. Navigate to System Admin > User management . 2. Select user and click Edit . 3. Assign groups. |
| Get Logs | 1. Navigate to Configuration > Retrieve Logs 2. Select desired option and click Retrieve logs |
| Get signed PDF | 1. Navigate to Administration > Report Configuration . 2. Enable Sign Document and click Manage Certificate to add keystore file. 3. Upload keystore file and provide public and private key under Manage Certificate popup for desired users. 4. Also set format, operations, position and location and save the changes. |

Appendix C: Using SmartConnectors to Collect Events

Similar to ArcSight Manager, Logger uses the ArcSight SmartConnectors to collect events. SmartConnectors can read security events from many different types of devices on a network (such as firewalls and servers) and filter events of interest (and optionally aggregate them) and send them to a Logger receiver. Logger can receive structured data in the form of normalized Common Event Format (CEF) events from the SmartConnectors.

Note: To receive events containing IPv6 data, you must use SmartConnector version 7.5.0 or later.

The following topics give basic information. For details on a specific connector, refer to the configuration guide for that connector.

- [SmartMessage559](#)
- [Configuring a SmartConnector to Send Events to Logger560](#)
- [Configuring SmartConnectors to Send Events to Both Logger and an ArcSight Manager560](#)
- [Configuring SmartConnectors for Failover Destinations561](#)
- [Sending Events from ArcSight ESM to Logger561](#)

SmartMessage

SmartMessage is an ArcSight technology that provides an efficient secure channel for Common Event Format (CEF) events between ArcSight SmartConnectors and Logger.

SmartMessage provides an end-to-end encrypted secure channel using secure sockets layer (SSL). One end is an ArcSight SmartConnector, receiving events from the many supported devices. The other end is a SmartMessage receiver on Logger.

Note: The SmartMessage secure channel uses SSL protocol to send encrypted events to Logger. This is similar to, but different from, the encrypted binary protocol used between SmartConnectors and ArcSight Manager.

Configuring a SmartConnector to Send Events to Logger

Logger comes pre-configured with a SmartMessage receiver. To use it to receive events from a SmartConnector, you must configure the SmartConnector as described below. You can also create new SmartMessage receivers and configure the SmartConnectors with these newly created receivers. When configuring a SmartConnector, be sure to specify the correct receiver name.

To configure a SmartConnector to send events to Logger:

1. Install the SmartConnector component using the SmartConnector Configuration Guide for the supported device as a reference. Specify Logger as the destination instead of ArcSight Manager or a CEF file.
2. Specify the required destination parameters. Enter the Logger hostname or IP address and the name of the SmartMessage receiver. These settings must match the receiver in Logger that listen for events from this connector.
 - To use the preconfigured receiver, specify **SmartMessage Receiver** as the Receiver Name.
 - To use SmartMessage to communicate between an ArcSight SmartConnector and a Logger Appliance, configure the SmartConnector to use port 443.
 - To communicate between an ArcSight SmartConnector and Software Logger, configure the SmartConnector to use the port configured for the Software Logger.
 - For unencrypted CEF syslog, enter the Logger hostname or IP address, the desired port, and choose UDP or TCP output.

Configuring SmartConnectors to Send Events to Both Logger and an ArcSight Manager

You can configure a SmartConnector to send CEF syslog output to Logger and send events to an ArcSight Manager at the same time.

1. Install the SmartConnector normally. Register the SmartConnector with a running ArcSight Manager and test that the SmartConnector is up and running.
2. Start the SmartConnector configuration program again using the **\$ARCSIGHT_HOME/current/bin/runagentsetup** script, where **\$ARCSIGHT_HOME** refers to the SmartConnector installation directory.

3. Select **Modify Connector**, click **Next**, then select **Add, modify, or remove destinations**. Click **Next**. Select **Add destination**.
4. Choose **Logger** and specify the requested parameters. Restart the SmartConnector for changes to take effect.

Configuring SmartConnectors for Failover Destinations

SmartConnectors can be configured to send events to a secondary, failover, destination when a primary connection fails.

To configure a failover destination, follow these steps:

1. Configure the SmartConnector for the primary Logger as described above. The transport must be raw TCP in order to detect the transmission errors that trigger failover.
2. Edit the agent.properties file in the directory `$ARCSIGHT_HOME/current/user/agent`, where `$ARCSIGHT_HOME` is the root directory where the SmartConnector component was installed.
Add this property: `transport.types=http,file,cefsyslog`
Delete this property: `transport.default.type`
3. Start the SmartConnector configuration program again using the `$ARCSIGHT_HOME/current/bin/runagentsetup` script.
4. Select **Modify Connector**, click **Next**, then select **Add, modify, or remove destinations**. Make sure the Logger destination is selected and click **Next**.
5. Enter information for the secondary Logger.
6. Restart the SmartConnector for the changes to take effect.
7. For more information about installing and configuring ArcSight SmartConnectors, refer to the ArcSight SmartConnector User's Guide, or specific SmartConnector Configuration Guides, available from the [Micro Focus Security Community](#).

Sending Events from ArcSight ESM to Logger

The ArcSight Forwarding Connector can read events from an ArcSight Manager and forward them to Logger as CEF-formatted syslog messages.

Note: The Forwarding Connector is a separate installable file, named similar to this:

ArcSight-4.x.x.<build>.x-SuperConnector-<platform>.exe

Use build 4810 or later for compatibility with Logger.

To configure the ArcSight Forwarding Connector to send events to Logger:

1. Install the SmartConnector component normally, through "Install Core Software" as described in the Forwarding Connector configuration guide. Exit the wizard at this point.
2. Create a file called **agent.properties** in the directory **\$ARCSIGHT_HOME/current/user/agent**, where **\$ARCSIGHT_HOME** is the root directory where the SmartConnector component was installed. This file should contain a single line:

```
transport.default.type=cefsyslog
```

3. Start the SmartConnector configuration program again using the **\$ARCSIGHT_HOME/current/bin/runagentsetup** script.
4. Specify the required parameters for CEF output. Enter the desired port for UDP or TCP output.

Tip: These settings will need to match the receiver you create in Logger to listen for events from ArcSight ESM.

| Parameter | Description |
|-----------------------------------|--|
| Ip/Host | IP or host name of the Logger |
| Port | 514 or another port that matches the receiver |
| Protocol | UDP or Raw TCP |
| ArcSight Source Manager Host Name | IP or host name of the source ArcSight Manager |
| ArcSight Source Manager Port | 8443 (default) |
| ArcSight Source Manager User Name | A user account on the source Manager with sufficient privileges to read events |
| ArcSight Source Manager Password | Password for the specified Manager user account |
| SmartConnector Name | A name for the ESM to Logger connector (visible in the Manager) |
| SmartConnector Location | Notation of where this connector is installed |
| Device Location | Notation of where the source Manager is installed |
| Comment | Optional comments |

To configure the Forwarding Connector to send CEF output to Logger and send events to another ArcSight Manager at the same time, see ["Configuring SmartConnectors to Send Events to Both Logger and an ArcSight Manager" on page 560](#).

Appendix D: Using the Rex Operator

The **rex** operator is a powerful operator that enables you to extract information that matches a specified regular expression and assigns it to a field, whose field name you specify. You can also specify an optional start point and an end point in the rex expression between which the information matching the regular expression is searched.

When a rex expression is included in a search query, it must be preceded by a basic search query that finds events from which the rex expression will extract information. For example:

```
failed | rex "(?<srcip>[^\ ]\d{1,3}\.\d{1,3}\.\d{1,3}\.\d{1,3})"
```

The following topics describe the **rex** search operator in detail.

| | |
|---|-----|
| • Syntax of the rex Operator | 563 |
| • Understanding the rex Operator Syntax | 563 |
| • Ways to Create a rex Expression | 565 |
| • Creating a rex Expression Manually | 565 |
| • Example rex Expressions | 566 |

Syntax of the rex Operator

```
| rex "text1(?<field1>text2regex)"
```

Where:

- **text1**: The text or point in the event AFTER which information extraction begins. The default is the beginning of the event.
- **text2**: The text or point in the event at which information extraction ends.
- **field1**: The name of the field to which the extracted information is assigned.
- **regex**: The pattern (regular expression) used for matching information to be extracted between **text1** and **text2**.

Tip: If you are an experienced regular expression user, see the Note in the next section for a quick understanding of how rex enables you to capture named input and reference it for further processing.

Understanding the rex Operator Syntax

Extract all information **after text1** and until **text2** that matches the specified **regex** (regular expression) and assign **to field1**.

- **text1** and **[text2]** can be any points in an event—start and end of an event, specific string in an event (even if the string is in the middle of a word in the event), a specific number of characters from the start or end of an event, or a pattern.

- To specify the next space in the event as **text2**, enter **[^]**.

This is interpreted as “not space.” Therefore, entering a “not” results in the capture to stop at the point where the specified character, in this case, a space, is found in the event.

- To specify **[text2]** to be the end of the line, enter **[^\$]**.

This is interpreted as “not end of line.” Therefore, when an end-of-line in an event is encountered, the capture will stop at that point. The **[^\$]** usage only captures one character if it is not an end-of-line character. However, by specifying **[^\$]*** in a rex expression, the usage captures all characters until end-of-line.

You can also specify **.*** to capture all characters in an event instead of **[^\$]**. Examples in this document, however, use **[^\$]**.

- Any extra spaces within the double quotes of the rex expression are treated literally.
- The characters that need to be escaped for rex expressions are the same as the ones for regular expressions. Refer to a regular expressions document of your choice to obtain a complete list of such characters.
- Information captured by a rex expression can be used for further processing in a subsequent rex expression as illustrated in the following example in which an IP address is captured by the first rex expression and the network ID (assuming the first three bytes of the IP address represent it) to which the IP address belongs is extracted from the captured IP address:

```
logger | rex "(?<srcip>[^ ]\d{1,3}\.\d{1,3}\.\d{1,3}\.\d{1,3})" | rex  
field=srcip "(?<netid>\d{1,3}\.\d{1,3}\.\d{1,3})"
```

Note: If you are an experienced regular expression user, you can interpret the **rex** expression syntax as follows:

```
rex "(?<field1>regex)"
```

where the entire expression in the parentheses specifies a named capture. That is, the captured group is assigned a name, which can be referenced later for further processing. For example, in the following expression “srcip” is the name assigned to the capture.

```
failed | rex "(?<srcip>[^ ]\d{1,3}\.\d{1,3}\.\d{1,3}\.\d{1,3})"
```

Once named, use “srcip” for further processing as follows:

```
failed | rex "(?<srcip>[^ ]\d{1,3}\.\d{1,3}\.\d{1,3}\.\d{1,3})" | top  
srcip
```


Ways to Create a rex Expression

You can create a rex expression in two ways:

- Manually: Follow the syntax and guidelines described in this appendix to create a rex expression to suit your needs.
- Regex Helper: Use the Regex Helper tool, as described in ["Regex Helper Tool" on page 103](#). This tool not only simplifies the process, it also makes it less error prone and more efficient.

Creating a rex Expression Manually

Start with a simple search that finds the events that contains the information in which you are interested. Once the events are displayed, identify a common starting point in those events that precedes the information.

For example, say you want to extract the client IP address, which always appears after the word "[client]" in the following event:

```
[Thu Jul 30 01:20:06 2009] [error] [client 69.63.180.245] PHP Warning:  
memcache_pconnect() [a href='function.memcache-pconnect']>function.memcache-  
pconnect</a>]: Can't connect to 10.4.31.4:11211
```

Therefore, "[client]" is the starting point. A good end point is the "]" after the last byte of the client IP address. Now, we need to define the regular expression that will extract the IP address. Because in this example, only the client IP address appears after the word "client", we use "*" as the regular expression, which means "extract everything". (We could be more specific and use `\d{1,3}\.\d{1,3}\.\d{1,3}\.\d{1,3}` for the IP address.) We assign the extracted IP address to a field name "clientIP". We are almost ready to create a rex expression, except that we need to escape the "[" and "]" characters in the expression. The escape character to use is "\".

Now, we are ready to create the **rex** expression to extract the IP address that appears after the word "client" in the event shown above:

```
| rex "[client(?<clientip>[^\]]*)"
```

Example rex Expressions

This section contains several sample examples for extracting different types of information from an event. The specificity of the information extracted increases with each example. Use these examples as a starting point for creating rex expressions to suit your needs. Also, use the Regex Helper tool that simplifies rex expression creation.

The following event examples illustrate how different rex expressions extract information.

Example One

The following **rex** example uses this event for illustration:

```
2010/07/01 13:46:00 PDT      unknown      Local      ArcSight      Logger      4.5.0.4836.0      eps:100
CEF:0|ArcSight|Logger|4.5.0.4836.0|eps:100|Logger Internal Event|1| cat=/Monitor/Receiver/A11/EPS cs2=SinceLastMonitorEvent cnt=1 dvc=192.168.36.3 cs1=Events/s
2010/07/01 13:46:00 PDT      unknown      Local      ArcSight      Logger      4.5.0.4836.0      eps:100
CEF:0|ArcSight|Logger|4.5.0.4836.0|eps:100|Logger Internal Event|1| cat=/Monitor/Forwarder/A11/EPS cs2=SinceLastMonitorEvent cnt=1 dvc=192.168.36.3 cs1=Events/
```

- Capture matching events from the left of the pipeline and assign them to the field **message**. The entire event is assigned to the **message** field.

```
| rex "(?<message>[^\$]*)"
```

This expression extracts the entire event (as shown above), starting at the word “CEF:0”.

- Specifying the starting point as number of characters from the start of an event instead of a specific character or word

```
| rex "[a-zA-Z0-9:\.\s]{16}(?<message>[^\$]*)"
```

This expression starts extracting after 16 **consecutive** occurrences of the characters specified for **text1**—alphanumeric characters, colons, periods, or spaces. Although the first 16 characters of the first event are **CEF:0|ArcSight|L**, the extraction does not begin at “Logger|4.5.0...” because the pipeline character is not part of the characters we are matching, but this character is part of the beginning of the event. Therefore, the first 16 consecutive occurrences are “Logger Internal.” As a result, information starting at the word **Event** is extracted from our example event.

- Extract a specified number of characters instead of specifying an end point such as the next space or the end of the line

```
| rex "[a-zA-Z0-9:\.\s]{16}(?<message>[^\$]{5})"
```

This expression only extracts the word “Event.” (See the previous sample rex expression for a detailed explanation of the reason extraction begins at the word “Event.”)

- Extract everything after **CEF:0|** into the **message** field. Then, pipe events for which the **message** field is not null through another rex expression to extract the IP address contained in the matching events and assign the IP addresses to another field, **msgip**. Only display events where **msgip** is not null.

```
| rex "CEF:0\|(?<message>[^$]*)\" | where message is not null | rex "dvc=
(?<msgip>[^ ]\d{1,3}\.\d{1,3}\.\d{1,3}\.\d{1,3})\" | where msgip is not null
```

Note: The colon (:) and equal sign (=) characters do not need to be escaped; however, pipe (|) characters must be escaped. The characters that need to be escaped for rex expressions are the same as the ones for regular expressions. Refer to a regular expressions document of your choice to obtain a complete list of such characters.

This expression extracts the device IP address from the event.

Example Two

The following **rex** example uses this event for illustration:

```
Nov 10 03:04:24 192.168.20.114 192.168.20.113 [REDACTED] C007:4D28;EvilPackets:Line 16:"New Group","My IP:192.168.20.150","11/10/2005 11:02:05.000","21561","11/10/2005 11:02:05.000","3106004","generator","1","192.168.20.111","http:80","192.168.20.112","32771","tcp","Alert","47302","47285","RPC Incomplete Segment","0","0","00:00:00:00:00:00","00:00:00:00:00:00")
```

- Extract the first two IP addresses from an event and assign them to two different fields, IP1 and IP2.

```
| rex "(?<IP1>[^\$]\d{1,3}\.\d{1,3}\.\d{1,3}\.\d{1,3})" | rex "\d{1,3}\.\d{1,3}\.\d{1,3}\.\d{1,3}(?<IP2>[^\$]\d{1,3}\.\d{1,3}\.\d{1,3}\.\d{1,3})"
```

This expression extracts the first and second IP addresses in the above event.

Because the two IP addresses are right after one another in this event, you can also specify the extraction of the two IP addresses in a single rex expression as follows:

```
| rex "(?<IP1>[^$]\d{1,3}\.\d{1,3}\.\d{1,3}\.\d{1,3})(?<IP2>[^$]\d{1,3}\.\d{1,3}\.\d{1,3}\.\d{1,3})"
```

Note: Do not enter any spaces in the expression.

- Building on the previous example, add a new field called **Ignore**. Assign the value “Y” to this field if the two IP addresses extracted in the previous example are the same and assign the value “N” if the two IP addresses are different. Then, list the top IP1 and IP2 combinations for events for which Ignore field is “N”

```
| rex (?<IP1>[^\$]\d{1,3}\.\d{1,3}\.\d{1,3}\.\d{1,3})" | rex "\d{1,3}\.\d{1,3}\.\d{1,3}\.\d{1,3}(?<IP2>[^\$]\d{1,3}\.\d{1,3}\.\d{1,3}\.\d{1,3})" | eval Ignore=if(IP1==IP2,"Y","N") | where Ignore="N" | top IP1 IP2
```

Note: The eval command uses a double equal sign (==) to equate the two fields.

- Information captured by a rex expression can be used for further processing in a subsequent rex expression as illustrated in the following example. The first IP address is captured by the first rex expression and the network ID (assuming the first three bytes of the IP address represent it) to which the IP address belongs is extracted from the captured IP address:

```
logger | rex "(?<srcip>[^\d{1,3}\.\d{1,3}\.\d{1,3}\.\d{1,3})" | rex  
field=srcip "(?<netid>\d{1,3}\.\d{1,3}\.\d{1,3})"
```

Example Three

The following rex example uses this event for illustration:

```
127.0.0.1 - name [10/Oct/2010:13:55:36 -0700] "GET /apache_pb.gif HTTP/1.0"  
200 2326 "http://www.example.com/start.html" "Mozilla/4.08 [en] (Win98; I  
;Nav)"
```

- Extract all URLs from events and generate a chart of the URL counts, excluding blank URLs. (The events contain the URL string in "http://" format.)

```
| rex "http://(?<customURL>[^\s]*)" | where customURL is not null | chart  
count by customURL | sort - customURL
```

Note: The meta character "/" needs to be enclosed in square brackets [] to be treated literally.

Example Four

The following rex example uses this event for illustration:

| | | |
|-----|---|----------|
| 1 | 2010/04/06 22:11:46 CDT 10.0.10.222 [Raw_Syslog] Local | root |
| RAW | Feb 25 14:03:24 beach login(pam_unix)[123]: session closed for sssd root | |
| 2 | 2010/04/06 22:11:46 CDT 10.0.10.222 [Raw_Syslog] Local | sysadmin |
| RAW | Feb 25 14:03:24 beach sshd(pam_unix)[123]: authentication failure; logname=uid=0 euid=0 tty=ssh ruser= rhost=123.123.123.123 sssd sysadmin | |
| 3 | 2010/04/06 22:11:46 CDT 10.0.10.222 [Raw_Syslog] Local | p4admin |
| RAW | Feb 25 14:03:24 beach sshd(pam_unix)[123]: session closed for sssd p4admin | |
| 4 | 2010/04/06 22:11:46 CDT 10.0.10.222 [Raw_Syslog] Local | sysadmin |
| RAW | Feb 25 14:03:24 beach sshd(pam_unix)[123]: session opened for sssd sysadmin by (uid=500) | |

- Extract the first word after the word "user" (one space after the word) or "user=". The word "user" is case-insensitive in this case, and must be preceded by a space character. That is, words such as "ruser" and "suser" should not be matched.

```
| rex "\s[u|U][s|S][e|E][r|R][\s|=](?<CustomUser>[^\s]*)"
```

Appendix E: Logger Audit Events

You can forward the Logger audit events, which are in Common Event Format (CEF), to ArcSight ESM directly for analysis and correlation. Use the Audit Forwarding feature (as described in ["Audit Forwarding" on page 475](#)) to forward the events.

For more information about CEF, refer to the document "ArcSight CEF". For a downloadable a copy of this guide, search for "ArcSight Common Event Format (CEF) Guide" in the [Micro Focus Security Community](#).

The following topics describe Logger's audit events:

- [Types of Audit Events](#) 569
- [Information in an Audit Event](#) 569
- [Platform Events](#) 570
- [Application Events](#) 579

Types of Audit Events

Two types of audit events are generated on Logger and available for Audit Forwarding to ArcSight ESM.

- ["Platform Events" on the next page](#), which are related to the Logger hardware/system.
- ["Application Events" on page 579](#), which are related to Logger functions and configuration changes on it.

Both types of events are stored in the Logger Internal Storage Group. As a result, these events can be searched using the Logger Search UI. For example, you can search for this platform event:

`"/Platform/Authentication/Failure/Password"`

Information in an Audit Event

A Logger audit event (in CEF format) contains information about the following prefix fields:

- Device Event Class ID
- Device Severity
- Message
- Device Event Category—(keyName for this CEF extension is "cat")

For example:

```
Sep 19 08:26:10 zurich CEF:0|ArcSight|Logger|3.5.0.13412.0|logger:500|Filter
added|2| cat=/Logger/Resource/Filter/Configuration/Add
msg=Filter [Regex Query Test] has been added
```

Platform Events

The following table lists the information contained in audit events related to the Logger platform. All events include the following fields.

- **duser**—UserName
- **duid**—User ID
- **src**—IP address of client
- **dst**—IP address of appliance
- **cat**—Device Event Category
- **cn1**—Session number
- **cn1label**—Session

Additional fields (if applicable) are listed in the following table.

| Device Event Class ID | Sev. | Device Event Category (cat) | Message | Additional Fields |
|-----------------------|------|--|--|---|
| platform:200 | 5 | /Platform/Authentication/PasswordChange/Failure | Failed password change | |
| platform:201 | 7 | /Platform/Authentication/Failure | Failed login attempt | |
| platform:202 | 5 | /Platform/Authentication/PasswordChange | Password changed | cs1: Affected User Id cs2: Affected User Login cs3: Affected User Full Name |
| platform:203 | 7 | /Platform/Authentication/InactiveUser/Failure | Login attempt by inactive user | |
| platform:205 | 7 | /Platform/Authentication/PasswordChange/AdminFailure | Automated password reset attempt made for admin account | duser: admin |
| platform:207 | 7 | /Platform/Authentication/PasswordChange/UnknownUser | Automated password reset attempted for non-existent user | duser: username cs1: username |

| Device Event Class ID | Sev. | Device Event Category (cat) | Message | Additional Fields |
|-----------------------|------|--|---|---|
| platform:213 | 7 | /Platform/Configuration /Global/AuditEvents | Audit forwarding modified | cs1: Audit Forwarders |
| platform:220 | 5 | /Platform/Certificate /Install | Installed certificate | cs1: Network Protocol |
| platform:221 | 7 | /Platform/Certificate/Mismatch | Certificate mismatch failure | cs1: Network Protocol |
| platform:222 | 1 | /Platform/Certificate/Request | Created certificate signing request | cs1: Certificate Signing Request cs2: Network Protocol |
| platform:224 | 5 | /Platform/Certificate/ Regenerate | Re-generate self-signed certificate | cs1: Certificate Signing Request cs2: Network Protocol |
| platform:226 | 7 | /Platform/Update/Failure/ CorruptPackage | Uploaded update file damaged or corrupt | cs1: Error cs2: fname cs3: fsize |
| platform:227 | 5 | /Platform/Update/Applied | Update installation success | cs1: Update Name cs2: Is Reboot Required |
| platform:228 | 7 | /Platform/Update/Failure /Installation | Update installation failure | cs1: Error cs2: Update Name |
| platform:230 | 3 | /Platform/Authentication /Login | Successful login | |
| platform:234 | 7 | /Platform/Authentication /Failure/LOCKED | Failed login attempt (LOCKED) | |
| platform:239 | 3 | /Platform/Authentication /Logout | User logout | |

| Device Event Class ID | Sev. | Device Event Category (cat) | Message | Additional Fields |
|-----------------------|------|--|--------------------------------|--|
| platform:240 | 3 | /Platform/Authorization /Groups/Add | Added user group | cn2: Current Number of Users cn3: Current Number of User Rights cs1: Affected Group Name cs2: Affected Group Id flexNumber1: Old Number of Users flexNumber2: Old Number of User Rights |
| platform:241 | 3 | /Platform/Authorization /Groups/Update | Updated user group | cn2: Current Number of Users cn3: Current Number of User Rights cs1: Affected Group Name cs2: Affected Group Id flexNumber1: Old Number of Users flexNumber2: Old Number of User Rights |
| platform:242 | 5 | /Platform/Authorization /Groups/Membership /Update/Clear | Removed all members from group | |
| platform:243 | 3 | /Platform/Authorization /Groups/Membership/Update | Modified user group membership | |
| platform:244 | 3 | /Platform/Authorization /Groups/Delete | Deleted user group | cs1: Affected Group Name cs2: Affected Group Id |
| platform:245 | 3 | /Platform/Authorization /Users/Add | Added user | cs1: Affected User Id cs2: Affected User Login cs3: Affected User Full Name |

| Device Event Class ID | Sev. | Device Event Category (cat) | Message | Additional Fields |
|-----------------------|------|---|-------------------------------------|---|
| platform:246 | 3 | /Platform/Authorization /Users/Update | Updated user | cs1: Affected User Id cs2: Affected User Login cs3: Affected User Full Name |
| platform:247 | 3 | /Platform/Authorization/Users /Delete | Deleted user | cs1: Affected User Id cs2: Affected User Login cs3: Affected User Full Name |
| platform:248 | 3 | /Platform/Authentication /Logout/SessionExpiration | Session expired | |
| platform:249 | 7 | /Platform/Authentication /AccountLocked | Account locked | |
| platform:250 | 5 | /Platform/Storage/RFS /Add | Added remote mount point | cs1: RFS Mount Name cs2: RFS Mount Host and Remote Path |
| platform:251 | 5 | /Platform/Storage/RFS /Edit | Edited remote mount point | cs1: RFS Mount Name cs2: RFS Mount Host and Remote Path |
| platform:252 | 7 | /Platform/Storage/RFS /Failure | Failed to create remote mount point | cs1: Server cs2: Remote Directory cs3: Mount Name cs4: Mount Type cs5: Username |
| platform:253 | 5 | /Platform/Storage/RFS /Remove | Removed remote mount point | cs1: RFS Mount Name cs2: RFS Mount Host and Remote Path |
| platform:254 | 5 | /Platform/Storage/SAN /Destroy | Destroyed SAN Logical Unit | cs1: Volume label |
| platform:255 | 5 | /Platform/Storage/SAN /Attach | Attached SAN Logical Unit | cn2: Volume size (in MB) cs1: Volume label cs2: World-wide Name cs3: Filesystem type |

| Device Event Class ID | Sev. | Device Event Category (cat) | Message | Additional Fields |
|-----------------------|------|--|------------------------------|---|
| platform:256 | 7 | /Platform/Storage/SAN /Detach | Detached SAN Logical Unit | cs1: Storage unit details |
| platform:259 | 5 | /Platform/Storage/SAN /Reattach | Reattached SAN Logical Unit | cs1: Volume label cs2: Filesystem type |
| platform:260 | 5 | /Platform/Configuration /Network/Route/Update | Static route modified | cs1: Destination cs2: Subnet cs3: Gateway |
| platform:261 | 5 | /Platform/Configuration /Network/Route/Remove | Static route removed | cs1: Destination cs2: Subnet cs3: Gateway |
| platform:262 | 5 | /Platform/Configuration /Time | Appliance time modified | cs1: Old Date/Time cs2: New Date/Time cs3: Old Time Zone cs4: New Time Zone |
| platform:263 | 5 | /Platform/Configuration /Network | NIC settings modified | cs1: NIC cs2: IP Address cs3: Netmask cs4: Speed |
| platform:264 | 5 | /Platform/Configuration /Network/NTP | NTP server settings modified | cs1: NTP Servers cs2: Is Appliance NTP Server |
| platform:265 | 5 | /Platform/Configuration /Network/DNS | DNS settings modified | |
| platform:266 | 5 | /Platform/Configuration /Network/Hosts | Hosts file modified | cs1: Difference from previous hosts file |
| platform:267 | 5 | /Platform/Configuration /SMTP | SMTP settings modified | cs1: EMail Address cs2: SMTP Server cs3: Backup SMTP Server cs4: Username SMTP Server cs5: Username Backup SMTP Server cs6: SMTP Auth/TLS Mode |
| platform:268 | 5 | /Platform/Configuration /Network/Route/Add | Static route added | cs1: Destination cs2: Subnet cs3: Gateway |

| Device Event Class ID | Sev. | Device Event Category (cat) | Message | Additional Fields |
|-----------------------|------|--|---|---|
| platform:270 | 5 | /Platform/Authorization /Users/Inactive/Disable | Inactive user disabled | cs1: User Login deviceCustomDate1: Date Last Active |
| platform:280 | 7 | /Appliance/State/Reboot /Initiate | Appliance reboot initiated | |
| platform:281 | 3 | /Appliance/State/Reboot /Cancel | Appliance reboot canceled | |
| platform:282 | 7 | /Appliance/State/ Shutdown | Appliance poweroff initiated | |
| platform:284 | 5 | /Platform/Storage/ Multipathing/Enable | Enabled SAN Multipathing | cs1: Multipath Configuration |
| platform:285 | 5 | /Platform/Storage/ Multipathing/Disable | Disabled SAN Multipathing | |
| platform:300 | 5 | /Platform/Certificate /Install | Installed trusted certificate | cs1: Certificate details |
| platform:301 | 5 | /Platform/Certificate /Revocation/Install | Installed certificate revocation list | cs1: CRL details |
| platform:302 | 5 | /Platform/Certificate/Delete | Deleted trusted certificate | cs1: Certificate details |
| platform:303 | 5 | /Platform/Certificate/ Revocation/Delete | Deleted certificate revocation list | cs1: CRL details |
| platform:304 | 7 | /Platform/Certificate/ Install/Failure | Failed installing trusted certificate | cs1: Error cs2: File Size cs3: File Name |
| platform:305 | 7 | /Platform/Certificate/ Revocation/Install/Failure | Failed installing certificate revocation list | cs1: Error cs2: File Size cs3: File Name |
| platform:306 | 5 | /Platform/Process/Start | Start process | cs1: Process Name |
| platform:307 | 5 | /Platform/Process/Stop | Stop process | cs1: Process Name |
| platform:308 | 5 | /Platform/Process/Restart | Restart process | cs1: Process Name |
| platform:310 | 5 | /Platform/Configuration /FIPS/Enable | Enabled FIPS mode | |

| Device Event Class ID | Sev. | Device Event Category (cat) | Message | Additional Fields |
|-----------------------|------|--|------------------------------------|---|
| platform:311 | 7 | /Platform/Configuration /FIPS/Disable | Disabled FIPS mode | |
| platform:312 | 7 | /Platform/Configuration /WebServer/CipherStrength | Web server cipher strength changed | cs1: New Value cs2: Old Value |
| platform:320 | 3 | /Appliance/State /Shutdown/Cancel | Appliance poweroff canceled | |
| platform:371 | 5 | /Platform/Service/Restart | Restarted OS service | cs1: Service Name |
| platform:400 | 2 | /Platform/Diagnostics /Command | Ran diagnostic command | cs1: Diagnostic Command |
| platform:407 | 7 | /Platform/Certificate /SSL/Expiration | SSL certificate expiration warning | cs1: Issuer cs2: Subject deviceCustomDate1: Expiration Date |
| platform:408 | 5 | /Appliance/State/Startup | Appliance startup completed | deviceCustomDate1: Startup Date |
| platform:409 | 3 | /Platform/Configuration /LoginBanner | Configure login warning banner | cs1: Acknowledgment Prompt cs2: Banner Text |
| platform:410 | 5 | /Platform/Configuration /Network | Network settings modified | cs1: Gateway cs2: Multi-homing cs3: Hostname |
| platform:411 | 5 | /Platform/Authentication /PasswordChange | Automated Password Reset | cn2: User ID cs1: User Login |
| platform:412 | 3 | /Platform/Configuration /Locale | Set Locale | cs1: Locale |
| platform:440 | 3 | /Platform/Configuration/ SNMP | SNMP configuration modified | cn2: Port Number cn3: Refresh Interval cs1: SNMP Enabled cs2: Community String cs3: Listen Address (es) |

| Device Event Class ID | Sev. | Device Event Category (cat) | Message | Additional Fields |
|-----------------------|------|---|---|---|
| platform:460 | 3 | /Platform/Network/Alias/Add | NIC alias added | cs1: NIC cs2: IP Address cs3: Netmask |
| platform:462 | 3 | /Platform/Network/Alias /Remove | NIC alias removed | cs1: NIC cs2: IP Address cs3: Netmask |
| platform:500 | 5 | /Platform/Authorization /Groups/Membership /Remove | Remove member from group | cs1: Affected Group Name cs2: Affected User Login cs3: Affected Group Id cs4: Affected User Id |
| platform:501 | 5 | /Platform/Authorization /Groups/Membership/Add | Group member added | cs1: Affected Group Name cs2: Affected User Login cs3: Affected Group Id cs4: Affected User Id |
| platform:502 | 5 | /Platform/Authorization /Users/Groups/Remove | User removed from group | cs1: Affected Group Name cs2: Affected User Login cs3: Affected Group Id cs4: Affected User Id |
| platform:503 | 5 | /Platform/Authorization /Users/Groups/Add | User added to group | cs1: Affected Group Name cs2: Affected User Login cs3: Affected Group Id cs4: Affected User Id |
| platform:530 | 5 | /Platform/Configuration /Authentication/Sessions /Success | Authentication Session settings successfully changed. | cn2: New Value cn3: Old Value cs1: Parameter Changed |

| Device Event Class ID | Sev. | Device Event Category (cat) | Message | Additional Fields |
|-----------------------|------|--|--|--|
| platform:540 | 5 | /Platform/Configuration /Authentication/Password /Lockout/Success | Password Lockout settings successfully updated. | cn2: New Value cn3: Old Value cs1: Parameter Changed |
| platform:550 | 5 | /Platform/Configuration /Authentication/Password /Expiration/Success | Password Expiration settings successfully updated. | cn2: New Value cn3: Old Value cs1: Parameter Changed |
| platform:560 | 5 | /Platform/Configuration /Authentication/Password /Validation/Success | Password Validation settings successfully updated. | cn2: New Value cn3: Old Value cs1: Parameter Changed |
| platform:570 | 5 | /Platform/Configuration /Authentication/Password /AutomatedPasswordReset /Success | Password Automated Password Reset setting successfully updated. | cs1: Parameter Changed cs2: New Value cs3: Old Value |
| platform:580 | 5 | /Platform/Configuration /Authentication/Certificate /Success | Client Certificate authentication settings successfully changed. | cs1: Parameter Changed cs2: New Value cs3: Old Value |
| platform:590 | 5 | /Platform/Configuration /Authentication/RADIUS /Success | RADIUS authentication settings successfully changed. | cs1: Parameter Changed cs2: New Value cs3: Old Value |
| platform:600 | 5 | /Platform/Configuration /Authentication/LDAP/ Success | LDAP authentication settings successfully changed. | cs1: Parameter Changed cs2: New Value cs3: Old Value |
| platform:610 | 5 | /Platform/Configuration /Authentication/Global /Success | Global Authentication settings successfully changed. | cs1: Parameter Changed cs2: New Value cs3: Old Value |

Application Events

The following table lists the information contained in audit events related to various Logger functions and configuration changes on it. The Severity for all Logger application events is **2**.

| Device Event Class ID | Device Event Category (cat) | Message | Additional Fields |
|--------------------------|--|-------------------------------|---|
| Alerts | | | |
| logger:610 | /Logger/Component /Alert/Configuration /Add | Alert [name] has been added | fname=AlertName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=forwarderType dvc=syslogOrSnmplpAddr dvchost=syslogOrSnmHostName cn1Label=Syslog or SNMP Destination Port cn1=syslogOrSnmPort cs1Label=Filter cs1=filter cs2Label=Email Destination(s) cs2=emailAddresses |
| logger:611 | /Logger/Component /Alert/Configuration /Delete | Alert [name] has been deleted | fname=AlertName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=forwarderType dvc=syslogOrSnmplpAddr dvchost=syslogOrSnmHostName cn1Label=Syslog or SNMP Destination Port cn1=syslogOrSnmPort cs1Label=Filter cs1=filter cs2Label=Email Destination(s) cs2=emailAddresses |

| Device Event Class ID | Device Event Category (cat) | Message | Additional Fields |
|-----------------------|---|--------------------------------|---|
| logger:612 | /Logger/Component /Alert/Configuration /Update | Alert [name] has been updated | fname=AlertName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=forwarderType dvc=syslogOrSnmplpAddr dvchost=syslogOrSnmpHostName cn1Label=Syslog or SNMP Destination Port cn1=syslogOrSnmpPort cs1Label=Filter cs1=filter cs2Label=Email Destination(s) cs2=emailAddresses |
| logger:613 | /Logger/Component /Alert/Configuration /Enable | Alert [name] has been enabled | fname=AlertName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=forwarderType dvc=syslogOrSnmplpAddr dvchost=syslogOrSnmpHostName cn1Label=Syslog or SNMP Destination Port cn1=syslogOrSnmpPort cs1Label=Filter cs1=filter cs2Label=Email Destination(s) cs2=emailAddresses |
| logger:614 | /Logger/Component /Alert/Configuration /Disable | Alert [name] has been disabled | fname=AlertName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=forwarderType dvc=syslogOrSnmplpAddr dvchost=syslogOrSnmpHostName cn1Label=Syslog or SNMP Destination Port cn1=syslogOrSnmpPort cs1Label=Filter cs1=filter cs2Label=Email Destination(s) cs2=emailAddresses |

| Device Event Class ID | Device Event Category (cat) | Message | Additional Fields |
|-----------------------------|---|--|--|
| logger:615 | /Logger/Alert /Configuration/Sent | Alert [name] has been sent | fname=AlertName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=forwarderType dvc=syslogOrSnmplpAddr dvchost=syslogOrSnmpOr EsmHostName cn1Label=Syslog Or SNMP Or ESM Destination Port cn1=syslogOrSnmpOrEsmPort cs1Label=Filter cs1=filter cs2Label=Email Destination(s) cs2=emailAddresses |
| Certificates | | | |
| logger:643 | /Logger/Component/ Certificate/Configuration /Add | Certificate [name] has been added | fname=alias duser=UserName duid=userId cs4=sessionId cs4Label=Session ID fileType=Certificate |
| logger:650 | /Logger/Component/ Certificate/Configuration /Delete | Certificate [name] has been deleted | fname=alias duser=UserName duid=userId cs4=sessionId cs4Label=Session ID fileType=Certificate |
| logger:651 | /Logger/Component/ Certificate/Configuration /Update | Certificate [name] has been updated | fname=alias duser=UserName duid=userId cs4=sessionId cs4Label=Session ID fileType=Certificate |
| Configuration Backup | | | |
| logger:660 | /Logger/Component/ ConfigBackup /Configuration/Update | Configuration backup has been updated | fname=Configuration Backup duser=UserName duid=userId cs4=sessionId cs4Label=Session ID fileType=Configuration Backup |

| Device Event Class ID | Device Event Category (cat) | Message | Additional Fields |
|--------------------------|--|---|---|
| logger:661 | /Logger/Component/ ConfigBackup /Configuration/Enable | Configuration backup has been enabled | fname=Configuration Backup duser=UserName duid=userId cs4=sessionId cs4Label=Session ID fileType=Configuration Backup |
| logger:662 | /Logger/Component/ ConfigBackup /Configuration/Disable | Configuration backup has been disabled | fname=Configuration Backup duser=UserName duid=userId cs4=sessionId cs4Label=Session ID fileType=Configuration Backup |
| logger:665 | /Logger/Component /ConfigBackup /Configuration/Backup | Configuration backup succeeded. Transfer process finished. | fname=Configuration Backup fileType=Configuration Backup fpath=pathToBackupFile fsize=fileSizeInByte |
| ESM Destinations | | | |
| logger:640 | /Logger/Component/ EsmDestination/ Configuration/Add | ESM destination [name] has been added | fname=esmDestinationName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=ESM Destination fileId=esmDestinationId dvc=esmDestinationIp dvchost=esmDestinationHost cn1Label=ESM Destination Port cn1=esmDestinationPort cs1Label=Connector Name cs1=connectorName cs2Label=Connector Location cs2=connectorLocation cs3Label=Logger Location cs3=loggerLocation |

| Device Event Class ID | Device Event Category (cat) | Message | Additional Fields |
|-----------------------|---|---|--|
| logger:641 | /Logger/Component/ EsmDestination/ Configuration/Delete | ESM destination [name] has been deleted | fname=esmDestinationName duser=UserName duid=userId cs4=sessionId file cs4Label=Session ID fileType=ESM Destination fileId=esmDestinationId dvc=esmDestinationIp dvchost=esmDestinationHost cn1Label=ESM Destination Port cn1=esmDestinationPort cs1Label=Connector Name cs1=connectorName cs2Label=Connector Location cs2=connectorLocation cs3Label=Logger Location cs3=loggerLocation |
| Forwarders | | | |
| logger:605 | /Logger/Component /Forwarder/Configuration /Add | Forwarder [name] has been added | fname=forwarderName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=forwarderType dvc=forwarderIpAddr dvchost=forwarderHostName cn1Label=Forwarder Port cn1=forwarderPort cs1Label=Forwarder Filter cs1=forwarderFilter |
| logger:606 | /Logger/Component/ Forwarder/Configuration /Delete | Forwarder [name] has been deleted | fname=forwarderName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=forwarderType dvc=forwarderIpAddr dvchost=forwarderHostName cn1Label=Forwarder Port cn1=forwarderPort cs1Label=Forwarder Filter cs1=forwarderFilter |

| Device Event Class ID | Device Event Category (cat) | Message | Additional Fields |
|--------------------------|---|---------------------------------------|--|
| logger:607 | /Logger/Component/ Forwarder/Configuration /Update | Forwarder [name] has been updated | fname=forwarderName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=forwarderType dvc=forwarderIpAddr dvchost=forwarderHostName cn1Label=Forwarder Port cn1=forwarderPort cs1Label=Forwarder Filter cs1=forwarderFilter |
| logger:608 | /Logger/Component/ Forwarder/Configuration /Enable | Forwarder [name] has been enabled | fname=forwarderName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=forwarderType dvc=forwarderIpAddr dvchost=forwarderHostName cn1Label=Forwarder Port cn1=forwarderPort cs1Label=Forwarder Filter cs1=forwarderFilter |
| logger:609 | /Logger/Component/ Forwarder/Configuration /Disable | Forwarder [name] has been disabled | fname=forwarderName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=forwarderType dvc=forwarderIpAddr dvchost=forwarderHostName cn1Label=Forwarder Port cn1=forwarderPort cs1Label=Forwarder Filter cs1=forwarderFilter |

| Device Event Class ID | Device Event Category (cat) | Message | Additional Fields |
|-----------------------|--|-----------------------------------|--|
| logger:663 | /Logger/Component/ Forwarder/Configuration /Pause | Forwarder [name] has been paused | fname=forwarderName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=forwarderType dvc=forwarderIpAddr dvchost=forwarderHostName cn1Label=Forwarder Port cn1=forwarderPort cs1Label=Forwarder Filter cs1=forwarderFilter |
| logger:664 | /Logger/Component/ Forwarder/Configuration /Resume | Forwarder [name] has been resumed | fname=forwarderName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=forwarderType dvc=forwarderIpAddr dvchost=forwarderHostName cn1Label=Forwarder Port cn1=forwarderPort cs1Label=Forwarder Filter cs1=forwarderFilter |
| Receivers | | | |
| logger:600 | /Logger/Component/ Receiver/Configuration /Add | Receiver [name] has been added | fname=receiverName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=receiverType dvc=receiverIpAddr dvchost=receiverHostName cn1Label=Receiver Port cn1=receiverPort |
| logger:601 | /Logger/Component/ Receiver/Configuration /Delete | Receiver [name] has been deleted | fname=receiverName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=receiverType dvc=receiverIpAddr dvchost=receiverHostName cn1Label=Receiver Port cn1=receiverPort |

| Device Event Class ID | Device Event Category (cat) | Message | Additional Fields |
|--------------------------|--|-----------------------------------|--|
| logger:602 | /Logger/Component/ Receiver/Configuration /Update | Receiver [name] has been updated | fname=receiverName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=receiverType dvc=receiverIpAddr dvchost=receiverHostName cn1Label=Receiver Port cn1=receiverPort |
| logger:603 | /Logger/Component/ Receiver/Configuration /Enable | Receiver [name] has been enabled | fname=receiverName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=receiverType dvc=receiverIpAddr dvchost=receiverHostName cn1Label=Receiver Port cn1=receiverPort |
| logger:604 | /Logger/Component/ Receiver/Configuration /Disable | Receiver [name] has been disabled | fname=receiverName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=receiverType dvc=receiverIpAddr dvchost=receiverHostName cn1Label=Receiver Port cn1=receiverPort |
| SNMP Destinations | | | |

| Device Event Class ID | Device Event Category (cat) | Message | Additional Fields |
|----------------------------|---|---|--|
| logger:644 | /Logger/Component/ SnmDestination/ Configuration/Add | SNMP destination [name] has been added | fname=snmpDestinationName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=SNMP Destination fileId=snmpDestinationId dvc=snmpDestinationIp dvchost=snmpDestinationHost cn1Label=SNMP Destination Port cn1=snmpDestinationPort cs1Label=Connector Name cs1=connectorName cs2Label=Connector Location cs2=connectorLocation cs3Label=Logger Location cs3=loggerLocation |
| logger:645 | /Logger/Component/ SnmDestination/ Configuration/Delete | SNMP destination [name] has been deleted | fname=snmpDestinationName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=SNMP Destination fileId=snmpDestinationId dvc=snmpDestinationIp dvchost=snmpDestinationHost cn1Label=SNMP Destination Port cn1=snmpDestinationPort cs1Label=Connector Name cs1=connectorName cs2Label=Connector Location cs2=connectorLocation cs3Label=Logger Location cs3=loggerLocation |
| Syslog Destinations | | | |

| Device Event Class ID | Device Event Category (cat) | Message | Additional Fields |
|--------------------------|--|--|--|
| logger:647 | /Logger/Resource/ SyslogDestination/ Configuration/Add | Syslog destination [name] has been added | fname=syslogDestinationName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Syslog Destination fileId=syslogDestinationId dvc=syslogDestinationIp dvchost=syslogDestinationHost cn1Label=Syslog Destination Port cn1=syslogDestinationPort |
| logger:648 | /Logger/Component/ SyslogDestination/ Configuration/Delete | Syslog destination [name] has been deleted | fname=syslogDestinationName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Syslog Destination fileId=syslogDestinationId dvc=syslogDestinationIp dvchost=syslogDestinationHost cn1Label=Syslog Destination Port cn1=syslogDestinationPort |
| logger:649 | /Logger/Component /SyslogDestination /Configuration/Update | Syslog destination [name] has been updated | fname=syslogDestinationName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Syslog Destination fileId=syslogDestinationId dvc=syslogDestinationIp dvchost=syslogDestinationHost cn1Label=Syslog Destination Port cn1=syslogDestinationPort |
| Archives | | | |

| Device Event Class ID | Device Event Category (cat) | Message | Additional Fields |
|---------------------------------------|---|---|--|
| logger:520, Manually added | /Logger/Resource/Archive/ Add | Event Archive Added ManualArchive [Date] [Internal Event Storage Group] | cat=/Resource/Archive/Add cs4=sessionIdFile cs4Label=Session ID dst=127.0.0.1 duid=userId duser=User name dvc=127.0.0.1 end=endTime fileType=archive fname= archiveName [Date] [Storage Group] fpath= geid=0 msg= rt=1542381263507 |
| logger:520, Added with schedule | /Logger/Resource/Archive/Add | Event Archive Added ManualArchive [Date] [Internal Event Storage Group] | cat=/Resource/Archive/Add cs4Label=Session ID dst=127.0.0.1 duser= scheduled Archivor dvc=127.0.0.1 end=endTime fileType=archive fname= archiveName fpath= geid=0 rt=1542304800457 |
| logger:521 | /Logger/Resource /Archive/Configuration /Delete | Archive [archiveName] has been deleted | fname=archiveName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=EventArchive fileId=archiveId |
| logger:523 | /Logger/Resource /Archive/Configuration /Load | Archive [archiveName] has been loaded | fname=archiveName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=EventArchive fileId=archiveId |

| Device Event Class ID | Device Event Category (cat) | Message | Additional Fields |
|---------------------------------------|---|--|--|
| logger:524 | /Logger/Resource /Archive/Configuration /Unload | Archive [archiveName] has been unloaded | fname=archiveName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=EventArchive fileId=archiveId |
| logger:525, Manually added | /Logger/Resource/Archive/ Archive | Event Archive Archived ManualArchive [date] [Internal Event Storage Group] | dst=127.0.0.1 dvc=127.0.0.1 end=endTime fileType=archive fpath=/tmp/logger/internal_ default_storage2 geid=0 rt=1542381271849 |
| logger:525, Added with schedule | /Logger/Resource/Archive/ Archive | Event Archive Archived archive [date] [Internal Event Storage Group] | dst=127.0.0.1 dvc=127.0.0.1 end=endTime fileType=archive fname=fileName fpath=/tmp/logger/internal_ default_storage2 geid=0 rt=1542304809316 |
| logger:526 | /Logger/Resource /Archive/Add | Event archive settings added | duser=UserName duid=userId cs1= Mount Location Path cs2= Remote Subdirectory path fileType= Event Archive Settings |
| logger:527 | /Logger/Resource /Archive/Update | Daily archive task settings updated | duser= UserName duid= userId cs1= Time for Daily Archive to Start fileType= Daily Archive Task Settings |
| logger:528 | /Logger/Resource /Archive/Failed | Event archive failed | fname=archiveName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=EventArchive fileId=archiveId |

| Device Event Class ID | Device Event Category (cat) | Message | Additional Fields |
|-----------------------|---|--|--|
| logger:529 | /Logger/Resource/Archive/Index | Event Archive [archiveName] has been indexed | fname=archiveName duser=UserName duid=userId fileType=EventArchive indexed geid=0 |
| Dashboards | | | |
| logger:580 | /Logger/Resource /Dashboard /Configuration/Add | Dashboard [name] has been added | fname=dashboardName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Dashboard fileId=DashboardId rt=receiptTime |
| logger:581 | /Logger/Resource /Dashboard /Configuration/Add | Dashboard [name] has been deleted | fname=dashboardName duser=UserName duid=userId cs4=sessionIdfile fileType=Dashboard fileId=DashboardId rt=receiptTime |
| logger:582 | /Logger/Resource /Dashboard /Configuration/Update | Dashboard [name] has been updated | fname=dashboardName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Dashboard fileId=DashboardId rt=receiptTime |
| Devices | | | |
| logger:510 | /Logger/Resource /Device/Configuration /Add | Device [deviceName] has been added | fname=deviceName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Device fileId=deviceId |
| logger:511 | /Logger/Resource /Device/Configuration /Delete | Device [deviceName] has been deleted | fname=deviceName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Device fileId=deviceId |

| Device Event Class ID | Device Event Category (cat) | Message | Additional Fields |
|-----------------------|--|--------------------------------------|---|
| logger:512 | /Logger/Resource /Device/Configuration /Update | Device [deviceName] has been updated | fname=deviceName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Device fileId=deviceId |
| Filters | | | |
| logger:500 | /Logger/Resource/Filter /Configuration/Add | Filter [filterName] has been added | fname=filterName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Filter fileId=filterId |
| logger:501 | /Logger/Resource/Filter /Configuration/Delete | Filter [filterName] has been deleted | fname=filterName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Filter fileId=filterId |
| logger:502 | /Logger/Resource/Filter /Configuration/Update | Filter [filterName] has been updated | fname=filterName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Filter fileId=filterId |
| Groups | | | |
| logger:513 | /Logger/Resource /Group/Configuration /Add | Group [groupName] has been added | fname=groupName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Group fileId=groupId |
| logger:514 | /Logger/Resource /Group/Configuration /Delete | Group [groupName] has been deleted | fname=groupName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Group fileId=groupId |

| Device Event Class ID | Device Event Category (cat) | Message | Additional Fields |
|-----------------------|---|---|--|
| logger:515 | /Logger/Resource /Group/Configuration /Update | Group [groupName] has been updated | fname=groupName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Group fileId=groupId |
| Peer Loggers | | | |
| logger:550 | /Logger/Resource /PeerLogger /Configuration/Add | Peer Logger [name] has been added | fname=Name duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Peer Logger fileId=LoggerId |
| logger:551 | /Logger/Resource /PeerLogger /Configuration/Delete | Peer Logger [name] has been deleted | fname=Name duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Peer Logger fileId=LoggerId |
| logger:570 | /Logger/Resource /Peer/Authorizations /Configuration/Add | Peer Logger authorization [name] has been added | fname=Name duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Peer Logger Authorization |
| logger:571 | /Logger/Resource /PeerLogger /Authorizations /Configuration/Delete | Peer Logger authorization [name] has been deleted | fname=Name duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Peer Logger Authorization fileId=LoggerId |
| Parsers | | | |

| Device Event Class ID | Device Event Category (cat) | Message | Additional Fields |
|--------------------------|---|---|--|
| logger:590 | /Logger/Resource /ParserDescription /Configuration/Add | Parser Description [name] has been added | fileType=Parser Description duid=1 cs4=sessionIdfile cs4Label=Session ID duser=UserName rt=receiptTime fname=parserName |
| logger:591 | /Logger/Resource /ParserDescription /Configuration/Delete | Parser Description [name] has been deleted | fileType=Parser Description cs4=sessionIdfile duser=UserName fileId=ParserID 710 duid=1 cs4Label=Session ID rt=receiptTime fname=parserName |
| logger:592 | /Logger/Resource /ParserDescription /Configuration/Update | Parser Description [name] has been updated | fileType=Parser Description cs4=sessionIdfile duser=UserName fileId=ParserID duid=1 cs4Label=Session ID rt=receiptTime fname=parserName |
| Saved Searches | | | |
| logger:540 | /Logger/Resource/ SavedSearch /Configuration/Add | Saved search [name] has been added | fname=savedSearchName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Saved Search fileId=savedSearchId |
| logger:541 | /Logger/Resource/ SavedSearch /Configuration/Delete | Saved search [name] has been deleted | fname=savedSearchName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Saved Search fileId=savedSearchId |

| Device Event Class ID | Device Event Category (cat) | Message | Additional Fields |
|-----------------------|---|---|--|
| logger:542 | /Logger/Resource/ SavedSearch /Configuration/Update | Saved search [name] has been updated | fname=savedSearchName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Saved Search fileId=savedSearchId |
| Source Types | | | |
| logger:596 | /Logger/Resource/ SourceType /Configuration/Add | Source Type [name] has been added | cs4=sessionIdfile fileType=Source Type duid=1 cs4Label=Session ID duser=UserName rt=receiptTime fname=SourceTypeName |
| logger:597 | /Logger/Resource /SourceType /Configuration/Delete | Source Type [name] has been deleted | fileType=Source Type cs4=sessionIdfile duser=UserName fileId=SourceTypeId duid=1 cs4Label=Session ID rt=receiptTime fname=SourceTypeName |
| logger:598 | /Logger/Resource /SourceType /Configuration/Update | Source Type [name] has been updated | fileType=Source Type cs4=sessionIdfile duser=UserName fileId=1SourceTypeId duid=1 cs4Label=Session ID rt=receiptTime fname=SourceTypeName |
| Storage Groups | | | |
| logger:530 | /Logger/Resource/ StorageGroup /Configuration/Add | Storage group [storageGroupName] has been added | fname=storageGroupName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Storage Group fileId=storageGroupId |

| Device Event Class ID | Device Event Category (cat) | Message | Additional Fields |
|-----------------------|--|---|--|
| logger:532 | /Logger/Resource/ StorageGroup /Configuration/Update | Storage group [storageGroupName] has been updated | fname=storageGroupName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Storage Group fileId=storageGroupId |
| Storage Rules | | | |
| logger:533 | /Logger/Resource/ StorageRule /Configuration/Add | Storage rule [name] has been added | fname=storageRuleName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Storage Rule |
| logger:535 | /Logger/Resource/ StorageRule /Configuration/Update | Storage rule [name] has been updated | fname=storageRuleName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Storage Rule |
| Storage Volume | | | |
| logger:536 | /Logger/Resource /StorageVolume/ Configuration/Add | Storage volume [name] has been added | fname=storageVolumeName duser=UserName duid=userId cs4=sessionIdfile cs4Label=Session ID fileType=Storage Volume fileId=storageVolumeId |
| Search | | | |
| logger:680 | /Logger/Search/Index /Update | Search indices have been added OR Search index has been added | cs4=sessionId fileType=Search Index Configuration duser=UserName msg=Search index has been added cn1=1 duid=1 cs4Label=Session ID rt=receiptTime cn1Label=No. of fields added |

| Device Event Class ID | Device Event Category (cat) | Message | Additional Fields |
|-------------------------|--|--|--|
| logger:690 | /Logger/Search/Options /Update | Search options have been updated | cs6=false cs7=true cs4=sessionId cs5=false cs2=false cs3=false cs1=true cs8=false cs1Label=Field Search Case Sensitivity duid=1 cs7Label=Field Summary cs8Label=Field Summary Field Discovery cs6Label=Display options raw Event cs3Label=Regex Search Unicode Case Sensitivity fileType=Search Options duser=UserName cs5Label=Regex Search Canonical Equality Check cs4Label=Session ID rt=receiptTime cs2Label=Regex Search Case Sensitivity |
| logger:710 | /Logger/Search /Canceled | Search session [sessionId] has been canceled by [user] | cs1Label=Session ID duid=1 cs1=sessionIdfile duser=UserName rt=receiptTime |
| Maintenance Mode | | | |
| logger:700 | /Logger/Server /MaintenanceMode/ Enter | Maintenance mode entered | fname=Maintenance Mode duser=UserName duid=userId cs4=sessionId cs4Label=Session ID fileType=Maintenance Mode |

Appendix F: System Health Events

The following table provides examples of system health events generated on Logger. These examples are intended to help you understand the format and various fields of the generated events.

Note: You can set up Alerts to be triggered to let you know when system health events are generated. For more information, see ["Saved Searches" on page 315](#).

The table includes information on the following system health event classes:

| Device Event Class: ID | Example |
|------------------------|--|
| cpu | |
| cpu:100 | CEF:0 ArcSight Logger 5.1.0.5780.0 cpu:100 CPU Usage 1 cat=/Monitor/CPU/Usage cn1=3 cn1Label=Percent Usage cs2=CurrentValue cs2Label=timeframe dst=192.0.2.6 dvc=192.0.2.6 end=1302739080014 rt=1302739080014 |
| disk | |
| disk:101 | CEF:0 ArcSight Logger 5.1.0.5803.0 disk:101 Root Disk Space Remaining 1 cat=/Monitor/Disk/Space/Remaining/Root cn1=99 cn1Label=Percent Available cs2=CurrentValue cs2Label=timeframe cs3=Ok cs3Label=Status cs4=Ok cs4Label=Raw Status cs5=Root cs5Label=Location cs6=Disk/Space/Remaining/Root cs6Label=Sensor Name dst=192.0.2.6 dvc=192.0.2.6 end=1303927171790 rt=1303927171790 |
| disk:102 | CEF:0 ArcSight Logger 5.1.0.5780.0 disk:102 Disk bytes read 1 cat=/Monitor/Disk/Read cn1=373524 cn1Label=Kb Read cs2=SinceStartup cs2Label=timeframe cs6=c0d0 cs6Label=Partition Name dst=192.0.2.6 dvc=192.0.2.6 end=1302743760036 rt=1302743760036 |
| disk:103 | CEF:0 ArcSight Logger 5.1.0.5780.0 disk:103 Disk bytes written 1 cat=/Monitor/Disk/Write cn1=24474998 cn1Label=Kb Written cs2=SinceStartup cs2Label=timeframe cs6=c0d0 cs6Label=Partition Name dst=192.0.2.6 dvc=192.0.2.6 end=1302743760038 rt=1302743760038 |
| eps | |
| eps:100 | CEF:0 ArcSight Logger 5.1.0.5780.0 eps:100 Overall Receiver EPS 1 cat=/Monitor/Receiver/All/EPS cn1=0 cn1Label=EPS cs2=SinceLastMonitorEvent cs2Label=timeframe dst=192.0.2.6 dvc=192.0.2.6 end=1302733680034 rt=1302733680034 |
| eps:101 | CEF:0 ArcSight Logger 5.1.0.5780.0 eps:101 Overall Forwarder EPS 1 cat=/Monitor/Forwarder/All/EPS cn1=0 cn1Label=EPS cs2=SinceLastMonitorEvent cs2Label=timeframe dst=192.0.2.6 dvc=192.0.2.6 |

| Device Event Class: ID | Example |
|------------------------------|--|
| eps:102 | CEF:0 ArcSight Logger 6.1.0.0.1 eps:102 Individual Receiver EPS 1 cat=/Monitor/Receiver/EPS/Individual cn1=0 cn1Label=EPS cn2=0 cn2Label=EVENT COUNT cs1=TCP cs1Label=Receiver Type cs2=SinceLastMonitorEvent cs2Label=timeframe cs3=up cs3Label=STATUS cs6=TCP Receiver cs6Label=Receiver name dst=192.0.2.6 dvc=192.0.2.6 end=1420620420064 rt=1420620420064 |
| eps:103 | CEF:0 ArcSight Logger 6.1.0.0.1 eps:103 Individual Forwarder EPS 1 cat=/Monitor/Forwarder/EPS/Individual cn1=0 cn1Label=EPS cn2=0 cn2Label=EVENT COUNT cs1=TCP cs1Label=Forwarder Type cs2=SinceLastMonitorEvent cs2Label=timeframe cs3=up cs3Label=STATUS cs6=TCP Forwarder cs6Label=Forwarder name dst=192.0.2.6 dvc=192.0.2.6 end=1420620420064 rt=1420620420064 |
| hardware | |
| hardware:101 | CEF:0 ArcSight Logger 5.1.0.5784.0 hardware:101 Electrical (Current) OK 1 cat=/Monitor/Sensor/Current/Ok cs1=0.80 Amps cs1Label=Raw Value cs2=CurrentValue cs2Label=timeframe cs3=Ok cs3Label=Status cs4=ok cs4Label=Raw Status cs5=10.2 (Power Supply) cs5Label=Location cs6=Current 2 cs6Label=Sensor Name dst=192.0.2.5 dvc=192.0.2.5 end=1303937520837 rt=1303937520837 |
| hardware:102 | CEF:0 ArcSight Logger 5.1.0.5776.0 hardware:102 Electrical (Current) Degraded 5 cat=/Monitor/Sensor/Current/Degraded cs1=126 Watts cs1Label=Raw Value cs2=CurrentValue cs2Label=timeframe cs3=Degraded cs3Label=Status cs4=inc cs4Label=Raw Status cs5Label=Location cs6=Power Meter cs6Label=Sensor Name dst=192.0.2.4 dvc=192.0.2.4 end=1302817019262 rt=1302817019262 |
| hardware:103 | CEF:0 ArcSight Logger 5.1.0.5776.0 hardware:103 Electrical (Current) Failed 8 cat=/Monitor/Sensor/Current/Failed cs1=126 Watts cs1Label=Raw Value cs2=CurrentValue cs2Label=timeframe cs3=Failed cs3Label=Status cs4=lcr cs4Label=Raw Status cs5Label=Location cs6=Power Meter cs6Label=Sensor Name dst=192.0.2.4 dvc=192.0.2.4 end=1302817019262 rt=1302817019262 |
| hardware:111 | CEF:0 ArcSight Logger 5.1.0.5780.0 hardware:111 Electrical (Voltage) OK 1 cat=/Monitor/Sensor/Voltage/Ok cs1=State Deasserted cs1Label=Raw Value cs2=CurrentValue cs2Label=timeframe cs3=Ok cs3Label=Status cs4=ok cs4Label=Raw Status cs5=3.1 (Processor) cs5Label=Location cs6=VCORE cs6Label=Sensor Name dst=192.0.2.6 dvc=192.0.2.6 end=1302819047959 rt=1302819047959 |
| hardware:112 | CEF:0 ArcSight Logger 5.1.0.5780.0 hardware:112 Electrical (Voltage) Degraded 5 cat=/Monitor/Sensor/Voltage/Degraded cs1=State Deasserted cs1Label=Raw Value cs2=CurrentValue cs2Label=timeframe cs3=Degraded cs3Label=Status cs4=inc cs4Label=Raw Status cs5=3.1 (Processor) cs5Label=Location cs6=VCORE cs6Label=Sensor Name dst=192.0.2.6 dvc=192.0.2.6 end=1302819047959 rt=1302819047959 |
| hardware:113 | CEF:0 ArcSight Logger 5.1.0.5780.0 hardware:113 Electrical (Voltage) Failed 8 cat=/Monitor/Sensor/Voltage/Failed cs1=State Deasserted cs1Label=Raw Value cs2=CurrentValue cs2Label=timeframe cs3=Failed cs3Label=Status cs4=lcr cs4Label=Raw Status cs5=3.1 (Processor) cs5Label=Location cs6=VCORE cs6Label=Sensor Name dst=192.0.2.6 dvc=192.0.2.6 end=1302819047959 rt=1302819047959 |

| Device Event Class: ID | Example |
|------------------------|--|
| hardware:121 | CEF:0 ArcSight Logger 5.1.0.5803.0 hardware:121 Battery OK 1 cat=/Monitor/Sensor/Battery/Ok cs1=cs1Label=Raw Value cs2=CurrentValue cs2Label=timeframe cs3=Ok cs3Label=Status cs4=ok cs4Label=Raw Status cs5=7.1 (System Board) cs5Label=Location cs6=CMOS Battery cs6Label=Sensor Name dst=192.0.2.6 dvc=192.0.2.6 end=1303937972008 rt=1303937972008 |
| hardware:122 | CEF:0 ArcSight Logger 5.1.0.5803.0 hardware:122 Battery Degraded 5 cat=/Monitor/Sensor/Battery/Degraded cs1=cs1Label=Raw Value cs2=CurrentValue cs2Label=timeframe cs3=Degraded cs3Label=Status cs4=Inc cs4Label=Raw Status cs5=7.1 (System Board) cs5Label=Location cs6=CMOS Battery cs6Label=Sensor Name dst=192.0.2.6 dvc=192.0.2.6 end=1303937972008 rt=1303937972008 |
| hardware:123 | CEF:0 ArcSight Logger 5.1.0.5803.0 hardware:123 Battery Failed 8 cat=/Monitor/Sensor/Battery/Degraded cs1=cs1Label=Raw Value cs2=CurrentValue cs2Label=timeframe cs3=Failed cs3Label=Status cs4=lcr cs4Label=Raw Status cs5=7.1 (System Board) cs5Label=Location cs6=CMOS Battery cs6Label=Sensor Name dst=192.0.2.6 dvc=192.0.2.6 end=1303937972008 rt=1303937972008 |
| hardware:131 | CEF:0 ArcSight Logger 5.1.0.5780.0 hardware:131 Fan OK 1 cat=/Monitor/Sensor/Fan/Ok cs1=29.01 unspecified cs1Label=Raw Value cs2=CurrentValue cs2Label=timeframe cs3=Ok cs3Label=Status cs4=Inc cs4Label=Raw Status cs5=7.1 (System Board) cs5Label=Location cs6=Fan Block 1 cs6Label=Sensor Name dst=192.0.2.1 dvc=192.0.2.1 end=1302823237825 rt=1302823237825 |
| hardware:132 | |
| hardware:133 | CEF:0 ArcSight Logger 5.1.0.5780.0 hardware:133 Fan Failure 8 cat=/Monitor/Sensor/Fan/Failed cs1=29.01 unspecified cs1Label=Raw Value cs2=CurrentValue cs2Label=timeframe cs3=Failed cs3Label=Status cs4=lcr cs4Label=Raw Status cs5=7.1 (System Board) cs5Label=Location cs6=Fan Block 1 cs6Label=Sensor Name dst=192.0.2.1 dvc=192.0.2.1 end=1302823237825 rt=1302823237825 |
| hardware:141 | CEF:0 ArcSight Logger 5.1.0.5803.0 hardware:141 Power Supply OK 1 cat=/Monitor/Sensor/PowerSupply/Ok cs1=cs1Label=Raw Value cs2=CurrentValue cs2Label=timeframe cs3=Ok cs3Label=Status cs4=ok cs4Label=Raw Status cs5=10.1 (Power Supply) cs5Label=Location cs6=Status cs6Label=Sensor Name dst=192.0.2.6 dvc=192.0.2.6 end=1303938572149 rt=1303938572149 |
| hardware:142 | |
| hardware:143 | CEF:0 ArcSight Logger 5.1.0.5776.0 hardware:143 Power Supply Failed 8 cat=/Monitor/Sensor/PowerSupply/Failed cs1=0 Watts cs1Label=Raw Value cs2=CurrentValue cs2Label=timeframe cs3=Failed cs3Label=Status cs4=lcr cs4Label=Raw Status cs5=10.2 (Power Supply) cs5Label=Location cs6=Power Supply 2 cs6Label=Sensor Name dst=192.0.2.4 dvc=192.0.2.4 end=1302817019263 rt=1302817019263 |
| hardware:151 | CEF:0 ArcSight Logger 5.1.0.5776.0 hardware:151 Temperature OK 1 cat=/Monitor/Sensor/Temperature/Ok cs1=17 degrees C cs1Label=Raw Value cs2=CurrentValue cs2Label=timeframe cs3=Ok cs3Label=Status cs4=ok cs4Label=Raw Status cs5=64.1 (Unknown (0x40)) cs5Label=Location cs6=Temp 1 cs6Label=Sensor Name dst=192.0.2.4 dvc=192.0.2.4 end=1302823560051 rt=1302823560051 |

| Device Event Class: ID | Example |
|------------------------------|---|
| hardware:152 | |
| hardware:153 | |
| memory | |
| memory:100 | CEF:0 ArcSight Logger 5.1.0.5780.0 memory:100 Platform Memory Usage 1 cat=/Monitor/Memory/Usage/Platform cn1=2757 cn1Label=MB Used cs2=CurrentValue cs2Label=timeframe dst=192.0.2.6 dvc=192.0.2.6 end=1302797940018 rt=1302797940018 |
| network | |
| network:100 | CEF:0 ArcSight Logger 5.1.0.5780.0 network:100 Network Usage - Inbound 1 cat=/Monitor/Network/Usage/In cn1=41837428 cn1Label=Bytes Received cs2=SinceStartup cs2Label=timeframe cs6=eth0 cs6Label=Interface Name dst=192.0.2.6 dvc=192.0.2.6 end=1302733620026 rt=1302733620026 |
| network:101 | CEF:0 ArcSight Logger 5.1.0.5780.0 network:101 Network Usage - Outbound 1 cat=/Monitor/Network/Usage/Out cn1=158442791 cn1Label=Bytes Sent cs2=SinceStartup cs2Label=timeframe cs6=eth0 cs6Label=Interface Name dst=192.0.2.6 dvc=192.0.2.6 end=1302733620028 rt=1302733620028 |
| raid | |
| raid:101 | CEF:0 ArcSight Logger 5.1.0.5780.0 raid:101 RAID Controller OK 1 cat=/Monitor/RAID/Controller/Ok cs1=Type: RAID-5 cs1Label=Raw Value cs2=CurrentValue cs2Label=timeframe cs3=Ok cs3Label=Status cs4=Optimal cs4Label=Raw Status cs5=RAIDController/Configuration cs5Label=Location cs6=RAIDController/Configuration cs6Label=Sensor Name dst=192.0.2.6 dvc=192.0.2.6 end=1302886250104 rt=1302886250104 |
| raid:102 | CEF:0 ArcSight Logger 5.1.0.5780.0 raid:102 RAID Controller Degraded 5 cat=/Monitor/RAID/ControllerDegraded cs1=Type: RAID-5 Critical Disks: 0 Failed Disks: 0 cs1Label=Raw Value cs2=CurrentValue cs2Label=timeframe cs3=Degraded cs3Label=Status cs4=Degraded cs4Label=Raw Status cs5=RAIDController/Configuration cs5Label=Location cs6=RAIDController/Configuration cs6Label=Sensor Name dst=192.0.2.6 dvc=192.0.2.6 end=1302826128482 rt=1302826128482 |
| raid:103 | |
| raid:111 | CEF:0 ArcSight Logger 5.1.0.5776.0 raid:111 RAID BBU OK 1 cat=/Monitor/RAID/BBU/Ok cs1=Battery/Capacitor Count: 1 cs1Label=Raw Value cs2=CurrentValue cs2Label=timeframe cs3=Ok cs3Label=Status cs4=OK cs4Label=Raw Status cs5=RAIDController/Battery/bbu cs5Label=Location cs6=RAIDController/Battery/bbu cs6Label=Sensor Name dst=192.0.2.4 dvc=192.0.2.4 end=1302890169285 rt=1302890169285 |

| Device Event Class: ID | Example |
|------------------------|---|
| raid:112 | CEF:0 ArcSight Logger 5.1.0.5780.0 raid:112 RAID BBU Degraded 5 cat=/Monitor/RAID/BBU/Degraded cs1=Fully Charged: false Remaining Time Alarm: false Remaining Capacity Alarm: false Over Charged: false isSOHGood: true cs1Label=Raw Value cs2=CurrentValue cs2Label=timeframe cs3=Degraded cs3Label=Status cs4=Degraded cs4Label=Raw Status cs5=RAIDController/Battery/bbu cs5Label=Location cs6=RAIDController/Battery/bbu cs6Label=Sensor Name dst=192.0.2.6 dvc=192.0.2.6 end=1302820608015 rt=1302820608015 |
| raid:113 | |
| raid:121 | CEF:0 ArcSight Logger 5.1.0.5780.0 raid:121 RAID Disk OK 1 cat=/Monitor/RAID/DISK/Ok cs1=Port: 1I Box: 1 Bay: 1 Size: 500 GB Serial Number: 9SP24JD5 cs1Label=Raw Value cs2=CurrentValue cs2Label=timeframe cs3=Ok cs3Label=Status cs4=OK cs4Label=Raw Status cs5=Port: 1I Box: 1 Bay: 1 Serial Number: 9SP24JD5 cs5Label=Location cs6=RAIDController/Port/p0 cs6Label=Sensor Name dst=192.0.2.1 dvc=192.0.2.1 end=1302849041777 rt=1302849041777 |
| raid:122 | CEF:0 ArcSight Logger 5.1.0.5776.0 raid:122 RAID Disk Rebuilding 5 cat=/Monitor/RAID/DISK/Rebuilding cs1=Port: 2I Box: 1 Bay: 1 Size: 1 TB Serial Number: WMATV6348517 cs1Label=Raw Value cs2=CurrentValue cs2Label=timeframe cs3=Rebuilding cs3Label=Status cs4=Rebuilding cs4Label=Raw Status cs5=Port: 2I Box: 1 Bay: 1 Serial Number: WMATV6348517 cs5Label=Location cs6=RAIDController/Port/p0 cs6Label=Sensor Name dst=192.0.2.4 dvc=192.0.2.4 end=1302826980530 rt=1302826980530 |
| raid:123 | CEF:0 ArcSight Logger 5.1.0.5780.0 raid:123 RAID Disk Failed 8 cat=/Monitor/RAID/DISK/Failed cs1=Port: 1I Box: 1 Bay: 2 Size: 500 GB Serial Number: 9SP23M08 cs1Label=Raw Value cs2=CurrentValue cs2Label=timeframe cs3=Failed cs3Label=Status cs4=Failed cs4Label=Raw Status cs5=Port: 1I Box: 1 Bay: 2 Serial Number: 9SP23M08 cs5Label=Location cs6=RAIDController/Port/p1 cs6Label=Sensor Name dst=192.0.2.1 dvc=192.0.2.1 end=1302826358346 rt=1302826358346 |
| search | |
| search:100 | CEF:0 ArcSight Logger 5.1.0.5780.0 search:100 Number of Searches Performed 1 cat=/Monitor/Search cn1=0 cn1Label=Number of Searches cs2=SinceStartup cs2Label=timeframe dst=192.0.2.6 dvc=192.0.2.6 end=1302741300026 rt=1302741300026 |
| storagegroup | |
| storagegroup: 100 | CEF:0 ArcSight Logger 5.1.0.5803.0 storagegroup:100 Storage Group Space Used 1 cat=/Monitor/StorageGroup/Space/Used cn1=1 cn1Label=Percent Used cn2=7 cn2Label=retention period (days) cn3=1024 cn3Label=used (MB) cs2=CurrentValue cs2Label=timeframe dst=192.0.2.6 dvc=192.0.2.6 end=1303928072008 fileType=storageGroup fName=Default Storage Group fsize=1534 rt=1303928072008 |

Appendix G: Event Field Name Mappings

The nomenclature for field names depends on the function area of the Logger. The following table provides the mapping between these types of names.

- **Database Name:** Field name created in the database when you index this field. There will be no database name for a field if you have not indexed it. This field name is used when creating a SQL query for generating a report.
- **Search Results:** Field name displayed in the search results when your search returns data in this field.
- **CEF Field Name:** The key or field name as defined in Implementing ArcSight CEF. For a downloadable a copy of this guide, search for "ArcSight Common Event Format (CEF) Guide" in the [Micro Focus Security Community](#).
- **Reports:** Field name displayed in a report containing data from this field.

| Database Name | Search Results | CEF Field Name | Reports |
|-------------------------|---------------------|---------------------|-----------------------|
| arc_agentAddress | agentAddress | agt | Agent Address |
| arc_agentHostName | agentHostName | ahost | Agent Host Name |
| arc_agentNtDomain | agentNtDomain | agentNtDomain | Agent NT Domain |
| arc_agentSeverity | agentSeverity | Severity | Severity |
| arc_agentType | agentType | at | Agent Type |
| arc_agentZone | agentZone | agentZone | Agent Zone |
| arc_agentZoneName | agentZoneName | agentZoneName | Agent Zone Name |
| arc_agentZoneResource | agentZoneResource | agentZoneResource | Agent Zone Resource |
| arc_agentZoneURI | agentZoneURI | agentZoneURI | Agent Zone URI |
| arc_applicationProtocol | applicationProtocol | app | Application Protocol |
| arc_baseEventCount | baseEventCount | cnt | Base Event Count |
| arc_bytesIn | bytesIn | in | Bytes In |
| arc_bytesOut | bytesOut | out | Bytes Out |
| arc_categoryBehavior | categoryBehavior | categoryBehavior | Category Behavior |
| arc_categoryDeviceGroup | categoryDeviceGroup | categoryDeviceGroup | Category Device Group |
| arc_categoryObject | categoryObject | categoryObject | Category Object |
| arc_categoryOutcome | categoryOutcome | categoryOutcome | Category Outcome |

| Database Name | Search Results | CEF Field Name | Reports |
|----------------------------------|------------------------------|------------------------------|--------------------------------|
| arc_categorySignificance | categorySignificance | categorySignificance | Category Significance |
| arc_categoryTechnique | categoryTechnique | categoryTechnique | Category Technique |
| arc_customerName | customerName | customerName | Customer Name |
| arc_destinationAddress | destinationAddress | dst | Destination Address |
| arc_destinationDnsDomain | destinationDnsDomain | destinationDnsDomain | Destination DNS Domain |
| arc_destinationHostName | destinationHostName | dhost | Destination Host Name |
| arc_destinationMacAddress | destinationMacAddress | dmac | Destination Mac Address |
| arc_destinationNtDomain | destinationNtDomain | dntdom | Destination NT Domain |
| arc_destinationPort | destinationPort | dpt | Destination Port |
| arc_destinationProcessName | destinationProcessName | dproc | Destination Process Name |
| arc_destinationServiceName | destinationServiceName | destinationServiceName | Destination Service Name |
| arc_destinationTranslatedAddress | destinationTranslatedAddress | destinationTranslatedAddress | Destination Translated Address |
| arc_destinationUserId | destinationUserId | duid | Destination User ID |
| arc_destinationUserName | destinationUserName | duser | Destination User Name |
| arc_destinationUserPrivileges | destinationUserPrivileges | dpriv | Destination User Privileges |
| arc_destinationZone | destinationZone | destinationZone | Destination Zone |
| arc_destinationZoneName | destinationZoneName | destinationZoneName | Destination Zone Name |
| arc_destinationZoneResource | destinationZoneResource | destinationZoneResource | Destination Zone Resource |
| arc_destinationZoneURI | destinationZoneURI | destinationZoneURI | Destination Zone URI |
| arc_deviceAction | deviceAction | act | Device Action |
| arc_deviceAddress | deviceAddress | dvc | Device Address |
| arc_deviceCustomDate1 | deviceCustomDate1 | deviceCustomDate1 | Device Custom Date 1 |
| arc_deviceCustomDate1Label | deviceCustomDate1Label | deviceCustomDate1Label | Device Custom Date 1 Label |
| arc_deviceCustomDate2 | deviceCustomDate2 | deviceCustomDate2 | Device Custom Date 2 |
| arc_deviceCustomDate2Label | deviceCustomDate2Label | deviceCustomDate2Label | Device Custom Date 2 Label |

| Database Name | Search Results | CEF Field Name | Reports |
|------------------------------|--------------------------|------------------------|------------------------------|
| arc_deviceCustomNumber1 | deviceCustomNumber1 | cn1 | Device Custom Number 1 |
| arc_deviceCustomNumber1Label | deviceCustomNumber1Label | cn1Label | Device Custom Number 1 Label |
| arc_deviceCustomNumber2 | deviceCustomNumber2 | cn2 | Device Custom Number 2 |
| arc_deviceCustomNumber2Label | deviceCustomNumber2Label | cn2Label | Device Custom Number 2 Label |
| arc_deviceCustomNumber3 | deviceCustomNumber3 | cn3 | Device Custom Number 3 |
| arc_deviceCustomNumber3Label | deviceCustomNumber3Label | cn3Label | Device Custom Number 3 Label |
| arc_deviceCustomString1 | deviceCustomString1 | cs1 | Device Custom String 1 |
| arc_deviceCustomString1Label | deviceCustomString1Label | cs1Label | Device Custom String 1 Label |
| arc_deviceCustomString2 | deviceCustomString2 | cs2 | Device Custom String 2 |
| arc_deviceCustomString2Label | deviceCustomString2Label | cs2Label | Device Custom String 2 Label |
| arc_deviceCustomString3 | deviceCustomString3 | cs3 | Device Custom String 3 |
| arc_deviceCustomString3Label | deviceCustomString3Label | cs3Label | Device Custom String 3 Label |
| arc_deviceCustomString4 | deviceCustomString4 | cs4 | Device Custom String 4 |
| arc_deviceCustomString4Label | deviceCustomString4Label | cs4Label | Device Custom String 4 Label |
| arc_deviceCustomString5 | deviceCustomString5 | cs5 | Device Custom String 5 |
| arc_deviceCustomString5Label | deviceCustomString5Label | cs5Label | Device Custom String 5 Label |
| arc_deviceCustomString6 | deviceCustomString6 | cs6 | Device Custom String 6 |
| arc_deviceCustomString6Label | deviceCustomString6Label | cs6Label | Device Custom String 6 Label |
| arc_deviceEventCategory | deviceEventCategory | cat | Device Event Category |
| arc_deviceEventClassId | deviceEventClassId | Signature ID | Signature Id |
| arc_deviceExternalId | deviceExternalId | deviceExternalId | Device External Id |
| arc_deviceHostName | deviceHostName | dvchost | Device Host Name |
| arc_deviceInboundInterface | deviceInboundInterface | deviceInboundInterface | Device Inbound Interface |

| Database Name | Search Results | CEF Field Name | Reports |
|-----------------------------|-------------------------|-------------------------|---------------------------|
| arc_deviceOutboundInterface | deviceOutboundInterface | deviceOutboundInterface | Device Outbound Interface |
| arc_deviceProduct | deviceProduct | Device Product | Device Product |
| arc_deviceReceiptTime | deviceReceiptTime | rt | Device Receipt Time |
| arc_deviceSeverity | deviceSeverity | deviceSeverity | Device Severity |
| arc_deviceVendor | deviceVendor | Device Vendor | Device Vendor |
| arc_deviceVersion | deviceVersion | Device Version | Device Version |
| arc_deviceZone | deviceZone | deviceZone | Device Zone |
| arc_deviceZoneName | deviceZoneName | deviceZoneName | Device Zone Name |
| arc_deviceZoneResource | deviceZoneResource | deviceZoneResource | Device Zone Resource |
| arc_deviceZoneURI | deviceZoneURI | deviceZoneURI | Device Zone URI |
| arc_endTime | endTime | end | End Time |
| arc_eventId | eventId | eventId | Event Id |
| arc_externalId | externalId | externalId | External Id |
| arc_fileName | fileName | fname | File Name |
| arc_filePath | filePath | filePath | File Path |
| arc_flexDate1 | flexDate1 | flexDate1 | Flex Date 1 |
| arc_flexDate1Label | flexDate1Label | flexDate1Label | Flex Date 1 Label |
| arc_flexNumber1 | flexNumber1 | flexNumber1 | Flex Number 1 |
| arc_flexNumber1Label | flexNumber1Label | flexNumber1Label | Flex Number 1 Label |
| arc_flexNumber2 | flexNumber2 | flexNumber2 | Flex Number 2 |
| arc_flexNumber2Label | flexNumber2Label | flexNumber2Label | Flex Number 2 Label |
| arc_flexString1 | flexString1 | flexString1 | Flex String 1 |
| arc_flexString1Label | flexString1Label | flexString1Label | Flex String 1 Label |
| arc_flexString2 | flexString2 | flexString2 | Flex String 2 |
| arc_flexString2Label | flexString2Label | flexString2Label | Flex String 2 Label |
| arc_message | message | msg | Message |
| arc_name | name | Name | Name |
| arc_priority | priority | priority | Priority |

| Database Name | Search Results | CEF Field Name | Reports |
|------------------------------|--------------------------|--------------------------|----------------------------|
| arc_requestClientApplication | requestClientApplication | requestClientApplication | Request Client Application |
| arc_requestContext | requestContext | requestContext | Request Context |
| arc_requestMethod | requestMethod | requestMethod | Request Method |
| arc_requestUrl | requestUrl | request | Request URL |
| arc_requestUrlFileName | requestUrlFileName | requestUrlFileName | Request URL File Name |
| arc_requestUrlQuery | requestUrlQuery | requestUrlQuery | Request URL Query |
| arc_sessionId | sessionId | sessionId | Session Id |
| arc_sourceAddress | sourceAddress | src | Source Address |
| arc_sourceHostName | sourceHostName | shost | Source Host Name |
| arc_sourceMacAddress | sourceMacAddress | smac | Source Mac Address |
| arc_sourceNtDomain | sourceNtDomain | sntdom | Source NT Domain |
| arc_sourcePort | sourcePort | spt | Source Port |
| arc_sourceProcessName | sourceProcessName | sproc | Source Process Name |
| arc_sourceServiceName | sourceServiceName | sourceServiceName | Source Service Name |
| arc_sourceTranslatedAddress | sourceTranslatedAddress | sourceTranslatedAddress | Source Translated Address |
| arc_sourceUserId | sourceUserId | suid | Source User Id |
| arc_sourceUserName | sourceUserName | suser | Source User Name |
| arc_sourceUserPrivileges | sourceUserPrivileges | spriv | Source User Privileges |
| arc_sourceZone | sourceZone | sourceZone | Source Zone |
| arc_sourceZoneName | sourceZoneName | sourceZoneName | Source Zone Name |
| arc_sourceZoneResource | sourcezoneResource | sourceZoneResource | Source Zone Resource |
| arc_sourceZoneURI | sourceZoneURI | sourceZoneURI | Source Zone URI |
| arc_startTime | startTime | start | Start Time |
| arc_transportProtocol | transportProtocol | proto | Transport Protocol |
| arc_type | type | type | Type |
| arc_vulnerabilityExternalID | vulnerabilityExternalID | vulnerabilityExternalID | Vulnerability External Id |
| arc_vulnerabilityURI | VulnerabilityURI | vulnerabilityURI | Vulnerability URI |

Appendix H: Logger Content

The following topics provide information about the out-of-box Logger reports:

- [Reports](#)608
- [Parameters](#)646
- [System Filters](#)652

Reports

Logger provides the reports described in the tables below. In the Logger UI, these reports are listed in categories, accessible through the Category Explorer (in the left pane). For example, the "Top Infected Systems" report is listed in the Anti-Virus category, which is listed in the parent category called [Device Monitoring](#).

The reports contain hyperlinks that drill down to other reports. For example, the report "Most Common Events" displays a field called **Count**. Clicking on the **Count** field drills down to the report [Target Attack Counts by Severity](#), which provides additional detail information, as shown in the following figure. The drill-down relationship between reports is shown in the tables below.

| Severity | Name | Count |
|---------------------------|---|----------------------|
| Very-High | SMB: WinLogon DoS | 2089 |
| Very-High | IRC: Trojan.IrcBounce Command Channel | 70 |
| Very-High | Snort Alarm [1:2404:5] | 58 |
| Very-High | Host is DOWN | 41 |
| Very-High | ids syn attack | 26 |
| Very-High | RCRS/POP3_INVALID_ARG_TO_QUIT | 16 |

| Severity | Target Zone | Target Address | Count |
|-----------|---|----------------|-------|
| Very-High | /All Zones/ArcSight System/Private Address Space Zones/RFC1918: 10.0.0.0-10.255.255.255 | 10.0.0.10 | 57 |
| Very-High | /All Zones/ArcSight System/Private Address Space Zones/RFC1918: 10.0.0.0-10.255.255.255 | 10.156.106.101 | 25 |
| Very-High | /All Zones/ArcNet Zones/sj2.west.arcnet.com - internal | 10.0.112.187 | 10 |
| Very-High | /All Zones/ArcSight System/Private Address Space Zones/RFC1918: 10.0.0.0-10.255.255.255 | 10.0.0.10 | 10 |
| Very-High | /All Zones/ArcSight System/Private Address Space Zones/RFC1918: 172.16.0.0-172.31.255.255 | 172.16.5.157 | 8 |

Logger provides the following top-level categories:

- [Device Monitoring](#)609
- [Foundation](#)618

- [Logger Administration](#)633
- [SANS Top 5](#)633
- [OWASP](#)638
- [Cloud](#) 641

Device Monitoring

This category provides a device or application based view on events.

The following categories are located under the Device Monitoring category:

- [Anti-Virus](#)609
- [CrossDevice](#)610
- [Database](#)613
- [Firewall](#)613
- [IDS-IPS](#) 614
- [Identity Management](#)615
- [Network](#)615
- [Operating System](#)616
- [VPN](#)617
- [DNS](#)618

Anti-Virus

This is a sub-category of the Device Monitoring category, focusing on events related to Anti-Virus systems.

The Anti-Virus category is located under the following path.

Device Monitoring\Anti-Virus

The Anti-Virus category reports are listed in the following table.

Anti-Virus

| Report | Description | Drill Down | Parameters |
|--|---|------------|------------|
| Errors Detected in Anti-Virus Deployment | This report shows a summary of information on the anti-virus errors, including the Anti-Virus product information, host details, error information, and the number of errors. | none | none |
| Failed Anti-Virus Updates | This report displays a table with the Device Vendor, Device Product Target Zone Name, Target Host Name, Target Address, and Minute (EndTime). | none | none |

Anti-Virus, continued

| Report | Description | Drill Down | Parameters |
|-------------------------------------|--|------------|------------|
| Top Infected Systems | This report displays summaries of the systems reporting the most infections. | none | none |
| Update Summary | This report shows a summary and details of anti-virus update activity. | none | none |
| Virus Activity by Hour | This report shows malware activity by hour. | none | none |
| Virus Activity Summary | This report summarizes the virus activity in the organization. | none | none |
| Virus Activity by Hostname | This report identifies virus activity by host name. Host name should be provided while running the report. | none | none |
| Anti-Virus Stopped or Paused Events | This report lists the stopped anti-virus or paused events. | none | none |

CrossDevice

This is a sub-category of the Device Monitoring category. It provides information on events that are similar across devices, e.g., logins, start up and shut down, etc.

The CrossDevice category is located under the following path.

Device Monitoring\CrossDevice

The CrossDevice category reports are listed in the following table.

CrossDevice

| Report | Description | Drill Down | Params |
|-----------------------------|---|--|--------|
| Bandwidth Usage by Hour | This report shows the network bandwidth usage per hour by device type. Note that the bandwidth values are based on all reported traffic, including traffic within the network, as well as traffic to and from internal and external sources. There is a parameter allowing the limitation of the devices to one of the following: Firewalls, Network Equipment, or VPNs. By default, the parameter is set to all devices and applications that report data. | The Reporting Device field drill downs to the Bandwidth Usage by Hour report. This report drills down to itself. | none |
| Bandwidth Usage by Protocol | This report shows all the protocols sorted by bandwidth usage, by device type. Note that the bandwidth values are based on all reported traffic, including traffic within the network, as well as traffic to and from internal and external sources. There is a parameter allowing the limitation of the devices to one of the following: Firewalls, Network Equipment, or VPNs. By default, the parameter is set to all devices and applications that report data. | The Reporting Device field drill downs to the Bandwidth Usage by Protocol report. This report drills down to itself. | none |

CrossDevice, continued

| Report | Description | Drill Down | Params |
|--------------------------------------|--|---|--------|
| By User Account - Accounts Created | This report shows all newly created accounts that were reported to Logger. | none | none |
| Configuration Changes by Type | This report shows recent configuration changes that were reported to Logger. | The Reporting Device field drill downs to the Configuration Changes by Type report. This report drills down to itself. | none |
| Configuration Changes by User | This report shows recent configuration changes that were reported to Logger. | The Reporting Device field drill downs to the Configuration Changes by User report. This report drills down to itself. | none |
| Failed Login Attempts | This report shows authentication failures from login attempts by hour. There is a parameter allowing the limitation of the devices to one of the following: Database, Firewalls, Identity Management systems, Network Equipment, Operating Systems, or VPNs. By default, the parameter is set to all devices and applications that report data. | The Reporting Device field drill downs to the Failed Login Attempts report. This report drills down to itself. | none |
| Failed Logins by Destination Address | This report shows authentication failures from login attempts by destination address. There is a parameter allowing the limitation of the devices to one of the following: Database, Firewalls, Identity Management systems, Network Equipment, Operating Systems, or VPNs. By default, the parameter is set to all devices and applications that report data. | The Reporting Device field drill downs to the Failed Logins by Destination Address report. This report drills down to itself. | none |
| Failed Logins by Source Address | This report shows authentication failures from login attempts by source address. There is a parameter allowing the limitation of the devices to one of the following: Database, Firewalls, Identity Management systems, Network Equipment, Operating Systems, or VPNs. By default, the parameter is set to all devices and applications that report data. | The Reporting Device field drill downs to the Failed Logins by Source Address report. This report drills down to itself. | none |
| Failed Logins by User | This report shows authentication failures from login attempts by user. There is a parameter allowing the limitation of the devices to one of the following: Database, Firewalls, Identity Management systems, Network Equipment, Operating Systems, or VPNs. By default, the parameter is set to all devices and applications that report data. | The Reporting Device field drill downs to the Failed Logins by User report. This report drills down to itself. | none |

CrossDevice, continued

| Report | Description | Drill Down | Params |
|--|--|---|--------|
| Login Event Audit | This report shows all authentication events. There is a parameter allowing the limitation of the devices to one of the following: Database, Firewalls, Identity Management systems, Network Equipment, Operating Systems, or VPNs. By default, the parameter is set to all devices and applications that report data. | The Reporting Device field drill downs to the Login Event Audit report. This report drills down to itself. | none |
| Password Changes | This report shows all password changes that were reported to Logger. | The Reporting Device field drill downs to the Password Changes report. This report drills down to itself. | none |
| Successful Logins by Destination Address | This report shows successful authentication events by destination addresses. There is a parameter allowing the limitation of the devices to one of the following: Database, Firewalls, Identity Management systems, Network Equipment, Operating Systems, or VPNs. By default, the parameter is set to all devices and applications that report data. | The Reporting Device field drill downs to the Successful Logins by Destination Address report. This report drills down to itself. | none |
| Successful Logins by Source Address | This report shows successful authentication events by source addresses. There is a parameter allowing the limitation of the devices to one of the following: Database, Firewalls, Identity Management systems, Network Equipment, Operating Systems, or VPNs. By default, the parameter is set to all devices and applications that report data. | The Reporting Device field drill downs to the Successful Logins by Source Address report. This report drills down to itself. | none |
| Successful Logins by User | This report shows successful authentication events by user. There is a parameter allowing the limitation of the devices to one of the following: Database, Firewalls, Identity Management systems, Network Equipment, Operating Systems, or VPNs. By default, the parameter is set to all devices and applications that report data. | The Reporting Device field drill downs to the Successful Logins by User report. This report drills down to itself. | none |
| Top Bandwidth Hosts | This report shows the top hosts, sorted by bandwidth usage. Note that the bandwidth values are based on all reported traffic, including traffic within the network, as well as traffic to and from internal and external sources. There is a parameter allowing the limitation of the devices to one of the following: Firewalls, Network Equipment, or VPNs. By default, the parameter is set to all devices and applications that report data. | none | none |

CrossDevice, continued

| Report | Description | Drill Down | Params |
|---|---|---|--------|
| Top Hosts by Number of Connections | This report shows a summary of the number of connections by the top hosts. There is a parameter allowing the limitation of the devices to one of the following: Firewalls, Network Equipment, or VPNs. By default, the parameter is set to all devices and applications that report data. | The Reporting Device field drill downs to the Top Hosts by Number of Connections report. This report drills down to itself. | none |
| Account Creation Deletion and Modifications | This report shows a summary of account creation, deletion and modification in the organization. | none | none |
| Configuration Changes Summary | This report provides an overview of configuration changes in the organization. | none | none |

Database

This is a sub-category of the Cross Device category, focusing on database events.

The Database category is located under the following path.

Device Monitoring\Database

The Database category reports are listed in the following table.

Database

| Report | Description | Drill Down | Parameters |
|--------------------------------|---|------------|------------|
| Database Errors and Warnings | This report shows recent database errors and warnings. | none | none |
| Database Configuration Changes | This report provides an overview of database configuration changes. | none | none |

Firewall

This is a sub-category of the Device Monitoring category, focusing on firewall events.

The Firewall category is located under the following path.

Device Monitoring\Firewall

The Firewall category reports are listed in the following table.

Firewall

| Report | Description | Drill Down | Parameters |
|--------------------------------|--|------------|------------|
| Denied Connections by Address | This report shows a summary and details of inbound and outbound connections denied by Firewall devices. | none | none |
| Denied Connections by Port | This report shows a summary and details of inbound and outbound ports denied by Firewall devices. | none | none |
| Denied Connections per Hour | This report shows a summary and details of inbound and outbound connections denied by Firewall devices on an hourly basis. | none | none |
| Denied Connections Overview | This report details the inbound and outbound connections denied by Firewall devices. | none | none |
| Firewall Configuration Changes | This report provides an overview of Firewall configuration changes. | none | none |

IDS-IPS

This is a sub-category of the Device Monitoring category, focusing on Intrusion Detection System and Intrusion Prevention System events.

The IDS-IPS category is located under the following path.

Device Monitoring\IDS-IPS

The IDS-IPS category reports are listed in the following table.

IDS-IPS

| Report | Description | Drill Down | Parameters |
|--------------------------|---|------------|------------|
| Alert Counts by Device | This report shows counts of IDS and IPS alerts. | none | none |
| Alert Counts by Port | This report shows count of IDS and IPS alerts by destination port. | none | none |
| Alert Counts by Severity | This report shows count of IDS and IPS alerts by agent severity. | none | none |
| Alert Counts by Type | This report shows the count of IDS and IPS alerts by type (category technique). | none | none |
| Alert Counts per Hour | This report shows the count of IDS and IPS alerts for each hour. | none | none |
| Top Alert Destinations | This report shows the top destinations of IDS and IPS alerts. | none | none |

IDS-IPS, continued

| Report | Description | Drill Down | Parameters |
|---|--|------------|------------|
| Top Alerts from IDS and IPS | This report shows the top alerts coming from Intrusion Detection Systems (IDS) and Intrusion Prevention Systems (IPS). | none | none |
| Top Alert Sources | This report shows the top sources of IDS and IPS alerts. | none | none |
| Worm Infected Systems | This report shows a list of systems that have been infected by a worm. | none | none |
| Intrusion Detection Configuration Changes | This report provides an overview of intrusion detection configuration changes. | none | none |

Identity Management

This is a sub-category of the Device Monitoring category, focusing on Identity Management system events.

The Identity Management category is located under the following path.

Device Monitoring\Identity Management

The Identity Management category reports are listed in the following table.

Identity Management

| Report | Description | Drill Down | Parameters |
|---|---|------------|------------|
| Connection Counts by User | This reports shows count information about connections for each user reported by Identity Management devices. | none | none |
| Accepted Accesses Through AAA Server | This report shows accepted access events through AAA server. | none | none |
| Identity Management Configuration Changes | This report provides an overview of identity management configuration changes. | none | none |
| Rejected Accesses Through AAA Server | This report displays rejected access events through AAA server. | none | none |

Network

This is a sub-category of the Device Monitoring category, focusing on network devices such as routers and switches.

The Network category is located under the following path.

Device Monitoring\Network

The Network category reports are listed in the following table.

Network

| Report | Description | Drill Down | Parameters |
|---------------------------------------|--|------------|------------|
| Device Critical Events | This report shows information regarding critical events on network devices. These critical events could be indications of hardware failure, resource exhaustion, configuration issues, or attacks. | none | none |
| Device Errors | This report shows information regarding error events on network devices. These critical events could be indications of hardware failure, resource exhaustion, configuration issues, or attacks. | none | none |
| Device Events | This report shows information regarding events on network devices. These critical events could be indications of hardware failure, resource exhaustion, configuration issues, or attacks. | none | none |
| Device Interface Down Notifications | This report shows a table displaying the network devices that report a down link. | none | none |
| Device Interface Status Messages | This report shows the network devices reporting link status changes. | none | none |
| Device SNMP Authentication Failures | This report shows information regarding network device SNMP failures. | none | none |
| Network Routing Configuration Changes | This report displays network routing configuration changes. | none | none |

Operating System

This is a sub-category of the Device Monitoring category, focusing on operating system events.

The Operating System category is located under the following path.

Device Monitoring\Operating System

The Operating System category reports are listed in the following table.

Operating System

| Report | Description | Drill Down | Parameters |
|----------------------|---|------------|------------|
| Login Errors by User | This report shows the details of failed logins for each username (time, event name, source, and destination). | none | none |
| User Administration | This report shows user and user group creations, modifications, and deletions. | none | none |

Operating System, continued

| Report | Description | Drill Down | Parameters |
|---------------------------------------|--|------------|------------|
| Audit Log Cleared | This report displays a summary of audit log cleared events. | none | none |
| Host Shutdown | This report provides an overview of shutdown events in the organization. | none | none |
| Host Started | This report lists host startup events in the organization. | none | none |
| Operating Systems Errors and Warnings | This report shows operating systems errors and warnings in the organization. | none | none |
| Security Log is Full | This report informs when the windows security log is full. | none | none |
| Service Shutdown | This report provides an overview of services shutdown in the organization. | none | none |
| Service Started | This report lists the services started in the organization. | none | none |

VPN

This is a sub-category of the Device Monitoring category, focusing on virtual private network events.

The VPN category is located under the following path.

Device Monitoring\VPN

The VPN category reports are listed in the following table.

VPN

| Report | Description | Drill Down | Parameters |
|---------------------------------|---|------------|------------|
| Authentication Errors | This report shows errors generated by a VPN connection attempt. The address is the IP address of the VPN connection source. This report can be used to see which users are having difficulties using or setting up their VPN clients. | none | none |
| Connection Counts by User | This report shows count information about VPN connections for each user. Details of each user's connection counts are provided, including connection count and systems accessed. | none | none |
| Connections Accepted by Address | This report shows successful VPN connection data. | none | none |

VPN, continued

| Report | Description | Drill Down | Parameters |
|-------------------------------|---|------------|------------|
| Connections Denied by Address | This report shows denied VPN connection data. | none | none |
| Connections Denied by Hour | This report shows denied VPN connection data for each hour. | none | none |
| Denied Connections Overview | This report displays denied VPN connections. | | |

DNS

This is a sub-category of the Device Monitoring category, focusing on DGA activity in the organization using DNS records.

The Database category is located under the following path.

Device Monitoring\DNS

The DNS category reports are listed in the following table.

DNS

| Report | Description | Drill Down | Parameters |
|--------------|--|------------|------------|
| DGA overview | This report monitors DGA domains in the organization using Microsoft DNS Trace Log events. | none | none |

Foundation

This category covers a broad range of events, from security and perimeter defense to network bandwidth usage and configuration events.

The following categories are located under the Foundation category:

- [Configuration Monitoring](#) 619
- [MITRE Monitoring](#) 620
- [Intrusion Monitoring](#) 621
- [NetFlow Monitoring](#) 630
- [Network Monitoring](#) 630
- [Vulnerabilities](#) 631

Configuration Monitoring

This category covers configuration changes to systems and applications.

The Configuration Monitoring category is located under the following path.

Foundation\Configuration Monitoring

The Configuration Monitoring category reports are listed in the following table. There are no parameters.

Configuration Monitoring

| Report | Description | Drill Down |
|--------------------------------------|---|--|
| Accounts Created by User Account | This report details the successfully created accounts created on network hosts. The table includes the timestamp of when the account was created, the created account name (Destination User Name), the name of the user creating the account (Source User Name), the account creation event name, and the zone and host name of the device on which the account was created. | none |
| Accounts Deleted by Host | This report provides a listing of user deletions, ordered by Customer, Zone, and System. | none |
| Accounts Deleted by User Account | This report displays a table showing the date, the deleted user name, the user name that deleted the account, the account deletion event name, and the zone and host name of the system from which the account was deleted. | none |
| Anti-Virus Updates-All-Failed | This report displays a table with the Device Vendor, Device Product Target Zone Name, Target Host Name, Target Address and Minute(EndTime), of all failed anti-virus update events. | none |
| Anti-Virus Updates-All-Summary | This report displays a table showing the Target Zone Name, Target Host Name, Target Address, Device Vendor, Device Product, Category Outcome and the sum of the Aggregated Event Count of all anti-virus events. | none |
| Asset Startup and Shutdown Event Log | This report provides a listing of the system startup and shutdown events. | none |
| Device Configuration Changes | This report shows a table of events related to successful device configuration modification events. The information provided includes the Device Group, the Zone, Address and Host Name, the Configuration Event name, the User ID and Name making the change, and the hour the change was made. Clicking on a device entry in the Device Group column will bring up a new report, Device Configuration Changes Drilldown, which will show only configuration events for that particular device type. | <p>The Device Group field drill downs to the Device Configuration Changes report.</p> <p>This report drills down to itself.</p> |

Configuration Monitoring, continued

| Report | Description | Drill Down |
|---|--|--|
| Device Configuration Events | This report shows a table of events related to various device configuration modification events, whether successful or not. The information provided includes the Device Group, the Zone, Address and Host Name, the Configuration Event name, the User ID and Name making the change, and the hour the change was made. Clicking on a device entry in the Device Group column will bring up a new report, Device Configuration Events Drilldown, which will show only configuration events for that particular device type. | The Device Group field drill downs to the Device Configuration Events report. This report drills down to itself. |
| Device Misconfigurations | This report shows a table of events related to device configuration checks. The information provided includes the Device Group, the Zone, Address and Host Name, the Misconfiguration name, and the count of the number of misconfigurations found. Clicking on a Device Group entry will run the Device Misconfigurations Drilldown report, focusing on the device type that was clicked. | The Device Group field drill downs to the Device Misconfigurations report. This report drills down to itself. |
| Password Changes | This report displays a table of user accounts having their passwords changed. The table shows the time the password was changed, the user name of the account with the new password, the zone and address of the system on which the password was changed, and the zone and address from which the change originated. | none |
| Vulnerability Scanner Logs by Host | This report shows Vulnerability Scanner Logs grouped by Zone and Host IP Address. | none |
| Vulnerability Scanner Logs by Vulnerability | This report shows Vulnerability Scanner Logs grouped by Vulnerability IDs and Names. | none |

MITRE Monitoring

This is a sub-category of the Foundation category, focusing on MITRE ATT&CK framework related events which forwarded from ArcSight ESM to Logger.

The MITRE Monitoring category is located under the following path.

Foundation\MITRE Monitoring

The MITRE Monitoring category reports are listed in the following table.

MITRE Monitoring

| Report | Description | Drill Down |
|---|---|--|
| MITRE Att&ck Events Overview | This report provides overview of MITRE ATT&CK events forwarded to Logger from ArcSight ESM. | none. |
| MITRE Att&ck Events - Drill Down by Destination Address | This report is a drill down report and used by MITRE ATT&CK Events Overview. This report should not be used as standalone report. | MITRE Att&ck Events drills down to Destination Address report. |
| MITRE Att&ck Event - Drill Down by Destination User | This report is a drill down report and used by MITRE ATT&CK Events Overview. This report should not be used as standalone report. | MITRE Att&ck Event drills down to Destination User report. |
| MITRE Att&ck Events - Drill Down by Event Name | This report is a drill down report and used by MITRE ATT&CK Events Overview. This report should not be used as standalone report. | MITRE Att&ck Events drills down to Event Name report. |
| MITRE Att&ck Events - Drill Down by Hour | This report is a drill down report and used by MITRE ATT&CK Events Overview. This report should not be used as standalone report. | MITRE Att&ck Events drills down to Hour report. |
| MITRE Att&ck Events - Drill Down by Source Address | This report is a drill down report and used by MITRE ATT&CK Events Overview. This report should not be used as standalone report. | MITRE Att&ck Events drills down to Source Address report. |
| MITRE Att&ck Events - Drill Down by Source User | This report is a drill down report and used by MITRE ATT&CK Events Overview. This report should not be used as standalone report. | MITRE Att&ck Events drills down by Source User report. |

Intrusion Monitoring

This is a sub-category of the Foundation category, focusing on security, perimeter defense, resource access and user tracking events.

The Intrusion Monitoring category is located under the following path.

Foundation\Intrusion Monitoring

The Intrusion Monitoring category reports are listed in the following table. There are no parameters.

Intrusion Monitoring

| Report | Description | Drill Down |
|-----------------------------------|--|--|
| Firewall Traffic by Service | This report displays a table showing the Port, transport protocol, application protocol, and the number of events reported by firewalls. | none |
| Least Common Events | This report displays all events in the time period selected and orders them by the sum of the aggregated event count in ascending order. The columns are hyperlinked for convenience. The Event Name column will bring up the Bottom Destinations report using the same time frame. The Count column will bring up the Bottom Sources report using the same time frame. | <p>The Event Name field drill downs to the Bottom Destinations report.</p> <p>The Count field drill downs to the Bottom Sources report.</p> |
| Most Common Events | This report displays the 200 most common events within the time range specified. The event name is hyperlinked to drilldown to the Destination Counts by Event Name report, which will show destination information for the event selected. The Count field will bring up the Source Counts by Destination Port report, which will include information about all sources by destination port. | <p>The arc_name field drill downs to the Destination Counts by Event Name report.</p> <p>The SUM(events.arc_baseEventCount) field drill downs to the Source Counts by Destination Port report.</p> |
| Most Common Events by Severity | This report displays a table showing the Severity, event name and count of events in descending order. | <p>The Severity field drill downs to the Source Counts by Device Severity report.</p> <p>The Count field drill downs to the Destination Counts by Device Severity report.</p> |
| Probes on Blocked Ports by Source | This report displays a table of events showing the source zone, address and host name, the transport protocol, the destination port, and the count of events where the destination port is in the list of commonly blocked ports. The query uses the commonlyblockedPorts parameter, which can be edited to include other ports (please make a copy of the report, the query, and the parameter, and modify your version as updates to the Foundation Content may overwrite your changes). | none |
| SecurityDash BoardRpt | This custom report displays a table showing the source address, category behavior, destination address and event ID. | none |

Intrusion Monitoring, continued

| Report | Description | Drill Down |
|----------------------------------|---|------------|
| SecurityDB Report | This custom Security Dashboard report displays two charts and a table. The first chart shows the number of events by source address. The second chart shows the number of events by destination address. The table shows the counts of events for each source and destination. | none |
| Top IDS Attack Events | This report displays a table showing the top events from IDS systems, with the IDS Event name, the type of IDS, and the count of each IDS event where the category significance is Compromise or Hostile. | none |
| Top IDS Events | This report displays a table showing the top events from IDS systems, with the IDS Event name, the type of IDS, and the count of each IDS event. | none |
| Top Machines Traversing Firewall | This report displays the source zone, address and hostname, and number of events reported by firewalls. | none |
| Top Web Traffic | This report displays a table showing the hour, source zone, address and host name, the web port and the count of events where the destination port is listed in the webPorts parameter. | none |
| Windows Events | This report displays a table showing the device zone, address and host name, the device event ID, the source user ID, user name and NT domain, the destination user ID, user name and NT domain, the behavior, outcome and event type, and the count of events of each type reported by any Microsoft operating system. | none |
| Worm Infected Systems | This report displays a table showing the Zone Name, Host Name and Address of systems exhibiting symptoms of being infected by a worm. | none |
| User Activity Statistics | This report provides different statistics about user activity, such as top users, top IP addresses, top events, top signatures, etc. | none |
| Email Attacks | This report shows the email attacks in the organization. | none |
| Man In the Middle Attacks | This report lists the man In the middle attacks on the organization. | none |
| Coordinated Brute Force | This report provides overview of failed logins and possible brute force attacks coordinated from different countries against your organization. | none |

Intrusion Monitoring, continued

| Report | Description | Drill Down |
|--------------------------------------|---|------------|
| Reconnaissance Overview | This report provides a Geo overview of reconnaissance activity against your organization. | none |
| Entropy Overview | This report provides an overview about the entropy of the target URLs using proxy events. To run this report, data science component must be enabled on Logger. | |
| Entropy Overview - Drill Down by URL | This report is a drill down report and used by Entropy Overview report. This report should not be used as standalone report. | |

The following categories are located under Intrusion Monitoring:

- [Attackers](#)624
- [Resource Access](#) 626
- [Targets](#)627
- [User Tracking](#) 629

Attackers

This is a sub-category of the Intrusion Monitoring category, focusing on events based on source or attacker information.

The Attackers category is located under the following path.

Foundation\Intrusion Monitoring\Attackers

The Attackers category reports are listed in the following table. There are no parameters.

Attackers

| Report | Description | Drill Down |
|-----------------------------------|---|---|
| Bottom Sources | This report displays the Source Zone Names, Source Addresses and event Count ordered by the sum of the base event counts in ascending order. Clicking on the hyperlink for the Count column will bring up the Bottom Targets report. It is the target of the Least Common Events report's Count column. | The Count field drill downs to the Bottom Targets report. |
| Source Counts by Destination | This report displays a table showing the destination zone and address, the source zone and the number of each event for a specific destination zone and address where the category significance is Compromise or Hostile. | <p>The Destination Zone field drill downs to the Source Counts by Destination report.</p> <p>The Destination Address field drill downs to the Source Counts by Destination report.</p> <p>The Source Count field drill downs to the Attack Events by Destination report.</p> <p>This report drills down to itself.</p> |
| Source Counts by Destination Port | This report displays a table showing the Destination Port, the source zone and address, and the number of events for each port. | none |
| Source Counts by Device | This report displays a table showing the device zone and address, the source zone and address, and the number of each event where the category significance is Compromise or Hostile. | none |
| Source Counts by Device Severity | This report displays a table showing the Severity, source zone and address, and the number of events at that severity. | none |
| Source Counts by Source Port | This report displays a table showing the Source Port, source zone and address, and a count of events where the category significance is Compromise or Hostile. | none |
| Source Port Counts | This report displays a table showing the Source Port, Event Name and count of the events where the category significance is Compromise or Hostile. | none |
| Top 10 Talkers | This report displays a table of the Top 10 systems generating events, showing the Source zone and address, as well as the number of events from that system. | none |
| Top Attacker Detail | This report displays a table showing the severity, attacker zone and address, the target zone and address, and the count of events for a specified source zone and address where the category significance is Compromise or Hostile. | none |

Attackers, continued

| Report | Description | Drill Down |
|----------------------------------|---|---|
| Top Attacker Details | This report displays the Severity, Attacker Zone, Attacker Address, Target Zone, Target Address and Count of events where the Category Significance of the event is compromise or hostile, ordered by the event count in descending order. This report is the target of the Top Attackers report's Attacker Address column. | none |
| Top Attacker Ports | This report displays a table showing the Attacker Port, Transport Protocol and the count of events where the category significance is Compromise or Hostile. | none |
| Top Attackers | This report shows the Attacker Zone Names, Attacker Addresses and Count of events where the Category Significance of the events is compromise or hostile, in descending order of the sum of the base event count. This report has hyperlinks that will run reports showing more information base on the field selected. The Attacker Zone column will run the Top Attack Sources report. The Attacker Address will run the Top Attacker Details report. The Count column will run the Top Targets report. | <p>The Attacker Address field drill downs to the Top Attacker Details report.</p> <p>The Count field drill downs to the Top Targets report.</p> |
| Top Attack Sources | This report displays the Attacker Zone and Count of events where the Category Significance of the event is compromise or hostile, ordered by the event count in descending order. This report has a hyperlink in the Attacker Zone column that will run the Top Attackers report. | The Attacker Zone field drill downs to the Top Attackers report. |
| Top Sources Detected by Snort | This report displays a table showing the source zone, address and host name and the number of events detected by Snort. | none |
| Top Sources Traversing Firewalls | This report displays a table of the source zone, address and host name, as well as the count of events, where the event was reported by a firewall device. | none |

Resource Access

This is a sub-category of the Intrusion Monitoring category, focusing on protected resources.

The Resource Access category is located under the following path.

Foundation\Intrusion Monitoring\Resource Access

The Resource Access category reports are listed in the following table. There are no parameters.

Resource Access

| Report | Description | Drill Down |
|---|--|---|
| Access Events by Resource | This report displays a table showing the Resource Type, the zone and address, the access event, the outcome and the number of times this has happened over the time period selected. Clicking on a resource type will run the Access Events by Resource Drilldown report showing the events for the selected resource type. | The Resource Type field drill downs to the Access Events by Resource report. This report drills down to itself. |
| Least Common Accessed Ports | This report displays a table showing the Destination Port, the Transport Protocol and a count of the events for that port where the transport protocol is TCP or UDP. | none |
| Resource Access by Users - Failures | This report displays a table showing the Resource Type, the User ID and Name, Destination zone and address, the Access Event and number of failed attempts to access a given resource. Clicking on an entry in the Resource Type column will bring up the Resource Access by Users - Failures Drilldown report, which will show all related events for that resource type. | The Resource Type field drill downs to the Resource Access by Users - Failures report. This report drills down to itself. |
| Resource Access by Users - Successes-Attempts | This report displays a table showing the Resource Type, Outcome, destination user ID and name, destination zone and address, the access event name and the number of such events. The Resource Type column is hyperlinked so that clicking on a resource type will run the Resource Access by Users - Successes-Attempts Drilldown report, showing only events for the selected resource type. | The Resource Type field drill downs to the Resource Access by Users - Successes-Attempts report. This report drills down to itself. |
| Top Machines Accessing the Web | This report displays a table showing the source zone, address and host name, the destination port and the number of events where the destination port is in the webPorts parameter list. | none |

Targets

This is a sub-category of the Intrusion Monitoring category, focusing on events based on destination or target information.

The Targets category is located under the following path.

Foundation\Intrusion Monitoring\Targets

The Targets category reports are listed in the following table. There are no parameters.

Targets

| Report | Description | Drill Down |
|---------------------------------------|---|---|
| Attack Events by Destination | This report displays a table showing the destination zone and address, the source zone and address, the event name and the number of each event for a specific destination zone and address where the category significance is Compromise or Hostile. | The Destination Zone field drill downs to the Attack Events by Destination report. The Destination Address field drill downs to the Attack Events by Destination report. This report drills down to itself. |
| Bottom Destinations | This report displays the Destination Zone Names, Destination Addresses and event Count ordered by the sum of the base event counts in ascending order. It is the target of the Least Common Events report's Event Name column. | none |
| Bottom Targets | This report shows the Target Zone Names, Target Addresses and Count of events where the Category Significance of the events is compromise or hostile, in ascending order of the sum of the base event count. This report is the target of the Bottom Sources report's Count column. | none |
| Destination Counts by Device Severity | This report displays a table showing the Severity, target zone and address, and the number of events for each severity. | none |
| Destination Counts by Event Name | This report displays a table showing the event name, the target zone and address, and the number of events for each destination. | none |
| Target Attack Counts by Severity | This report displays a table showing the Severity, the target zone and the number of events where the event has a category significance of Compromise, Hostile or Suspicious. | none |
| Target Counts by Event Name | This report displays a table showing the event name, target zone and address, and the number of time that event has occurred where the category significance is Compromise or Hostile. | none |
| Target Counts by Severity | This report displays a table showing the Severity, the target zone and address, and the number of events where the event has a category significance of Compromise, Hostile or Suspicious. | none |
| Target Counts by Source | This report displays a table showing the Source zone and address, the target zone and address, and the number of events where the event has a category significance of Compromise, Hostile or Suspicious. | none |
| Target Counts by Source Port | This report displays a table showing the Source Port, the count of events for that port, with the destination zone and address, where the category significance is Compromise or Hostile. | none |

Targets, continued

| Report | Description | Drill Down |
|-----------------------------------|---|------------|
| Target Counts by Target Port | This report displays a table showing the Destination Port, the number of events for each port, and the target zone and address for events with category significance of Compromise or Hostile. | none |
| Target Port Counts | This report displays a table showing the Target Port, the number of events for that port, and the target zone and address of events where the category significance is Compromise or Hostile. | none |
| Top Destination Ports | This report displays a table of the top destination ports and the number of events for each port. | none |
| Top Destinations Across Firewalls | This report displays a table of the destination zone, address and host name, as well as the count of events, where the event was reported by a firewall device. | none |
| Top Destinations in IDS Events | This report displays a table showing the Destination zone, address and host name, as well as the count of event going to each host, for all events coming from an IDS. | none |
| Top Targets | This report displays the Target Zone, Target Address and Count of events where the Category Significance of the event is compromise or hostile, ordered by the event count in descending order. This report is the target of the Top Attackers report's Count column. | none |

User Tracking

This is a sub-category of the Intrusion Monitoring category, focusing on events based on user information.

The User Tracking category is located under the following path.

Foundation\Intrusion Monitoring\User Tracking

The User Tracking category reports are listed in the following table. There are no parameters.

User Tracking

| Report | Description | Drill Down |
|---|---|------------|
| Common Account Login Failures by Source | This report displays a table of the Resource Type, Attacker Address, Attacker Asset Name, Attacker NT Domain, Attacker User ID, Attacker User Name, Attacker Zone Name and the sum of the Aggregated Event Count. | none |
| Number of Failed Logins | This report displays a table showing the number of failed logins for each hour covered by the report time-range. | none |
| Top User Logins | This report displays a table showing the NT Domain, the user ID and name, and the number of successful logins. | none |

User Tracking, continued

| Report | Description | Drill Down |
|------------------------------|--|------------|
| Top Users with Failed Logins | This report displays a table showing the user ID and name, time (by minute) and the number of failed login attempts. | none |
| User Activity | This report displays a table of events, showing the source user ID and user name, the destination user ID and user name, the time of the event, the event name and the result (success, attempt, failure). | none |
| User Activity Statistics | This report provides different statistics about user activity, such as top users, top IP addresses, top events, top signatures, etc. | none |

NetFlow Monitoring

This is a sub-category of the Foundation category, focusing on NetFlow data.

The NetFlow Monitoring category is located under the following path.

Foundation\NetFlow Monitoring

The NetFlow Monitoring category reports are listed in the following table.

NetFlow Monitoring

| Report | Description | Drill Down |
|---|--|------------|
| Daily Bandwidth Usage | This report displays a chart and a table to show the bandwidth usage by day. | none |
| Hourly Bandwidth Usage | This report displays a chart and a table to show the bandwidth usage by hour. | none |
| Top Bandwidth Usage by Destination | This report displays a chart and a table to show the bandwidth usage by destination address. | none |
| Top Bandwidth Usage by Destination Port | This report displays a chart and a table to show the bandwidth usage by destination port. | none |
| Top Bandwidth Usage by Source | This report displays a chart and a table to show the bandwidth usage by source address. | none |

Network Monitoring

This is a sub-category of the Foundation category, focusing on network bandwidth and status events.

The Network Monitoring category is located under the following path.

Foundation\Network Monitoring

The Network Monitoring category reports are listed in the following table. There are no parameters.

Network Monitoring

| Report | Description | Drill Down |
|--------------------------------------|---|------------|
| Top VPN Accesses by User | This report displays a table showing the source user ID and name, and the count of events for VPN access, authorization or authentication events. | none |
| Top VPN Event Destinations | This report displays a table showing the VPN destination zone, address and host name, and the count of events for that host, reported by the VPN device, excluding modification events. | none |
| Top VPN Events | This report displays a table showing the VPN event name, source zone and address, destination zone and address, and the count of events for that event reported by the VPN device, excluding modification events. | none |
| Top VPN Event Sources | This report displays a table showing the VPN source zone, address and host name, and the count of events for that source, reported by the VPN device, excluding modification events. | none |
| Traffic Statistics | This report displays two charts and a table. The first chart shows the bytes in and out by hour. The second chart shows the bytes in and out by device. The table shows the hour, firewall zone and address, the transport protocol and the bytes in and out. | none |
| VPN Connection Attempts | This report displays a table showing the source hostname, source user name, destination zone, address and host name, destination user ID and user name and the count of events where the VPN access, authorization or authentication event did not result in failure. | none |
| VPN Connection Failures | This report displays a table showing the VPN device zone, address and host name, the VPN event, the source user ID, host name and user name, the destination zone, address, host name and user name, and the count of each event, where the VPN device reports and access, authorization or authentication failure. | none |
| Traffic Anomaly | This report identifies traffic anomalies in the organization. | none |
| Traffic Anomaly on Application Layer | This report presents the traffic anomalies on application in the organization. | none |
| Traffic Anomaly on Network Layer | This report provides an overview of traffic anomaly in the network layer. | none |
| Traffic Anomaly on Transport Layer | This report provides an overview of traffic anomaly in the transport layer. | none |

Vulnerabilities

This is a sub-category of the Foundation category, focusing on vulnerabilities.

The Vulnerabilities category is located under the following path.

Foundation\Vulnerabilities

The Vulnerabilities category reports are listed in the following table.

Vulnerabilities

| Report | Description | Drill Down |
|--|---|------------|
| Account Hijacking Vulnerabilities | This report shows account hijacking vulnerabilities. | none |
| Cloud Related Vulnerabilities | This report lists cloud related vulnerabilities in the organization | none |
| Critical Vulnerabilities | This report presents critical vulnerabilities in the organization. | none |
| Heartbleed Vulnerabilities | This report shows heartbleed vulnerabilities in the organization. | none |
| Information Disclosure Vulnerabilities | This report displays the disclosure vulnerabilities reported in the organization. | none |
| Injection Vulnerabilities | This report provides an overview of injection vulnerabilities in the organization (such as SQL,XPATH,NOSQL,OS command, and LDAP injections flaws) | none |
| Kernel Vulnerabilities | This report lists the kernel vulnerabilities found in the organization. | none |
| LDAP Vulnerabilities | This report summarizes LDAP vulnerabilities in the organization. | none |
| Overflow Vulnerabilities | This report lists the overflow vulnerabilities in the organization. | none |
| Shellshock Vulnerabilities | This report provides an overview of Shellshock vulnerabilities on the organization. | none |
| Spectre and Meltdown Vulnerabilities | This report shows spectre and meltdown vulnerabilities on the organization. | none |
| SQL Injection Vulnerabilities | This report displays SQL Injection vulnerabilities on the organization. | none |
| SSH Vulnerabilities | This report summarizes SSH vulnerabilities on the organization. | none |
| SSL Vulnerabilities | This report exhibits SSL vulnerabilities on the organization. | none |
| TOP 5 Vulnerable Hosts | This report outlines the top 5 vulnerable hosts. | none |
| Vulnerabilities by Host | This report provides an overview of vulnerabilities by Host, (Host Name should be provided while running the report). | none |
| Vulnerability Overview | This report provides vulnerability overview in the organization. | none |
| XML Vulnerabilities | This report displays xml vulnerabilities in the organization. | none |
| XSRF Vulnerabilities | This report lists XSRF vulnerabilities in the organization. | none |
| XSS Vulnerabilities | This report provides an overview of XSS vulnerabilities in the organization. | none |

Logger Administration

This category covers Logger administration tasks. The Logger Administration category reports are listed in the following table.

Logger Administration

| Report | Description | Drill Down | Params |
|------------------|--|------------|--------|
| Daily Byte Count | This report displays a daily count of bytes from events that have been received from connectors. | none | none |

SANS Top 5

This category covers the SANS Top 5 Essential Log Reports (<http://www.sans.org/security-resources/top5-logreports.pdf>). Each of the sub-categories addresses one of the 5 areas.

The following categories are located under the SANS Top 5 category:

- [1 - Attempts to Gain Access through Existing Accounts](#)633
- [2 - Failed File or Resource Access Attempts](#)634
- [3 - Unauthorized Changes to Users Groups and Services](#)635
- [4 - Systems Most Vulnerable to Attack](#)635
- [5 - Suspicious or Unauthorized Network Traffic Patterns](#)636

1 - Attempts to Gain Access through Existing Accounts

This is a sub-category of the SANS Top 5 Essential Log Reports. It addresses attempts to gain access to a system through existing accounts.

The 1 - Attempts to Gain Access through Existing Accounts category is located under the following path.

SANS Top 5\1 - Attempts to Gain Access through Existing Accounts

The 1 - Attempts to Gain Access through Existing Accounts category reports are listed in the following table.

1 - Attempts to Gain Access through Existing Accounts

| Report | Description | Drill Down | Params |
|------------------------------|--|------------|--------|
| Number of Failed Logins | This report, based on the SANS Top 5 Essential Log Reports, section 1 - Attempts to Gain Access Through Existing Accounts, displays a table showing the number of failed logins for each hour covered by the report time-range. | none | none |
| Top Users with Failed Logins | This report, based on the SANS Top 5 Essential Log Reports, section 1 - Attempts to Gain Access Through Existing Accounts, displays a table showing the user ID and name, the time and the number of attempts to login to a system during that minute. | none | none |

2 - Failed File or Resource Access Attempts

This is a sub-category of the SANS Top 5 Essential Log Reports. It addresses failed file or resource access attempts.

The 2 - Failed File or Resource Access Attempts category is located under the following path.

SANS Top 5\2 - Failed File or Resource Access Attempts

The 2 - Failed File or Resource Access Attempts category reports are listed in the following table.

2 - Failed File or Resource Access Attempts

| Report | Description | Drill Down | Params |
|---------------------------------|--|---|--------|
| Failed Resource Access by Users | This report, based on the SANS Top 5 Essential Log Reports, section 2 - Failed File or Resource Access Attempts, displays a table showing the Resource Type, the User ID and Name, Destination zone and address, the Access Event and number of failed attempts to access a given resource. Clicking on an entry in the Resource Type column will bring up the SANS Top 5 -2- Failed Resource Access by Users Drilldown report, which will show all related events for that resource type. | The Resource Type field drill downs to the Failed Resource Access by Users report. This report drills down to itself. | none |
| Failed Resource Access Events | This report, based on the SANS Top 5 Essential Log Reports, section 2 - Failed File or Resource Access Attempts, displays a table showing the Resource Type, the User ID and Name, Destination zone and address, the Access Event and number of failed attempts to access a given resource. Clicking on an entry in the Resource Type column will bring up the SANS Top 5 -2- Failed Resource Access Events Drilldown report, which will show all related events for that resource type. | The Resource Type field drill downs to the Failed Resource Access Events report. This report drills down to itself. | none |

3 - Unauthorized Changes to Users Groups and Services

This is a sub-category of the SANS Top 5 Essential Log Reports. It addresses unauthorized changes to users, groups and services.

The 3 - Unauthorized Changes to Users Groups and Services category is located under the following path.

SANS Top 5\3 - Unauthorized Changes to Users Groups and Services

The 3 - Unauthorized Changes to Users Groups and Services category reports are listed in the following table.

3 - Unauthorized Changes to Users Groups and Services

| Report | Description | Drill Down | Params |
|----------------------------|--|------------|--------|
| Account Modifications | This custom report, based on the SANS Top 5 Essential Log Reports, section 3 - Unauthorized Changes to Users, Groups and Services, displays a chart and a table. The chart shows the top user account modifications. The table shows the source user name, source zone and address, destination user name, destination zone and address, the modification event, and the date of the modification. | none | none |
| Password Changes | This report, based on the SANS Top 5 Essential Log Reports, section 3 - Unauthorized Changes to Users, Groups and Services, displays a table showing the user name, source zone and address, destination zone and address, and the date of password change events. | none | none |
| User Account Creations | This report, based on the SANS Top 5 Essential Log Reports, section 3 - Unauthorized Changes to Users, Groups and Services, displays a table showing the source user name, the source zone and address, the destination user name, the destination zone and address, the modification event name and the date of the account creation. | none | none |
| User Account Deletions | This report, based on the SANS Top 5 Essential Log Reports, section 3 - Unauthorized Changes to Users, Groups and Services, displays a table showing the source user name, the source zone and address, the destination user name, the destination zone and address, and the time when a user account was deleted. | none | none |
| User Account Modifications | This report, based on the SANS Top 5 Essential Log Reports, section 3 - Unauthorized Changes to Users, Groups and Services, displays a table showing the source user name, the source zone and address, the destination user name, the destination zone and address, the modification event name, and the date of the account modification. | none | none |

4 - Systems Most Vulnerable to Attack

This is a sub-category of the SANS Top 5 Essential Log Reports. It addresses the systems that are most vulnerable to attack.

The 4 - Systems Most Vulnerable to Attack category is located under the following path.

SANS Top 5\4 - Systems Most Vulnerable to Attack

The 4 - Systems Most Vulnerable to Attack category reports are listed in the following table.

4 - Systems Most Vulnerable to Attack

| Report | Description | Drill Down | Params |
|---|---|---|--------|
| Vulnerability Scanner Logs by Host | This report, based on the SANS Top 5 Essential Log Reports, section 4 - Systems Most Vulnerable to Attack, displays a table showing the system zone and address, the vulnerability ID and name, and the number of times that vulnerability has been reported for that system. | The arc_destinationAddress field drill downs to the Vulnerability Scanner Logs by Host report. This report drills down to itself. | none |
| Vulnerability Scanner Logs by Vulnerability | This report, based on the SANS Top 5 Essential Log Reports, section 4 - Systems Most Vulnerable to Attack, displays a table showing the vulnerability ID and name, the zone and address, and the number of times that vulnerability has been reported for that system. | The arc_destinationAddress field drill downs to the Vulnerability Scanner Logs by Host report. This report drills down to itself. | none |

5 - Suspicious or Unauthorized Network Traffic Patterns

This is a sub-category of the SANS Top 5 Essential Log Reports. It addresses suspicious or unauthorized network traffic patterns.

The 5 - Suspicious or Unauthorized Network Traffic Patterns category is located under the following path.

SANS Top 5\5 - Suspicious or Unauthorized Network Traffic Patterns

The 5 - Suspicious or Unauthorized Network Traffic Patterns category reports are listed in the following table.

5 - Suspicious or Unauthorized Network Traffic Patterns

| Report | Description | Drill Down | Params |
|----------------------------|---|------------|--------|
| Alerts from IDS | This report, based on the SANS Top 5 Essential Log Reports, section 5 - Suspicious or Unauthorized Network Traffic Patterns, displays a table showing the device vendor and product, the device event ID, the IDS signature name and the number of times that signature was reported. | none | none |
| IDS Signature Destinations | This report, based on the SANS Top 5 Essential Log Reports, section 5 - Suspicious or Unauthorized Network Traffic Patterns, displays a table showing the destination zone and address, the device vendor and product and the count of events reported for the address by the IDS. | none | none |

5 - Suspicious or Unauthorized Network Traffic Patterns, continued

| Report | Description | Drill Down | Params |
|--------------------------------|---|------------|--------|
| IDS Signature Sources | This report, based on the SANS Top 5 Essential Log Reports, section 5 - Suspicious or Unauthorized Network Traffic Patterns, displays a table showing the destination zone and address, the device vendor and product, and the count of each event. | none | none |
| Top 10 Talkers | This report, based on the SANS Top 5 Essential Log Reports, section 5 - Suspicious or Unauthorized Network Traffic Patterns, displays a table showing the source zone and address, and the number of events coming from each address. | none | none |
| Top 10 Types of Traffic | This report, based on the SANS Top 5 Essential Log Reports, section 5 - Suspicious or Unauthorized Network Traffic Patterns, breaks down the traffic by the Application Protocol, Port number and Transport Protocol, where at least one of the three must be available and the bytes in or bytes out are available. The count is bases on the number of base events, presuming that each event with these conditions represents a packet of some type. | none | none |
| Top Alerts from IDS | This report, based on the SANS Top 5 Essential Log Reports, section 5 - Suspicious or Unauthorized Network Traffic Patterns, displays a chart and a table. The chart shows the top 10 alerts from IDSes. The table shows the Signature ID, the signature name, the device vendor and the number of times that signature was reported. | none | none |
| Top Destination IPs | This report, based on the SANS Top 5 Essential Log Reports, section 5 - Suspicious or Unauthorized Network Traffic Patterns, displays a table showing the target zone and address and the count of events for each destination address. | none | none |
| Top IDS Signature Destinations | This report, based on the SANS Top 5 Essential Log Reports, section 5 - Suspicious or Unauthorized Network Traffic Patterns, displays a chart and a table. The chart shows the top signature destinations by address. The table shows the destination zone and address, the device vendor and product, and the count of events to that host. | none | none |
| Top IDS Signature Sources | This report, based on the SANS Top 5 Essential Log Reports, section 5 - Suspicious or Unauthorized Network Traffic Patterns, displays a chart and a table. The chart shows the top signature sources by address. The table shows the source zone and address, the device vendor and product, and the count of events by that host. | none | none |
| Top Target IPs | This report, based on the SANS Top 5 Essential Log Reports, section 5 - Suspicious or Unauthorized Network Traffic Patterns, displays a table showing the target zone and address, and the number of IDS event reported for that address where the category significance is Compromise or Hostile. | none | none |

OWASP

This category covers the OWASP Top 10 Security Risks. Each of the sub-categories addresses one of those security risks.

The following categories are located under the OWASP category:

- [A1 - Injections](#) 638
- [A2- Broken Authentication](#)638
- [A3- Sensitive Data Exposure](#)639
- [A4- XML External Entities](#)639
- [A5- Broken Access Control](#)639
- [A6- Security Misconfiguration](#) 640
- [A7- Cross-Site Scripting](#) 640
- [A8- Insecure Deserialization](#)640
- [A9 - Using Components with Known Vulnerabilities](#)641
- [A10 - Insufficient Logging AND Monitoring](#) 641

A1 - Injections

This is a sub-category of OWASP category, focusing on injections.

The A-1 injections category is located under the following path.

OWASP\A-1 Injections

The A-1 Injections category reports are listed in the following table.

A-1 Injections

| Report | Description | Drill Down | Parameters |
|------------------------------------|--|------------|------------|
| Command Injections on HTTP Request | This report shows command injections on HTTP Requests. | none | none |

A2- Broken Authentication

This is a sub-category of OWASP category, focusing on broken authentications.

The A-2 Broken Authentication category is located under the following path.

OWASP\A-2 Broken Authentication

The A-2 Broken Authentication category reports are listed in the following table.

A-2 Broken Authentication

| Report | Description | Drill Down | Parameters |
|------------------------------|---|------------|------------|
| Broken Authentication Events | This report provides an overview of broken authentication events. | none | none |

A3- Sensitive Data Exposure

This is a sub-category of OWASP category, focusing on sensitive data exposure.

The A-3 Sensitive Data Exposure category is located under the following path.

OWASP\A-3 Sensitive Data Exposure

The A-3 Sensitive Data Exposure category reports are listed in the following table.

A-3 Sensitive Data Exposure

| Report | Description | Drill Down | Parameters |
|------------------------------------|--|------------|------------|
| All Information Leakage events | This report lists the leakage events in the organization. | none | none |
| Organizational Information Leakage | This report outlines the organizational information leakage events. | none | none |
| Personal Information Leakage | This report shows the personal information leakage events on the organization. | none | none |

A4- XML External Entities

This is a sub-category of OWASP category, focusing on sensitive XML external entities vulnerabilities.

The A-4 XML External Entities category is located under the following path.

OWASP\A-4 XML External Entities

A5- Broken Access Control

This is a sub-category of OWASP category, focusing on broken access control.

The A-5 Broken Access Control category is located under the following path.

OWASP\A-5 Broken Access Control

The A-5 Broken Access Control category reports are listed in the following table.

A-5 Broken Access Control

| Report | Description | Drill Down | Parameters |
|-----------------------|--|-------------------|-------------------|
| Broken Access Control | This report displays information of broken access control events | none | none |

A6- Security Misconfiguration

This is a sub-category of OWASP category, focusing on security misconfiguration.

The A-6 Security Misconfiguration category is located under the following path.

OWASP\A-6 Security Misconfiguration

The A-6 Security Misconfiguration category reports are listed in the following table.

A-6 Security Misconfiguration

| Report | Description | Drill Down | Parameters |
|-------------------------|--|-------------------|-------------------|
| Misconfiguration Events | This report shows the misconfiguration events found in the organization. | none | none |
| Security Patch Missing | This report provides information about security patches missing. | none | none |

A7- Cross-Site Scripting

This is a sub-category of OWASP category, focusing on cross-site scripting.

The A-7 Cross-Site Scripting category is located under the following path.

OWASP\A-7 Cross-Site Scripting

A8- Insecure Deserialization

This is a sub-category of OWASP category, focusing on insecure deserialization.

The A-8 Insecure Deserialization category is located under the following path.

OWASP\A-8 Insecure Deserialization

The A-8 Insecure Deserialization category reports are listed in the following table.

A-8 Insecure Deserialization

| Report | Description | Drill Down | Parameters |
|-----------------------|--|------------|------------|
| Deserialization Flaws | This report displays the serializations and deserialization flaws found on different products in the organization. | none | none |

A9 - Using Components with Known Vulnerabilities

This is a sub-category of OWASP category, focusing on vulnerabilities on known components.

The A-9 - Using Components with Known Vulnerabilities category is located under the following path.

OWASP\A-9 - Using Components with Known Vulnerabilities

A10 - Insufficient Logging AND Monitoring

This is a sub-category of OWASP category, focusing on insufficient logging and monitoring.

The A-10 - Insufficient Logging AND Monitoring category is located under the following path.

OWASP\A-10 - Insufficient Logging AND Monitoring

The A-10 - Insufficient Logging AND Monitoring category reports are listed in the following table.

A-10 - Insufficient Logging AND Monitoring

| Report | Description | Drill Down | Parameters |
|--------------------------------------|---|------------|------------|
| All Failed Logins | This report provides an overview of failed logins in the organization. | none | none |
| All Logins by Host | This report provides all login information of an specific host, (host name should be provided while report is running). | none | none |
| Attacks And Suspicious Activity | This report lists the attacks and suspicious activity in the organization. | none | none |
| Failed Signature Updates | This report displays information about failed signature updates events in the organization. | none | none |
| Login Activity | This report shows all login activity in the organization. | none | none |
| Unable to Log Events to Security Log | This report details when windows is unable to log events to the security log. | none | none |

Cloud

This category covers the cloud content.

CSA

This is a sub-category of Cloud category. This category covers the cloud security alliance content.

Treacherous 12

This is a sub- category of CSA. This category covers cloud security alliance > treacherous 12 top threats. Each of the sub-categories addresses one of the treacherous 12 threats.

The following categories are located under the treacherous 12 category:

Abuse and Nefarious Use of Cloud Services

This is a sub-category of the Treacherous 12 category, focusing on abuse and nefarious use of Cloud services.

The Abuse and Nefarious Use of Cloud Services category is located under the following path.

Treacherous 12\Abuse and Nefarious Use of Cloud Services

Abuse and Nefarious Use of Cloud Services

| Report | Description | Drill Down | Parameters |
|---|---|------------|------------|
| DoS Originated from EC2 Instances | This report identifies DoS Activity originated from EC2 Instances. | none | none |
| EC2 Instances Communicating with Cryptocurrency Entity | This report displays EC2 instances communicating with cryptocurrency IP addresses or domains. | none | none |
| EC2 Machines Involved on Suspicious Communication | This report lists EC2 Machines involved in suspicious communication. | none | none |
| EC2 Instances Querying Domains Involved in Phishing Attacks | This report presents EC2 instances in which querying domains are involved in phishing attacks. | none | none |
| Email Spam Originated from EC2 Instances | This report identifies email spam originated from EC2 Instances. | none | none |
| Nefarious Activity by an Unauthorized Individual from EC2 | This report displays events reported by Amazon GuardDuty related to nefarious activity by an unauthorized individual from EC2 machines. | none | none |
| Trojans or Backdoors installed on EC2 Instances | This report lists backdoors or trojans installed in EC2 machines. | none | none |
| Suspicious Activity Reported by Microsoft Azure | This report lists suspicious activity reported by Microsoft Azure. | none | none |

Account Hijacking

This is a sub-category of the Treacherous 12 category, focusing on Account Hijacking.

The Account Hijacking category is located under the following path.

Treacherous 12\Account Hijacking

The Account Hijacking category reports are listed in the following table.

Account Hijacking

| Report | Description | Drill Down | Parameters |
|--|--|------------|------------|
| Principal Invoked an API Commonly Used to Discover Information Associated with AWS account | This report lists principals invoked by an API commonly used to discover information associated with AWS accounts. | none | none |
| Phishing Attacks | This report shows phishing attacks in the organization. | none | none |

Advanced Persistent Threats

This is a sub-category of the Treacherous 12 category, focusing on advanced persistent threats.

The Advanced Persistent Threats category is located under the following path.

Treacherous 12\Advanced Persistent Threats

Data Breaches

This is a sub-category of the Treacherous 12 category, focusing on data breaches.

The Data Breaches category is located under the following path.

Treacherous 12\Data Breaches

Data Loss

This is a sub-category of the Treacherous 12 category, focusing on data loss.

The Data Loss category is located under the following path.

Treacherous 12\Data Loss

The Data Loss category reports are listed in the following table.

Data Loss

| Report | Description | Drill Down | Parameters |
|----------------------------------|--|------------|------------|
| Amazon S3 Bucket Deletion Events | This report shows Amazon S3 Buckets deletion events. | none | none |
| Amazon AWS Deletion Events | This report lists Amazon AWS deletion events reported in the organization. | none | none |
| Amazon VPC Deletion Events | This report presents Amazon VPC deletion events. | none | none |

Denial of Service

This is a sub-category of the Treacherous 12 category, focusing on denial of service (DoS).

The Data Breaches category is located under the following path.

Treacherous 12\Denial of Service

The Denial of Service category reports are listed in the following table.

Denial of Service

| Report | Description | Drill Down | Parameters |
|--------------|--|------------|------------|
| DoS Activity | This report summarizes DoS activity in the organization. | none | none |

Insecure Interfaces and APIs

This is a sub-category of the Treacherous 12 category, focusing on insecure interfaces and APIs.

The Insecure Interfaces and APIs category is located under the following path.

Treacherous 12\Insecure Interfaces and APIs

The Insecure Interfaces and APIs reports are listed in the following table.

Insecure Interfaces and APIs

| Report | Description | Drill Down | Parameters |
|------------------------------|--|------------|------------|
| Insecure Interfaces and APIs | This report displays the vulnerabilities found in various interfaces and APIs. | none | none |

Insufficient Due Diligence

This is a sub-category of the Treacherous 12 category, focusing on insufficient due diligence.

The Insufficient Due Diligence category is located under the following path.

Treacherous 12\Insufficient Due Diligence

The Insufficient Due Diligence reports are listed in the following table.

Insufficient Due Diligence

| Report | Description | Drill Down | Parameters |
|--|---|-------------------|-------------------|
| EC2 Machines Behavior Deviates from the Established Baseline | This report details how EC2 machines behavior deviates from the established baseline. | none | none |
| Failed Technical Compliance Events | This report lists the failed technical compliance events. | none | none |

Insufficient Identity Credential and Access Management

This is a sub-category of the Treacherous 12 category, focusing on insufficient identity credential and access management.

The Insufficient Identity Credential and Access Management category is located under the following path.

Treacherous 12\Insufficient Identity Credential and Access Management

The Insufficient Identity Credential and Access Management category reports are listed in the following table.

Insufficient Identity Credential and Access Management

| Report | Description | Drill Down | Parameters |
|--|---|-------------------|-------------------|
| AWS Account Password Policy Was Weakened | This report presents AWS account password policy weakened events. | none | none |
| Invalid or Expired Certificate | This report lists invalid or expired certificate events. | none | none |
| Unsecured Password Events | This report displays unsecured password events. | none | none |

Malicious Insiders

This is a sub-category of the Treacherous 12 category, focusing on malicious insiders.

The Malicious Insiders category is located under the following path.

Treacherous 12\Malicious Insiders

System Vulnerabilities

This is a sub-category of the Treacherous 12 category, focusing on system vulnerabilities.

The System Vulnerabilities category is located under the following path.

Treacherous 12\System Vulnerabilities

Vulnerabilities in Shared Technologies

This is a sub-category of the Treacherous 12 category, focusing on vulnerabilities in shared technologies.

The Vulnerabilities in Shared Technologies is located under the following path.

Treacherous 12\Vulnerabilities in Shared Technologies

The Vulnerabilities on Shared Technologies reports are listed in the following table.

Vulnerabilities on Shared Technologies

| Report | Description | Drill Down | Parameters |
|--|---|------------|------------|
| Vulnerabilities in Shared Technologies | This report lists vulnerabilities in shared technologies. | none | none |

Parameters

Some reports invoke queries that prompt for field values during report runtime. The values entered for these fields are passed to the query using parameters. To change the value of the parameter that is passed to the query, you can enter a new value when prompted by the report during runtime or you can change the default value of the parameter. SQL wildcards are supported values for parameters; for example, the % wildcard character matches one or more characters. For more information about parameters, see ["Parameters" on page 273](#).

Logger reports invoke queries that use the following parameters:

- [IPAddress](#)647
- [categoryObjectParameter](#)647
- [commonlyBlockedPorts](#)647
- [destinationAddress](#)648
- [destinationPort](#)648
- [deviceGroupParameter](#)648
- [deviceProduct](#)648
- [deviceSeverityParameter](#)649
- [deviceVendor](#)649
- [dmBandwidthParameter](#)649
- [dmConfigurationParameter](#)649
- [dmLoginParameter](#)650
- [eventNameParameter](#)650

| | |
|---|-----|
| • resourceTypeParameter | 650 |
| • webPorts | 650 |
| • zoneParameter | 651 |
| • zones | 651 |
| • userName Parameter | 651 |
| • hostName Parameter | 652 |

IPAddress

When a report invokes a query that expects the **IPAddress** parameter as input, the IP Address prompt is displayed during report runtime with a default value of %.

This is a single value character type (CHAR) parameter that takes an IP address, such as **192.168.35.5**.

This parameter is used with the LIKE keyword in the WHERE clause of an SQL query. See the Foundation \\
Intrusion Monitoring \\
Attackers \\
Top Attacker Details query object for an example of a query using this parameter.

categoryObjectParameter

When a report invokes a query that expects the **categoryObjectParameter** parameter as input, the Resource Type prompt is displayed during report runtime with a default value of **'/Host/Application/Database', '/Host/Application/Database/Data', '/Host/Application/Service/Email', '/Host/Resource/File'**.

This is a multiple value character type (CHAR) parameter that allows the selection of one or more Category Object URIs, such as **Host/Application/Database**.

This parameter is used with the IN keyword in the WHERE clause of an SQL query. See the Foundation \\
Intrusion Monitoring \\
Resource Access \\
Access Events by Resource query object for an example of a query using this parameter.

commonlyBlockedPorts

When a report invokes a query that expects the **commonlyBlockedPorts** parameter as input, the Blocked Ports prompt is displayed during report runtime with all default values listed in the Combo Source panel.

This is a multiple value number type (NUMBER) parameter that allows the selection of one or more listed port numbers, such as **135, 139**.

This parameter is used with the IN keyword in the WHERE clause of an SQL query. See the Foundation \\
Intrusion Monitoring \\
Probes on Blocked Ports query object for an example of a query using this parameter.

destinationAddress

When a report invokes a query that expects the **destinationAddress** parameter as input, the Destination IP Address prompt is displayed during report runtime with a default value of %.

This is a single value character type (CHAR) parameter that takes an IP address, such as **192.168.35.5**.

This parameter is used with the LIKE keyword in the WHERE clause of an SQL query. See the Foundation \\ Intrusion Monitoring \\ Attackers \\ Source Counts by Destination query object for an example of a query using this parameter.

destinationPort

When a report invokes a query that expects the **destinationPort** parameter as input, the Destination Port prompt is displayed during report runtime with a default value of **80**.

This is a single value number type (NUMBER) parameter that allows the entry of one port number, such as **80**.

deviceGroupParameter

When a report invokes a query that expects the **deviceGroupParameter** parameter as input, the Category Device Group prompt is displayed during report runtime with a default value of **'/Firewall','/IDS','/IDS/Host','/IDS/Host/Antivirus','/IDS/Host/File Integrity','/IDS/Network','/IDS/Network/Traffic Analysis','/Network Equipment','/Network Equipment/Router','/Network Equipment/Switches','/VPN'**.

This is a multiple value character type (CHAR) parameter that allows the selection of one or more Category Object URIs, such as **Host/Application/Database**.

This parameter is used with the IN keyword in the WHERE clause of an SQL query. See the Foundation \\ Configuration Monitoring \\ Device Configuration Changes query object for an example of a query using this parameter.

deviceProduct

When a report invokes a query that expects the **deviceProduct** parameter as input, the Device Product prompt is displayed during report runtime with a default value of %.

This is a single value character type (CHAR) parameter that takes a string, such as **Snort**.

This parameter is used with the LIKE keyword in the WHERE clause of an SQL query. See the Foundation \\ Configuration Monitoring \\ Vulnerability Scanner Logs by Host query object for an example of a query using this parameter.

deviceSeverityParameter

When a report invokes a query that expects the **deviceSeverityParameter** parameter as input, the Device Severity prompt is displayed during report runtime with a default value of **%**.

This is a single value character type (CHAR) parameter that takes a string, such as **High**.

This parameter is used with the LIKE keyword in the WHERE clause of an SQL query. See the Foundation \\ Intrusion Monitoring \\ Attackers \\ Source Counts by Device Severity query object for an example of a query using this parameter.

deviceVendor

When a report invokes a query that expects the **deviceVendor** parameter as input, the Device Vendor prompt is displayed during report runtime with a default value of **%**.

This is a single value character type (CHAR) parameter that takes a string, such as **Snort**.

This parameter is used with the LIKE keyword in the WHERE clause of an SQL query. See the Foundation \\ Configuration Monitoring \\ Vulnerability Scanner Logs by Host query object for an example of a query using this parameter.

dmBandwidthParameter

When a report invokes a query that expects the **dmBandwidthParameter** parameter as input, the Device Type prompt is displayed during report runtime with a default value of **all**.

This is a single value character type (CHAR) parameter that allows the selection of predefined value, such as **Firewall**.

This parameter is used with the LIKE keyword in the WHERE clause of an SQL query. See the Foundation \\ Configuration Monitoring \\ Vulnerability Scanner Logs by Host query object for an example of a query using this parameter.

dmConfigurationParameter

When a report invokes a query that expects the **dmConfigurationParameter** parameter as input, the Device Type prompt is displayed during report runtime with a default value of **all**.

This is a single value character type (CHAR) parameter that allows the selection of predefined value, such as **Firewall**.

This parameter is used with the LIKE keyword in the WHERE clause of an SQL query.

dmLoginParameter

When a report invokes a query that expects the **dmLoginParameter** parameter as input, the Device Type prompt is displayed during report runtime with a default value of **all**.

This is a single value character type (CHAR) parameter that allows the selection of predefined value, such as **Firewall**.

This parameter is used with the LIKE keyword in the WHERE clause of an SQL query. See the Device Monitoring \\ CrossDevice \\ Failed Login Attempts query object for an example of a query using this parameter.

eventNameParameter

When a report invokes a query that expects the **eventNameParameter** parameter as input, the Event Name prompt is displayed during report runtime with a default value of **%**.

This is a single value character type (CHAR) parameter that takes a string, such as **Connector Raw Event Statistics**.

This parameter is used with the LIKE keyword in the WHERE clause of an SQL query. See the Foundation \\ Intrusion Monitoring \\ Targets \\ Destination Counts by Event Name query object for an example of a query using this parameter.

resourceTypeParameter

When a report invokes a query that expects the **resourceTypeParameter** parameter as input, the Resource Type prompt is displayed during report runtime with a default value of **/Host/Application/Database**.

This is a single value character type (CHAR) parameter that takes a string, such as **/Host/Application/Database**.

This parameter is used with the LIKE keyword in the WHERE clause of an SQL query.

webPorts

When a report invokes a query that expects the **webPorts** parameter as input, the Web Ports prompt is displayed during report runtime with all default values listed in the Combo Source panel.

This is a multiple value number type (NUMBER) parameter that allows the selection of one or more listed port numbers, such as **80,443**.

This parameter is used with the IN keyword in the WHERE clause of an SQL query. See the Foundation \\ Intrusion Monitoring \\ Top Web Traffic query object for an example of a query using this parameter.

zoneParameter

When a report invokes a query that expects the **zoneParameter** parameter as input, the Zone prompt is displayed during report runtime with a default value of %.

This is a single value character type (CHAR) parameter that takes an IP address, such as **/All Zones/ArcSight System/Private Address Space Zones/RFC1918: 10.0.0.0-10.255.255.255**.

This parameter is used with the LIKE keyword in the WHERE clause of an SQL query. See the Foundation \\ Intrusion Monitoring \\ Attackers \\ Top Attacker Details query object for an example of a query using this parameter.

zones

When a report invokes a query that expects the **zones** parameter as input, the Zone prompt is displayed during report runtime with a default value of %.

This is a multiple value character type (CHAR) parameter that allows the selection of one or more Category Object URIs, such as **/All Zones/ArcSight System/Private Address Space Zones/RFC1918: 10.0.0.0-10.255.255.255,/All Zones/ArcSight System/Private Address Space Zones/RFC1918: 192.168.0.0-192.168.255.255**.

This parameter is used with the IN keyword in the WHERE clause of an SQL query. See the Foundation \\ Intrusion Monitoring \\ Attackers \\ Source Counts by Destination query object for an example of a query using this parameter.

userName Parameter

When a report invokes a query that expects the **userNameParameter** parameter as input, the **userNameParameter** prompt is displayed during report runtime and the user name should be provided in order to run the report.

This parameter is used with the = keyword in the WHERE clause of an SQL query. See the Foundation \\ MITRE Monitoring \\ MITRE Attacks Events - Drill Down by Destination User and Foundation \\ MITRE Monitoring \\ MITRE Attacks Events - Drill Down by Source User query objects for an example of a queries using this parameter.

hostName Parameter

When a report invokes a query that expects the `hostNameParmeter` parameter as input, the `hostNameParamter` prompt is displayed during report runtime and the host name should be provided in order to run the report.

This parameter is used with the `=` keyword in the WHERE clause of an SQL query. See the Device Monitoring \ Anti-Virus \ Virus Activity by Host Name query object for an example of a query using this parameter.

System Filters

Logger provides the system filters listed in the following table.

Filters

| Filter | Type | Description |
|---|--------------------|---|
| Configuration - Configuration Changes (Unified) | Unified Query | This filter looks for events categorized as configuration changes events. |
| Configuration - System Configuration Changes (CEF format) | Regular Expression | This filter looks for events categorized as configuration changes events. It is a Regular Expression filter and can be used to create alerts. |
| Events - CEF | Regular Expression | This filter looks for all CEF formatted events. It is a Regular Expression filter and can be used to create alerts. |
| Events - Event Counts by Destination | Unified Query | This filter looks for all CEF events that have a destination address and shows a chart. |
| Events - Event Counts by Source | Unified Query | This filter looks for all CEF events that have a source address and shows a chart. |
| Events - High and Very High Severity CEF Events | Regular Expression | This filter looks for CEF events with a high or very high severity. It is a Regular Expression filter and can be used to create alerts. |
| Events - High and Very High Severity Events (Unified) | Unified Query | This filter looks for CEF events with a high or very high severity. |
| Firewall - Deny | Unified Query | This filter looks for events with deny or shun. |
| Firewall - Drop | Unified Query | This filter looks for drop events that are not database related. |
| Firewall - Permit | Unified Query | This filter looks for events that have the word permit. |

Filters, continued

| Filter | Type | Description |
|--|--------------------|---|
| Intrusion - Malicious Code (CEF format) | Regular Expression | This filter looks for CEF events categorized to indicate malicious code. It is a Regular Expression filter and can be used to create alerts. |
| Intrusion - Malicious Code (Unified) | Unified Query | This filter looks for CEF events categorized to indicate malicious code. |
| Logins - All Logins (CEF format) | Regular Expression | This filter looks for CEF events categorized as authentication events. It is a Regular Expression filter and can be used to create alerts. |
| Logins - All Logins (Non-CEF format) | Regular Expression | This filter looks for non-CEF format events with words indicating it is an authentication event. It is a Regular Expression filter and can be used to create alerts. |
| Logins - All Logins (Unified) | Unified Query | This filter looks for CEF events categorized as authentication events. |
| Logins - Failed Logins | Unified Query | This filter looks for failure events related to logins, user authentication and user authorization. |
| Logins - Successful Logins (Non-CEF format) | Regular Expression | This filter looks for events with keywords indicating a successful login attempt. It is a Regular Expression filter and can be used to create alerts. |
| Logins - Successful Logins (CEF format) | Regular Expression | This filter looks for CEF events categorized as successful login events. It is a Regular Expression filter and can be used to create alerts. |
| Logins - Successful Logins (Unified) | Unified Query | This filter looks for CEF events categorized as successful login events. |
| Logins - Unsuccessful Logins (Non-CEF format) | Regular Expression | This filter looks for failure events related to logins, user authentication and user authorization. It is a Regular Expression filter and can be used to create alerts. |
| Logins - Unsuccessful Logins (CEF format) | Regular Expression | This filter looks for failure events related to logins, user authentication and user authorization. It is a Regular Expression filter and can be used to create alerts. |
| Logins - Unsuccessful Logins (Unified) | Unified Query | This filter looks for failure events categorized as login events. |
| Network - DHCP Lease Events | Unified Query | This filter looks for DHCP lease related events. |
| Network - Port Links Up and Down | Unified Query | This filter looks for port or link status messages. |
| Network - Protocol Links Up and Down | Unified Query | This filter looks for protocol status messages. |
| SystemAlert - CPU Utilization Above 90% (CEF format) | Regular Expression | This filter looks for internal events indicating that CPU utilization is above 90%. It is a Regular Expression filter and can be used to create alerts. |
| SystemAlert - CPU Utilization Above 90% (Unified) | Unified Query | This filter looks for internal events indicating that CPU utilization is above 90%. |
| SystemAlert - CPU Utilization Above 95% (CEF format) | Regular Expression | This filter looks for internal events indicating that CPU utilization is above 95%. It is a Regular Expression filter and can be used to create alerts. |

Filters, continued

| Filter | Type | Description |
|--|--------------------|--|
| SystemAlert - CPU Utilization Above 95% (Unified) | Unified Query | This filter looks for internal events indicating that CPU utilization is above 95%. |
| SystemAlert - Device Configuration Changes (CEF format) | Regular Expression | This filter looks for internal events indicating a Logger configuration change. It is a Regular Expression filter and can be used to create alerts. |
| SystemAlert - Device Configuration Changes (Unified) | Unified Query | This filter looks for internal events indicating a Logger configuration change. |
| SystemAlert - Filter Configuration Changes (CEF format) | Regular Expression | This filter looks for internal events indicating a Logger filter change. It is a Regular Expression filter and can be used to create alerts. |
| SystemAlert - Filter Configuration Changes (Unified) | Unified Query | This filter looks for internal events indicating a Logger filter change. |
| SystemAlert - High CPU Temperature (CEF format) | Regular Expression | This filter looks for internal events indicating potential CPU over-heating. It is a Regular Expression filter and can be used to create alerts. |
| SystemAlert - High CPU Temperature (Unified) | Unified Query | This filter looks for internal events indicating potential CPU over-heating. |
| SystemAlert - Bad Fan (CEF format) | Regular Expression | This filter looks for Logger appliance internal events related to fan failure. It is a Regular Expression filter and can be used to create alerts. |
| SystemAlert - Power Supply Failure (CEF format) | Regular Expression | This filter looks for internal events indicating that a power supply has failed. It is a Regular Expression filter and can be used to create alerts. |
| SystemAlert - Power Supply Failure (Unified) | Unified Query | This filter looks for internal events indicating that a power supply has failed. |
| SystemAlert - RAID Status Battery Failure (CEF format) | Regular Expression | This filter looks for internal events indicating that the RAID battery backup unit (BBU) has failed. It is a Regular Expression filter and can be used to create alerts. |
| SystemAlert - RAID Status Battery Failure (Unified) | Unified Query | This filter looks for internal events indicating that the RAID battery backup unit (BBU) has failed. |
| SystemAlert - Disk Failure (CEF format) | Regular Expression | This filter looks for Logger appliance internal events indicating a disk failure. It is a Regular Expression filter and can be used to create alerts. |
| SystemAlert - Disk Failure (Unified) | Unified Query | This filter looks for Logger appliance internal events indicating a disk failure. |
| SystemAlert - RAID Controller Issue (CEF format) | Regular Expression | This filter looks for internal events indicating that a RAID disk has failed. It is a Regular Expression filter and can be used to create alerts. |
| SystemAlert - RAID Controller Issue (Unified) | Unified Query | This filter looks for internal events indicating that a RAID disk has failed. |
| SystemAlert - Root Partition Free Space Below 5% (Unified) | Unified Query | This filter looks for internal events indicating that the root partition disk free space is below 5%. |

Filters, continued

| Filter | Type | Description |
|--|--------------------|---|
| SystemAlert - Root Partition Free Space Below 10% (Unified) | Unified Query | This filter looks for internal events indicating that the root partition disk free space is below 10%. |
| SystemAlert - Root Partition Free Space Below 10% (CEF format) | Regular Expression | This filter looks for internal events indicating that the root partition disk free space is below 10%. It is a Regular Expression filter and can be used to create alerts. |
| SystemAlert - Root Partition Free Space Below 5% (CEF format) | Regular Expression | This filter looks for internal events indicating that the root partition disk free space is below 5%. It is a Regular Expression filter and can be used to create alerts. |
| SystemAlert - Storage Configuration Changes (CEF format) | Regular Expression | This filter looks for Logger internal events related to changes of the storage configuration. It is a Regular Expression filter and can be used to create alerts. |
| SystemAlert - Storage Configuration Changes (Unified) | Unified Query | This filter looks for Logger internal events related to changes of the storage configuration. |
| SystemAlert - Storage Group Usage Above 90% (CEF format) | Regular Expression | This filter looks for Logger internal events indicating that the storage group usage is above 90%. It is a Regular Expression filter and can be used to create alerts. |
| SystemAlert - Storage Group Usage Above 90% (Unified) | Unified Query | This filter looks for Logger internal events indicating that the storage group usage is above 90%. |
| SystemAlert - Storage Group Usage Above 95% (CEF format) | Regular Expression | This filter looks for Logger internal events indicating that the storage group usage is above 95%. It is a Regular Expression filter and can be used to create alerts. |
| SystemAlert - Storage Group Usage Above 95% (Unified) | Unified Query | This filter looks for Logger internal events indicating that the storage group usage is above 95%. |
| SystemAlert - Zero Events Incoming (CEF format) | Regular Expression | This filter looks for Logger internal events indicating that the no events are being received by Logger. It is a Regular Expression filter and can be used to create alerts. |
| SystemAlert - Zero Events Incoming (Unified) | Unified Query | This filter looks for Logger internal events indicating that the no events are being received by Logger. |
| SystemAlert - Zero Events Outgoing (CEF format) | Regular Expression | This filter looks for Logger internal events indicating that the no events are being forwarded by Logger. It is a Regular Expression filter and can be used to create alerts. |
| SystemAlert - Zero Events Outgoing (Unified) | Unified Query | This filter looks for Logger internal events indicating that the no events are being forwarded by Logger. |
| SystemStatus - CPU Utilization by Connector Host | Unified Query | This filter looks for SmartConnector system health events and charts the CPU utilization by host. |
| SystemStatus - Disk Utilization by Connector Host | Unified Query | This filter looks for SmartConnector system health events and charts the disk utilization by host. |

Filters, continued

| Filter | Type | Description |
|---|---------------|--|
| SystemStatus - Memory Utilization by Connector Host | Unified Query | This filter looks for SmartConnector system health events and charts the memory utilization by host. |
| Unix - CRON related events | Unified Query | This filter looks for events with the cron keyword. |
| Unix - IO Errors and Warnings | Unified Query | This filter looks for I/O events with error or warning keywords. |
| Unix - PAM and Sudo Messages | Unified Query | This filter looks for events with the keywords PAM or sudo. |
| Unix - Password Changes | Unified Query | This filter looks for events related to password changes. |
| Unix - SAMBA Events | Unified Query | This filter looks for events related to SAMBA. |
| Unix - SSH Authentications | Unified Query | This filter looks for SSH authentication events. |
| Unix - User and Group Additions | Unified Query | This filter looks for events related to adding users or groups. |
| Unix - User and Group Deletions | Unified Query | This filter looks for events related to deleting users or groups. |
| Windows - Account Added to Global Group | Unified Query | This filter looks for non-CEF events related to adding a Windows account to a Global Group. |
| Windows - Account Added to Global Group (CEF) | Unified Query | This filter looks for CEF events related to adding a Windows account to a Global Group. |
| Windows - Audit Policy Change | Unified Query | This filter looks for non-CEF events related to Windows Audit Policy changes. |
| Windows - Audit Policy Change (CEF) | Unified Query | This filter looks for CEF events related to Windows Audit Policy changes. |
| Windows - Change Password Attempt | Unified Query | This filter looks for non-CEF events related to Windows password changes. |
| Windows - Change Password Attempt (CEF) | Unified Query | This filter looks for CEF events related to Windows password changes. |
| Windows - Global Group Created | Unified Query | This filter looks for non-CEF events related to the creation of Windows global groups |
| Windows - Global Group Created (CEF) | Unified Query | This filter looks for CEF events related to the creation of Windows global groups. |
| Windows - Logon Bad User Name or Password | Unified Query | This filter looks for non-CEF events related to Windows logon failures. |

Filters, continued

| Filter | Type | Description |
|--|---------------|--|
| Windows - Logon Bad User Name or Password (CEF) | Unified Query | This filter looks for CEF events related to Windows logon failures. |
| Windows - Logon Local User | Unified Query | This filter looks for non-CEF events related to Windows logons to the local system. |
| Windows - Logon Local User (CEF) | Unified Query | This filter looks for CEF events related to Windows logons to the local system. |
| Windows - Logon Remote User | Unified Query | This filter looks for non-CEF events related to Windows logons to a remote system. |
| Windows - Logon Remote User (CEF) | Unified Query | This filter looks for CEF events related to Windows logons to a remote system. |
| Windows - Logon Unexpected Failure | Unified Query | This filter looks for non-CEF events related to Windows logons with an unexpected failure. |
| Windows - Logon Unexpected Failure (CEF) | Unified Query | This filter looks for CEF events related to Windows logons with an unexpected failure. |
| Windows - New Process Creation | Unified Query | This filter looks for non-CEF events related to the creation of new Windows processes. |
| Windows - New Process Creation (CEF) | Unified Query | This filter looks for CEF events related to the creation of new Windows processes. |
| Windows - Pre-Authentication Failure | Unified Query | This filter looks for non-CEF events related to failures with Windows pre-authentication. |
| Windows - Pre-Authentication Failure (CEF) | Unified Query | This filter looks for CEF events related to failures with Windows pre-authentication. |
| Windows - Special Privileges Assigned to New Logon | Unified Query | This filter looks for non-CEF events related to logons for accounts with special privileges (power user or administrator-like accounts). |
| Windows - Special Privileges Assigned to New Logon (CEF) | Unified Query | This filter looks for CEF events related to logons for accounts with special privileges (power user or administrator-like accounts). |
| Windows - User Account Changed | Unified Query | This filter looks for non-CEF events related to user account changes. |
| Windows - User Account Changed (CEF) | Unified Query | This filter looks for CEF events related to user account changes. |
| Windows - User Account Password Set | Unified Query | This filter looks for non-CEF events related to user account password changes. |
| Windows - User Account Password Set (CEF) | Unified Query | This filter looks for CEF events related to user account password changes. |
| Windows - Windows Events (CEF) | Unified Query | This filter looks for all CEF events that are generated by Microsoft Windows. |

Appendix I: Restoring Factory Settings

The following topics describe how to restore your appliance to its original factory settings by over-writing the current files with an image of the original system.

Caution: Restoring an appliance to its original factory settings **irrevocably deletes all event data** and some configuration settings.

- [Before Restoring Your System](#) 658
- [Restoring Your System](#)658

Before Restoring Your System

Note the following cautions and guidelines before you restore to factory settings.

When restoring the configuration of the Logger from a backup, first ensure that the appliance is restored, then complete the upgrade to the desired version.

After restoring, you can restore backups of your data and configuration settings.

Logger With Multipath SAN Enabled

If your Logger is running version 5.1 or later and multipath SAN is enabled, AND you encounter one of these situations:

- You have returned a system to Micro Focus and received a new system that is either running Logger 5.0 Patch 3 or earlier;
- You restored the system to its factory default settings, which resets the Logger version to 5.0 Patch 3 or earlier

You must upgrade your system to Logger 5.1 or later **before** attaching the LUN, in order to restore your Logger to its last working state—running version 5.1 or later, with multipath enabled.

Restoring Your System


Instructions for performing a factory reset vary by the appliance model. Refer to the appropriate section for your appliance.

Restoring LX400 and Earlier Appliance Models

You can restore LX400 and earlier appliances to the original factory settings by using the built-in Acronis True Image software.

To restore LX400 and earlier appliance models:

1. Attach a keyboard, monitor, and mouse directly to the appliance or, if your appliance is configured for remote access through iLO, you can use that functionality to access the appliance console. (For information on how to set up the Logger Appliance for remote access, refer to the Logger Installation Guide.) You will see something like the following image.



2. Log into the appliance, type **reboot** at the command prompt, and then press Enter.
3. As the system reboots, messages scroll by. As soon as a message like the following appears on the screen, press any key on your keyboard.

Press any key to enter the menu

Booting Red Hat Enterprise Linux <version> in N seconds...

This message is displayed for a very short time. Make sure you press a key on your keyboard quickly; otherwise, the appliance will continue to boot normally. You need to press the key after the BIOS is done booting but before the OS boots.

If the OS boots, you will see something like the screen capture below. You'll need to try again in that case.



4. The session viewer opens. Use the mouse or arrow keys to select **System Restore** and press **Enter**.
5. In the **Acronis True Image Echo Server** dialog box, select **Recovery** from the **Pick a Task** list and then press Enter.
6. When the Restore Data Wizard starts, click **Next** to continue.
7. On the Welcome to the Restore Data Wizard page, click **Next** to continue.

8. On the **Backup Archive Selection** page, select **Acronis Secure Zone** and click **Next**. You will have a chance to review the choices you make on this page and the wizard pages that follow before initiating the restore process.
9. On the **Restoration Type Selection** page, select **Restore disks or partitions** and click **Next**. Only choose other options if specifically directed to do so by customer support.
10. On the **Partition or Disk to Restore** page, select the entire drive, labeled **cciss/c0d0** or **sda** (depending on the appliance model) and click **Next**.
11. On the **NT Signature selection for image restoration** page, select how you want the NT signature for the restored disk to be processed and click **Next**.
12. On the **Restored Hard disk Location** page, select the drive to restore (**cciss/c0d0** or **sda**) and click **Next**.
13. On the **Non-empty Destination Hard Disk Drive** page, select **Yes, I want to delete all partitions on the destination hard disk drive before restoring** and click **Next**.
14. On the **Next Selection** page, select **No, I do not** and click **Next** (there are no other partitions or disks to restore).
15. On the **Restoration Options** page, select **Validate backup archive for the data restoration process** if you want to validate the archive before resetting the appliance. Select **Reboot the computer automatically after the restoration is finished** if you want to reboot the appliance automatically. Click **Next**.
16. Review the checklist of operations to be performed and click **Proceed** to begin factory reset. Click **Back** to revisit previous pages.

Caution: Do not interrupt or power-down the Logger Appliance during the restore process. Interrupting the restore process may force the system into a state from which it cannot be recovered.

Progress bars show the status of the current operation and the total progress.

17. When you see a message indicating that the data was restored successfully, click **OK**.
If you specified automatic reboot, the appliance reboots when the restore is complete. Otherwise, reboot manually.

Restoring LX500 or LX600 Appliance Models

You can restore LX500 or LX600 model appliances to their original factory settings by using the built-in System Restore utility.

To restore an LX500 or LX600 appliance:

1. Attach a keyboard, monitor, and mouse directly to the appliance or, if your appliance is configured for remote access through iLO, you can use that functionality to access the appliance console. (For information on how to set up the Logger Appliance for remote access, refer to the Logger Installation

Guide.) You will see something like the following image.

2. Log into the appliance with your username and password.
3. At the command prompt, type **reboot**, and then press Enter.
4. As the system reboots, messages scroll by. As soon as a message like the following appears on the screen, press any key on your keyboard.

Press any key to enter the menu

Booting Red Hat Enterprise Linux <version> in N seconds...

This message is displayed for a very short time. Make sure you press a key on your keyboard quickly; otherwise, the appliance will continue to boot normally. You need to press the key after the BIOS is done booting but before the OS boots.

If the OS starts booting, you will see something like the screen capture below. You'll need to try again in that case.



5. The session viewer window opens.



Use the mouse or arrow keys to select **System Restore L<XXXX>** and press **Enter**.

6. System Restore automatically detects and displays the archive image. The image is named following the pattern **YYYY-MM-DD_LXX00_L<XXXX>.ari**, where **YYYY-MM-DD** is the date, **LXX00** is the appliance version and **L<XXXX>** is the appliance build number.
7. Press **F1** (auto-select) to automatically map the Source Image, displayed in the top panel, to the Target Disk, displayed in the bottom panel. The restore image name is displayed in the right-most column.
8. Optionally, press **F10** (VERIFY) to check the archive for damage before performing the restore. Once the archive has been verified, press Enter to continue.
9. Press **F2** (RESTORE) to begin the restore process. A dialog box asks whether you want to restore. Press **y** to proceed with the restore or **n** to cancel.
10. Progress bars show the status of the restoration.

Caution: Do not interrupt or power-down the appliance during the restore process. Interrupting the restore process may force the system into a state from which it cannot be recovered.

11. When the restore process is complete, press F12 to reboot the appliance. A dialog box asks whether you want to reboot. Press **y** to proceed with the reboot.

Caution After reboot, specify IP address and the gateway to adjust the network settings. For more information, see Configuring an IP Address for the Appliance in [Logger Installation Guide](#).

Appendix J: Logger Search From ArcSight ESM

If you have ArcSight Logger and ArcSight ESM deployed in your network infrastructure, you can perform Logger search operations from ArcSight Command Center or the ArcSight Console.

If you are running ESM 6.5c or later, you can use the search functionality provided by the ArcSight Command Center. For information on this feature, refer to the ArcSight Command Center User's Guide. For ESM 6.0c and earlier versions, you can perform a Logger search from your ArcSight Console.

The following topics discuss how use the integrated search functionality from the ArcSight Console.

- [Understanding the Integrated Search Functionality](#)663
- [Setup and Configuration](#)664
- [Supported Search Options](#) 665
- [Guidelines](#)665
- [Searching on Logger From ArcSight Console](#)666

Understanding the Integrated Search Functionality

Tip: If you are using ESM 6.5c and above, you can search from ArcSight Command Center in addition to the ArcSight Console described here. Refer to the ArcSight Command Center User's Guide for details.

There are several ways to perform a search operation on Logger from an ArcSight Console:

- Search: a regular search operation in which you can specify search options.
- Quick search: a search operation based on field and value you select in an ArcSight Console active channel; you are not prompted for any search options.

To run a Logger search, right click on an event in an active channel of the ArcSight Console to display a menu to select a search method—Logger Search or Logger Quick Search.

If you select Logger Search, you need to select search options such as Event Name, Destination, Source, and so on, and the Logger Appliances on which the search should be run (if there are multiple Logger Appliances). If you select Logger Quick Search, you are not prompted to specify any search options because the search is run on the field you had clicked on.

The search results are displayed in the ArcSight Console, as shown in the following figure:

Before you can run a search operation on Logger from ArcSight Console, you need to set up parameters in the ArcSight Console that are used to authenticate the user who performs the search. Authentication can be done via Basic Authentication (user name and password) or a One Time Password (OTP). This option makes the user authentication between Logger and ArcSight Console highly secure.

By default, a Logger search from the ArcSight Console uses the OTP method to authenticate. However, if Logger or ArcSight Console is not running a release that supports the OTP option, an error message is displayed and basic authentication is used.

Setup and Configuration

The following table lists the minimum and recommended versions that Logger and ArcSight Console must be running.

| Option | Requirement |
|-------------|---|
| Recommended | Logger 6.6x ESM 6.8 Tip: To verify the latest supported ESM release, refer to ArcSight Product Documentation on Micro Focus Security Community . |
| Minimum | Logger 5.1 ESM 5.0 SP1 Patch 2 |

On ESM

Follow these instructions to set up and configure ArcSight Manager to run integrated search operations:

1. Ensure that the ArcSight Manager is running one of the recommended versions.
2. Follow instructions in the ArcSight ESM User's Guide to set up ArcSight Console for integrated searches on Logger. When setting up a user for Logger access (as described in the "Set Up Users for Logger Access" section of the User's Guide), specify the following integration parameters.

| Parameter | Description |
|--------------------------------------|---|
| For a Logger Appliance Target | |
| LoggerUser | The user account for a Logger Appliance target. |
| LoggerPassword | The password for LoggerUser. |
| LoggerHost | The IP address of the Logger host. |
| LoggerPort | 443 |
| For a Software Logger Target | |
| OTPUser | The user account for one-time password (OTP) authentication. This account must exist on the Logger. |

| Parameter | Description |
|--------------|---|
| OTP Password | The password for OTPUser. |
| LoggerHost | The IP address of the Logger host. |
| LoggerPort | The Logger port number you assigned it during installation. |

The ArcSight ESM User's Guide is available in [Micro Focus Security Community](#).

On Logger

Make sure:

1. Your Logger is one of the recommended versions.
2. The Logger user name is the one you specified while creating an integration parameter (**in**) on the ArcSight Console.

Supported Search Options

You can select from the following search options when running a Logger search (not Quick Search) from the ArcSight Console:

- By Destination
- By Event Name
- By Source
- By Source and Destination
- By User
- By Vendor and Product

Additionally, if multiple Loggers are configured on your ArcSight Console, you can select the one on which the integrated search should be run.

Guidelines

Make sure you are aware of the following guidelines about Logger Search when it is run from ArcSight Console:

- A field-based search query is used to perform search on the Logger.
- Only searches from an active channel of an ArcSight Console is supported; searches from other ESM resources are not supported.

- Only one search option per search operation is supported. That is, you cannot select by both Event Name and By Destination for one search operation. For multiple search options, see ["Supported Search Options" on the previous page](#).
- You can run the search operation on only one Logger at a time. That is, you cannot select multiple Loggers from the menu list on ArcSight Console.
Additionally, even if a Logger peers with other Loggers, integrated search runs only on the local Logger that you select from the menu list on ArcSight Console.
- The one-time password (OTP) authentication is available for use only when Logger is running 5.1 or later and ArcSight Console is running 5.0 SP1 Patch 2 or later. Check the ESM Administrator's Guide of your version for password policies.
If OTP cannot be used, the searches run from the ArcSight Console display a message that a single-use session token could not be negotiated, thus regular authentication will be used. Click **OK**. LoggerUser and LoggerPassword is then used to authenticate.

Searching on Logger From ArcSight Console

You can perform two types of searches on Logger from ArcSight Console—Quick search, and regular search. Follow the steps for the type of search you want to run.

Running a Quick Search:

To run a Quick Search on Logger as described in ["Understanding the Integrated Search Functionality" on page 663](#):

1. Right click on the event field in an active channel of the ArcSight Console.
2. From the menu list, select **Integration Commands>Logger Quick Search**, as shown in the following figure.

Note: When running a Logger Quick Search using OTP authentication method, the embedded browser displays an error after Logger session becomes inactive for a period >15 minutes. Use an external browser to see results after the Logger session expires.

Running a Regular Search:

To run a regular **Search** (in which you specify search options):

1. Right click on any field of an event in an active channel of the ArcSight Console.
2. From the menu list, select **Integration Commands > Logger Search > Select Search Options**.
3. Click **OK** to run the search or **Cancel** to quit.

- a. If Logger or ArcSight Console is not running a release that supports the OTP option, an error message is displayed indicating that a single-use session token was not negotiated and basic authentication will be used instead.
- b. If that option is acceptable, click **OK** to proceed.

The search results are displayed in the ArcSight Console Web Viewer.

Send Documentation Feedback

If you have comments about this document, you can [contact the documentation team](#) by email. If an email client is configured on this computer, click the link above and an email window opens with the following information in the subject line:

Feedback on Administrator's Guide (Logger 7.0)

Just add your feedback to the email and click send.

If no email client is available, copy the information above to a new message in a web mail client, and send your feedback to arcsight_doc@microfocus.com.

We appreciate your feedback!