DevPartnerStudio Quick Reference

Print out all or portions of this document and keep it handy for quick reference (use a color printer when available).

DevPartner Features

Use the links in the left column in the following table to locate reference information about DevPartner features.

| To solve this problem | Use this DevPartner feature |
|---|---|
| Detect programming problems and naming inconsistencies | Code Review |
| Diagnose run-time errors in the source code | Error Detection |
| Locate performance bottlenecks in the application | Coverage, Memory, and Performance Analysis |
| Ensure code base stability throughout development and testing phases | Coverage Analysis Session Data |
| Determine memory allocation in an application and get feedback to reduce memory consumption | Memory Analysis |
| | |

More Information

Refer to the DevPartner online help or to the *Understanding DevPartner* manual for more information.

Common Elements

The DevPartner software provides these common elements, regardless of feature.

- DevPartner Toolbar
- DevPartner Menu
- DevPartner File Extensions
- Command Line Instrumentation Options

DevPartner Menu and Toolbar

Accessed from the DevPartner menu or toolbar in Visual Studio. **Note:** Menu items and icons vary slightly in Visual Studio 6.0.

| Choose this menu or toolbar item | То |
|---------------------------------------|---|
| Error detection | Perform run-time error detection using BoundsChecker technology |
| Coverage Analysis | Perform run-time code coverage analysis |
| Error detection and Coverage Analysis | Perform run-time error detection with cod coverage analysis |
| Performance Analysis | Execute run-time performance analysis |
| Memory Analysis | Execute run-time memory analysis |
| Performance Expert | Execute run-time analysis with Performanc Expert |
| Perform Code Review | Perform static code analysis |
| Manage Code Review Rules | Access code review rules management |
| Error Detection Rules | Access error detection rules management, used to filter or suppress detected errors |
| Native C/C++ Instrumentation | Perform compile-time instrumentation for: Error detection, Error detection with coverage, Performance or coverage analysi |
| Native C/C++ Instrumentation Manager | Access the Instrumentation Manager |
| Correlate | Correlate performance or coverage files |
| Merge Coverage Files | Merge coverage analysis sessions |
| Submit TrackRecord defect | Submit TrackRecord defect See Note |

Note: The Submit TrackRecord defect toolbar button is only available when TrackRecord is installed.

Options

Access DevPartner options Choices include: Analysis, Code review, Error detection

Common Elements

DevPartner File Extensions

File extensions for session files.

| Run this DevPartner feature | To create this session file (extension) |
|-----------------------------|---|
| Code review | .dpmdb |
| Code coverage | .dpcov |
| Code coverage merge files | .dpmrg |
| Error detection | .dpbcl |
| Memory analysis | .dpmem |
| Performance analysis | .dpprf |
| Performance Expert | .dppxp |

Command Line Instrumentation Options

NMCL Options

The following table lists the NMCL options that you can use to instrument your unmanaged (native) Visual C++ code from the command line. Use NMCL.EXE only to compile unmanaged Visual C++ code with DevPartner performance and coverage or error detection instrumentation. NMCL is not used with managed code, which DevPartner instruments as it is passed to the common language runtime during execution.

Note All NMCL options must begin with a forward slash (shown in the following list) or hyphen, followed by the letters NM. For example: /NMoption or –NMoption.

| Use | То |
|--|--|
| /NMbcpath:bc-path | Specify the directory location of bcinterf.lib if you do not have the directory that contains NMCL on your path. |
| /NMclpath:cl-path | Specify the directory location of cl.exe. You can use this option to bypass the installed location of DEVENV, or if DEVENV is not installed. |
| /NMhelp or /? | Display help text |
| /NMignore:source-file or /NMignore:source-file:method source-file | Specify a source file or a method in a source file that should not be instrumented |

| Use | То |
|--|---|
| /NMlog:log-file | Specify a log file for NMCL messages (default: stdout) |
| /NMnogm | Ignore the CL /Gm (minimal rebuild) option if it appears on the command line. You can use this option to avoid a known conflict between the NMAKE /A and CL /Gm options. |
| /NMonly:source-file | Specify a single source file that should be instrumented |
| /NMopt:option-file or /NM@option-file | Specify an option file (an ASCII file containing individual command-line options, each on a separate line. |
| /NMpass | Specify pass-through mode, which instructs NMCL to call CL without intervention. In this case, no instrumentation takes place. |
| /NMstoponerror | Stop NMCL if an error occurs during instrumentation. If this option is not specified, the default behavior is to fall back to a standard CL compile. |
| /NMbcOn | Use DevPartner Error Detection instrumentation. This is the default setting. |
| /NMtxOn | Specifies instrumentation for performance and coverage analysis. |
| /NMtxInlines | Instruments methods that are marked as inlineable if inline optimizations are enabled (using the /O1, /O2, /Ob1, or /Ob2 option) |
| /NMtxNoLines | Instruct DevPartner not to collect line information. When you use this option, DevPartner does not display any line data in the Source tab. You can also use this to improve the time required to instrument and run your application. |
| /NMtxpath:tx-path | Specify the directory location of the performance and coverage analysis library files if you do not have the directory that contains NMCL on your path. |

Note: When using NMCL, add the directory containing these utilities to your path. For example, if you installed the product into the default directory, add the following directory to your path:

C:\Program Files\Common Files\Compuware\NMShared

Common Elements

NMLINK Options

The following table lists the NMLINK options that you can use to link your unmanaged (native code) Visual C++ application to DevPartner.

Note: All NMLINK options must begin with a forward slash (shown in the following list) or hyphen, followed by the letters NM. For example: /NMoption or -NMoption.

| Use | То |
|-----------------------|--|
| /NMbcOn | Use DevPartner Error Detection instrumentation. This is the default setting. |
| /NMbcpath:bc-path | Specify the directory location of bcinterf.lib if you do not have the directory that contains NMCL on your path. |
| /NMhelp or /? | Display help text |
| /NMlinkpath:link-path | Specify the directory location of LINK.EXE. You can use this option to bypass the installed location of DEVENV, or if DEVENV is not installed. |

| Use | То |
|-------------------|---|
| /NMpass | Specify pass-through mode, which instructs NMLINK to call LINK without intervention. |
| /NMtxOn | Specifies instrumentation for coverage and performance analysis. |
| /NMtxpath:tx-path | Specify the directory location of the performance and coverage analysis library files if you do not have the directory that contains NMCL on your path. |

Note: When using NMCL and NMLINK, add the directory containing these utilities to your path. For example, if you installed the product into the default directory, add the following directory to your path:

C:\Program Files\Common Files\Compuware\NMShared

Code Review

Command Shortcuts for Rule Manager

Use the following keyboard shortcuts to enter Rule Manager commands:

| Command | Action |
|---------|----------------------------|
| Ctrl+A | Rule > Select All Rules |
| Ctrl+C | Rule > Copy Selected Rules |
| Ctrl+N | Rule > New Rule |
| Ctrl+O | File > Open Rule Set |
| Ctrl+P | File > Print |
| Ctrl+V | Rule > Paste Rules |
| F5 | View > Refresh |

Command-line Switches Used in CRBatch

CRBatch.exe /<switch>

| itch Func | tion |
|-----------------------------------|------------------------------------|
| nfiguration file/file name Inform | is CRBatch what configuration file |
| to use | when reviewing a solution or |
| project | t |
| This sv | vitch is mandatory. |
| r /verbose Instruc | ts CRBatch to report errors in a |
| messag | ge box, and to set the exit code |
| used b | y batch procedures |
| Althou | igh this switch is optional, it is |
| useful | if you want to physically debug |
| config | uration files. |
| 7.1" or /vs "8.0" Indicat | tes the Visual Studio environment |
| where | the batch review will be |
| execut | ted; choices include 7.1 or 8.0. |
| It is rec | commended that you use this |
| switch, | , most importantly if you have |
| more t | than one version of Visual Studio |
| on you | ar system. If you do not include |
| this sw | vitch, DevPartner will default to |
| the lat | est version. |
| on you | ur system. If you do not incl |
| this sw | vitch, DevPartner will defaul |
| the lat | est version. |

Command-line Switches Used in CRExport

CRExport.exe /<switch>

| Switch | Function |
|-------------------|---|
| /? | Help — Displays this list of the available command line interface arguments. |
| /f sessionfile | Fully-qualified session file path and name — Identifies the session database to use for this export. (Mandatory) |
| /e xml exportfile | Fully-qualified export file path and name — Identifies the XML file to receive the exported data. (Mandatory) |
| /a | Export all session data — Exports all data for the specified session, including the outbound methods for call graph data. Inbound methods are not exported. |
| /a i | Export all session data with inbound methods — Exports all data for the specified session, including inbound and outbound methods for call graph data. |
| /p | Export problems data — Exports the problems data for the specified session. |
| /m | Export metrics data — Exports the metrics data for the specified session. |
| /n | Export naming analysis data — Exports the naming analysis data for the specified session. |
| /s | Export code size data — Exports the code size data for the specified session. |
| /c | Export call graph data — Exports the outbound, or called, methods in the call graph data for the specified session. |
| /c i | Export call graph data with inbound methods — Exports the call graph data, including inbound and outbound methods, for the specified session. |

Code Review

Code Review Default Options (General Node)

| Category | Settings |
|------------------------------|---|
| Projects to be reviewed | All projects selected (C# and VB.NET projects only) |
| Rule set | All Rules |
| Naming analysis to use | Naming Guidelines (see below) |
| Collect metrics | On |
| Collect call graph data | On |
| Always generate a batch file | On |
| Always save review results | On |
| Prompt for session file name | Off |

| Description | Default |
|-----------------------------|--------------------------|
| Include naming analysis for | All identifiers selected |
| Company name | |
| Technology name | |

Code Review Toolbars



Naming Guidelines

| Description | Default |
|-------------------|-------------------------------------|
| What to analyze | All public or protected identifiers |
| Choose dictionary | American English |





Code Review

Code Review Summaries

| Summary of Problems * | | | | | | |
|-------------------------------|-------|-------|------|--------|-------|---------|
| Type Problems | | | | | erity | |
| Names | Total | Fixed | High | Medium | Low | Warning |
| COM Interop | 1 | 0 | 0 | 0 | 0 | 1 |
| Database | 0 | 0 | 0 | 0 | 0 | 0 |
| Date | 0 | 0 | 0 | 0 | 0 | 0 |
| Design Time Properties | 0 | 0 | 0 | 0 | 0 | 0 |
| Error/Exception Handling | 21 | 0 | 0 | 1 | 20 | 0 |
| Garbage Collection | 0 | 0 | 0 | 0 | 0 | 0 |
| Internationalization | 12 | 0 | 12 | 0 | 0 | 0 |
| Language | 0 | 0 | 0 | 0 | 0 | 0 |
| Logic | 2 | 0 | 0 | 0 | 0 | 2 |
| Maintainability | 13 | 0 | 0 | 2 | 3 | 8 |
| Performance | 1 | 0 | 1 | 0 | 0 | 0 |
| Portability | 0 | 0 | 0 | 0 | 0 | 0 |
| Project & Solution Properties | 0 | 0 | 0 | 0 | 0 | 0 |
| Reliability | 0 | 0 | 0 | 0 | 0 | 0 |
| Security | 3 | 0 | 3 | 0 | 0 | 0 |
| Standards | 0 | 0 | 0 | 0 | 0 | 0 |
| System | 0 | 0 | 0 | 0 | 0 | 0 |
| Usability | 0 | 0 | 0 | 0 | 0 | 0 |
| User-Defined Rule | 0 | 0 | 0 | 0 | 0 | 0 |
| Versioning | 0 | 0 | 0 | 0 | 0 | 0 |
| Windows API | 0 | 0 | 0 | 0 | 0 | 0 |
| Totals | 53 | 0 | 16 | 3 | 23 | 11 |

* Summaries include all rule violations. Your filter settings do not apply.

| Summary of Counts | | | | |
|-------------------------------------|---------|--|--|--|
| Summary Type | Count | | | |
| Review Time (in minutes) | 1.212 | | | |
| Total Lines (including blank lines) | 2,183 | | | |
| Code Only Lines | 1,162 | | | |
| Comment Only Lines | 270 | | | |
| Code with Comments | 0 | | | |
| Rule Comparisons Made | 468,267 | | | |
| Total Lines Checked | 2,183 | | | |

| | | | | | Review | Settings | | |
|---------|------------------------|------------------------------------|----------------|-----------|---|---|---|--|
| | | R | Review Setting | 5 | | | Setting Value | |
| | | Solution | | | | SpeedBump.Net2003 | | |
| | | Solution Path | | | | C:\p4_MHT-NMSource1666_MHT101515D01 \pPS\pP_Mainline\Analysis\Examples\SpeedBump.Net\SpeedBump.Net2003.sln | | |
| | | Session File | | | | C:\p4_MHT-NMSource1666_MHT101515D01 \pPS\DP_Mainline\4nalysis\Examples\SpeedBump.Net\SpeedBump.Net2003.DPMDB | | |
| | | Batch Command Execution File | | | | C:\p4_MHT-NMSource1666_M | HT101515D01 | |
| | | | | | Project Lis | st | - | |
| | | Project Name | Compile I | Errors | Reviewed | | Project Path | |
| | Driver2 | 003 | False | | True | C:\p4_MHT-NMSource166 \DPS\DP_Mainline\Analysi | 6_MHT101515D01 s\Examples\SpeedBump.Net\Driver\Driver2003.csproj | |
| | CSharp2003 False | | False | | True | C:\p4_MHT-NMSource166 \DPS\DP_Mainline\Analysi | 6_MHT101515D01 s\Examples\SpeedBump.Net\CSharp\CSharp2003.csproj | |
| | VB2003 False | | | True | C:\p4_MHT-NMSource1666_MHT101515D01 \DPS\DP_Mainline\Analysis\Examples\SpeedBump.Net\VB\VB2003.vbp | | | |
| | Metrics Analysis | | | | True | | | |
| | | Naming Analysis | | | | Naming Guidelines | | |
| | | Dictionary Name | | | | American English | | |
| | | Sun | nmary of C | all Grapi | h Data | | | |
| | | Summary Type | | | Count | | | |
| Total f | viethods | Graphed | | 24 | | | - | |
| Total I | Total Methods Uncalled | | 0 | 0 | | - | | |
| - | Technology Name | | | | | not supplied | | |
| | Call Graph Analysis | | | | | True | | |
| | Ignore compile errors | | | | | False | | |
| | | Exclude rules that require a build | | | | False | | |
| | | Always generate a batch file | | | | True | | |

Code Review Results Panes



Coverage, Memory, and Performance Analysis

Determine application test coverage, analyze an application's use of memory, and profile application performance.

General and Data Collection Properties

The following data collection properties apply to performance, coverage, and memory analysis.

| Property | Default setting |
|---|------------------------------------|
| Automatically Merge Session Files | Ask me if I would like to merge it |
| Collect information about .NET assemblies | True |
| Collect COM Information | True |
| Exclude Others | True |
| Instrument inline functions | True |
| Instrumentation Level | Line |
| Track System Objects | True |

DevPartner toolbar buttons for Coverage, Memory, and Performance







Memory Analysis

Memory Analysis

Session Control for memory analysis



In leak analysis, monitor Tracked instance count for objects that were not collected as expected

Clear temporary object allocations tracked to this point

| DevPartner Memory Analysis | | | | | | |
|----------------------------|------|---------------|--------------------------|------------|--|--|
| 🧴 Memory Leaks | | RAM Footprint | 🛃 Temporary Objects | | | |
| View RAM Footp | rint | 0 | 06645N01 - 1448 (Optimiz | edWFB.exe) | | |

| Dev | DevPartner Memory Analysis | | | | | | |
|-----|----------------------------|-------|---------|---------|---|-------------------|----------------------|
| | Memory Leaks | | RAM For | otprint | G | Temporary Objects | |
| -× | Ce View Tempo | orary | Objects | Û | п | C106645N01 - 144 | 8 (OptimizedWFB.exe) |

Memory Analysis

Memory Analysis Session Data



Performance Analysis

Performance Analysis Session Data

Results Summaries

DevPartner displays results for performance analysis in Visual Studio or in the Performance Analysis Viewer. Session files present data in tabbed format, including the following tabs:

- Method List
- Source Code
- Session Summary



Performance Expert

Results Summaries

DevPartner displays results for Performance Expert in session files. Session files present data in tabbed format, including the following tabs:

- Call Graph
- Call Tree
- Methods table
- Source code
- Call stacks

Performance Expert Session Controls





Performance Expert Session Data



Using DPAnalysis.exe

| Using DPAnal | ysis.exe | Category | Switches |
|--|---|----------------------|---|
| Use DPAnalysis exe | to run coverage analysis memory analysis performance analysis or | {c} Other Options | /O[utput] - Specify the session file output directory and/or filename |
| Performance Expert | sessions from the command line. DPAnalysis.exe accepts command line | | /W[orkingDir] - Specify working directory for the process or service |
| switches or an XML | configuration file. | | /H[ost] - Specify the target's host machine |
| | | | /NOWAIT - Do not wait for the process to exit, just wait for it to start |
| Command Line | Operations | | /N[ewconsole] - Run the process in its own command window |
| Use this syntax to re the command line: | un coverage, memory, performance, or Performance Expert sessions from | | /F[orce] - Forces profiling for coverage or performance of applications written without managed code or CTI. |
| DPAnalysis.exe | <pre>[a] {b} {c} {d} [e] target {target args}</pre> | {d} Analysis Options | /NO_MACH5 - Disables excluding time spent on other threads |
| DPAnalysis.exe requ | ires Analysis Type and Target Type switches. Other switches are optional. | | /NM_METHOD_GRANULARITY - Sets data collection granularity to method-level (line-level is default) |
| The following table | lists the switches used with DPAnalysis.exe: | | /EXCLUDE_SYSTEM_DLLS - Excludes data collection for system dlls (performance analysis only) |
| Category | Switches | | /NM_ALLOW_INLINING - Enable run-time instrumentation of inline methods |
| [a] Analysis Type | /Cov[erage] - Sets analysis type to DevPartner coverage analysis | | (coverage and performance analysis only) |
| | /Mem[ory] - Sets analysis type to DevPartner memory analysis | | /NO_OLEHOOKS- Disable collection of COM |
| | /Perf[ormance] - Sets analysis type to DevPartner performance analysis /Exp[ert] - Sets analysis type to DevPartner Performance Expert /E[nable] - Enables data collection for the specified process or service | | <pre>/NM_TRACK_SYSTEM_OBJECTS - Track system object allocation (memory analysis only)</pre> |
| {b} Data Collection | | [e] Target Type | Identifies target that follows as either a process or service. Pick only one. All statements that follow the target name/path are considered arguments to the target |
| | /D[isable] - Disables data collection for the specified process or service | | /P[ocess] - Specify a target process (followed by arguments to process) |
| | /R[epeat] - Profiling will occur any time you run the specified process until you use | | /S[ervice] - Specify a target service (followed by arguments to service) |
| | the <i>D</i> switch to disable profiling. | | /C[onfig] - Path to configuration file |

Using DPAnalysis.exe

Configuration File

Use this syntax to run coverage, memory, performance, or Performance Expert sessions through a configuration file:

DPAnalysis.exe /config c:\temp\config.xml

The following table briefly describes the XML elements. See the DevPartner online help or the *Understanding DevPartner* manual for more information.

| Element | Description |
|-----------------|---|
| AnalysisOptions | (Optional) For each Process or Service, zero or one. Defines runtime attributes for the specified target process or service. Attributes correspond to DevPartner properties accessible from the Properties Window in Visual Studio. <i>Attributes</i> : SESSION_DIR, SESSION_FILENAME, NM_METHOD_GRANULARITY, EXCLUDE_SYSTEM_DLLS, NM_ALLOW_INLINING, NO_OLEHOOKS, NM_TRACK_SYSTEM_OBJECTS, NO_MACH5 |
| Arguments | (Optional) For each Process or Service, zero or one. Defines runtime attributes for the specified target process or service. Attributes correspond to DevPartner Coverage, Memory and Performance Analysis properties accessible from the Properties Window in Visual Studio. <i>Attributes</i> : SESSION_DIR, SESSION_FILENAME, NM_METHOD_GRANULARITY, EXCLUDE_SYSTEM_DLLS, NM_ALLOW_INLINING, NO_OLEHOOKS, NM_TRACK_SYSTEM_OBJECTS, NO_MACH5 |
| ExcludeImages | (Ontional) For each Process or Service, zero or one. No default if omitted. Defines |

Excludelmages (Optional) For each Process or Service, zero or one. No default if omitted. Defines images (at least one, no maximum) which, if loaded by the target process or service, will not be profiled. No attributes.

| Element | Description |
|-----------------|---|
| Host | (Optional) For each Process or Service, zero or one. No default if omitted. Sets the host machine of the target process or service. No attributes. |
| Name | One required for each service. Provides the name of the service as registered with the service control manager. This is the same name you would use for the system's NET START command. No attributes. |
| Path | One required for each process. Specify a fully qualified or relative path to the executable. You can specify the executable name without the path if the executable exists in the current directory. No attributes. |
| Process | The configuration file must contain at least one Process or one Service element. Specifies a target executable. <i>Attributes</i> : CollectData, Spawn, NoWaitForCompletion, NewConsole |
| RuntimeAnalysis | Required; one only. Defines the type of analysis and maximum session time. |
| Service | The configuration file must contain at least one Process or one Service element. Specifies a target service. <i>Attributes</i> : CollectData, Start, RestartlfRunning, RestartAtEndOfRun |
| Targets | Required. One only. Begins a block of one or more Process or Service entries. Target processes and services are started in the order they are listed in the configuration file. <i>Attributes:</i> RunInParallel |

Error Detection

Error Detection

File Extensions Used by Error Detection

| Extension | File Type | Description |
|------------------|-----------------------------------|---|
| .dpbcl | Error Detection Session File | This is the Error Detection log for the user's program execution. |
| .dpbcc .dpbcd | Error Detection Settings File | This file contains the various settings for Error Detection. The .dpbcd extension refers to the default settings file created, while .dpbcc refers to a custom settings file that has been saved separately. |
| .dpsup | Error Detection Suppressions File | This file contains the various suppressions for the user's program. |
| .dpflt | Error Detection Filters File | This file contains the various filters for the user's program. |
| .dprul | Error Detection Rules File | This is a database of the user's suppressions and filters. |

Default Options (Visual Studio) or Settings (Visual C++)

| Category | | Settings | |
|-----------------|-----|--|---------------------|
| General | On | Log events | |
| | On | Display error and pause | COM Call Reporting |
| | Off | Prompt to save program results | |
| | Off | Show memory and resource viewer when application exits | |
| | On | Source file search path - based on the location of the .EXE (standalone), .DSW (Visual C++), or .SLN (Visual Studio). | |
| | - | Override symbol path - Default: empty | COM Object Tracking |
| | - | Working directory (standalone only) based on the location of the .EXE | |
| | - | Command line arguments (standalone only) - Default: empty | |
| Data Collection | On | Call parameter coding depth = 1 | |
| | On | Maximum call stack depth on allocation = 5 | |
| | On | Maximum call stack depth on error = 20 | |
| | On | NLB file directory is based on the location of the .EXE (standalone), .DSW (Visual C++), or .SLN (Visual Studio). | |
| | On | Generate NLB files dynamically | |

| Category | | Settings |
|---------------------|-----|---|
| API Call Reporting | Off | Enable API call reporting. All selections are unavailable until you select th item. |
| | - | Collect window messages - Default when active: Off |
| | - | Collect API method calls and returns Default when active: On |
| | - | View only modules needed by this application - Default when active: C |
| | - | All modules (tree view) Default when active: All selected |
| Call Validation | Off | Enable call validation. All selections unavailable until you select this item |
| | - | Enable memory block checking - Default when active: Off |
| | - | Fill output argument before call - Default when active: Off |
| | - | COM failure codes - Default when active: On |
| | - | Check for COM "Not Implemented" return code - Default when activ On |
| | - | API failure codes - Default when active: On |
| | - | Check invalid parameter errors: API, COM - Default when active: both |
| | - | Category: Handle and pointer arguments - Default when active: On |
| | - | Category: Flag, range and enumeration arguments - Default when active: On |
| | - | Check statically linked C run-time library APIs - Default when active: C |
| | | DLLs to check for API errors (failures or invalid arguments) - <i>Default when active: All items selected</i> |
| COM Call Reporting | Off | Enable COM method call reporting on objects that are implemented the selected modules |
| | - | Report COM method calls on objects implemented outside of the list modules - <i>Default when active: On</i> |
| | - | All components tree view - Default when active: All selected |
| COM Object Tracking | Off | Enable COM object tracking |
| | - | All COM classes tree view - Default when active: All selected |

Error Detection

| Category | ry Settings | | Error Dete | |
|---------------------|-------------|---|-------------|--|
| Deadlock Analysis | Off | Enable deadlock analysis | | |
| | - | Assume single process - Default when active: On | l r | |
| | - | Enable watcher thread - Default when active: Off | | |
| | - | Generate errors when: A critical section is re-entered - Default when active: Off | | |
| | - | Generate errors when: A wait is requested on an owned mutex - <i>Default</i> when active: Off | | |
| | - | Number of historical events per resource - Default when active: 10 | | |
| | - | Report synchronization API timeouts - Default when active: Off | 対 🗸 💰 | |
| | - | Report wait limits or actual waits exceeding (seconds) - Default when active: 60 | | |
| | - | Synchronization Naming Rules - Default when active: Don't warn about resource naming | Native C/C | |
| Memory Tracking | On | Enable memory tracking | Enable/disa | |
| | Off | Enable Leak Analysis Only | Choose ins | |
| | Off | Show leaked allocation blocks | | |
| | Off | Enforce strict reallocation semantics | | |
| | On | Enable FinalCheck | Error Doto | |
| | On | Enable guard bytes; Pattern = FC; Count = 4 bytes | Error Dete | |
| | - | Check heap blocks at runtime: On free | | |
| | On | Enable fill on allocation; Pattern = FB | | |
| | On | Check uninitialized memory; Size = 2 bytes | | |
| | On | Enable poison on free; Pattern = FD | | |
| .NET Analysis | Off | Enable .NET analysis | | |
| | - | Exception monitoring - Default when active: On | Log Eve | |
| | - | Finalizer monitoring - Default when active: On | Display I | |
| | - | COM interop monitoring - Default when active: On | Show filt | |
| | - | PInvoke interop monitoring - Default when active: On | Show Int | |
| | - | Interop reporting threshold - Default when active: 1 | | |
| .NET Call Reporting | Off | Enable .NET method call reporting | | |
| | - | All types (tree view node) - Default when active: Selected. | | |
| | - | .NET User Assemblies (tree view node) - Default when active: Selected | | |
| | - | .NET System Assemblies (tree view node) - Default when active: Not selected | | |
| Resource Tracking | On | Enable resource tracking | | |
| | On | Resources tree view. All listed resources are selected by default | | |

Error Detection Toolbar in Visual Studio



Error Detection Toolbar in Visual C++ 6.0



Error Detection Window

| Results Pane Summary, Memory Leaks, Other Performance, Modules, Transcri overview and detail about detect | ⁻ Leaks, Erro pt tabs provi ted errors. | ors, .NET ide | Details Pane Displays long description of detected error; call stack information; referenc count graph (see inset below). |
|--|--|--|---|
| Tupe | Quantitu | Location 🔺 | Pointer Error: Pointer 0x0012EE90, used as an |
| Movesble Memory Error | 2 | Locado | argument, is out of range; no longer within the buffer |
| Nonzero lock count | 1 | API Fre | for variable a 0x0012EE78 (20) in function |
| Nonzero lock count Dangling pointer | 1 | Pointer | Pointer_ArrayParamExHange. |
| Pointer Error | 1 | T OILKOI_ | Current Cell Check Thread 0 (9:0100) |
| Pointer argument range error | 1 | Pointer | Current Call Stack - Thread 0 (0x0106) |
| Pointer Unrelated | 1 | | Function File |
| K Unrelated pointer comparison | 1 | Pointer | Pointer_ArrayParamExRange PTRERR.CPP |
| H-X Read Overrun | 1 | | Executer unction BugBench/Dig.cpj |
| 🕂 🗶 Write Overrun | 1 | | AfxDispatchCmdMsg cmdtarg.cpp |
| | | <u> </u> | OnCmdMsg cmdtarg.cpp |
| E Summany A Memory Lenks A. Other I | aaka 😖 a | | OnCmdMsq digcore.cpp |
| E Duninary Themory Leaks | ears X Erro | rs | |
| { TRY { int a[5]; int b; b = a[5]; // array index out of range CATCH CATCH | | Reference Court | T View Dbject Identity View |
| Displays source code for the detected error, if available. | | Function CreateInstance COM_Interface ExecuteFunction OnFest _A xDispatchCr OnCmdMsg | File Line / Offset ol=32.dll 0x0001806F comin; h 570 Leak: comencipie bugbench/7dig.cpp 639 bugbench/7dig.cpp 639 cmidarg.cpp 38 cmidarg.cpp 38 |
| | Ī | Disp View Rest | ills Pane - Reference Count Graph lays Reference Count View and Object Identity v tabs when you select an Interface Leak in the ults pane. |

Icons Used in the Results Pane

| lcon | Description | Appears in |
|----------------|--------------------------|--|
| ۵ | Memory Leaks | Summary, Memory Leaks, and Transcript tabs |
| 4 ₆ | Other Leaks | Summary, Other Leaks, and Transcript tabs |
| × | Errors | Summary, Errors, and Transcript tabs |
| <u>a</u> | .NET Performance | Summary, .NET Performance tabs |
| * \$ | Module Load Event | Summary, Modules, and Transcript tabs |
| * | Subroutine call | Transcript tab |
| 面 | Garbage Collection Event | Transcript tab |
| Ŧ | Event Begins | Transcript tab |
| * | Event Resumes | Transcript tab |
| Ŧ | Event Ends | Transcript tab |

Icons Used in the Details Pane

| lcon | Description |
|--------------------|-----------------------------------|
| * | Subroutine call |
| (<mark>↓</mark>) | Entry Parameters |
| (†) | Exit Parameters |
| 0+ | Return Value |
| ai 🖓 | Property (default) for data types |
| @ | Property for data types |
| | |

Reference Count Graph Toolbar



Program Error Detected Dialog Box

| Error description | | | Tabs for multiple ca | all stacks |
|---------------------------------|---|---------------------------|--------------------------|------------|
| 💥 🖁 Program Error De | tected - BugBench7.ex | e | _ | |
| Memory Leak I CObject::opera | Leaving Scope: Variable re ator new. | ferences address 0x031; | A5130 (64) allocated by | < × |
| Current Call Stack - 1 | Thread 0 [0x0408] Call Sta | ack At Allocation - Threa | d 0 [0x0408] | |
| Function | | File | Line / C | Offset |
| DIIMain | | main.cpp | | 67 |
| _DIMainCRTStartup | | crtdll.c | 0.000 | 272 |
| | | ntdii.dii | UXUUUL | J/FC9 |
| // Fi // Fi | Regular DLL's resource chai esult. | n, and serious problems | will | • |
| new | CDvnLinkLibrarv(MainDLL): | | | |
| } else if (dwRe | ason == DLL_PROCESS_D | ETACH) | | |
| TBA | CEOCIMAIN BLIG Terminatir | nal\n"): | | - |
| Explain M | emory/Resource Viewer | | Copy Suppre | ess |
| Don't show this err | ror dialog This Run | • | | |
| D sable event logg | jing This Run | Debug | Halt Contin | nue |
| Call stack | information | Sour | ce code for the detected | d error |

Memory and Resource Viewer Dialog Box

| — Results Pane | | | | — M | lem | ory Con | tents I | Pane |
|--|------------------|-------------|--------------------------------------|--------------|--------|------------|--------------|--------------|
| Displays Memory, Resource, and S | Summary t | abs | | | i | - Stacl | k Pane |) |
| | | | | | | | | |
| 🗞 De Partner Error Detection Memory and Resource | Viewer | | | | | | | <u>_ ×</u> |
| A Location (combined) | Thread ID | Byte | 02F 02F | 56B78 | 10 | 000000 | | |
| CBugUtility::FillTree - [bugutility.cpp - line 159 (main.bug)] | 0x041c | 40 | 025 | SKB90 | 00 | 000002 | 46 | |
| CBu gUtility::FillTree - [bugutility.cpp - line 159 [main.bug]] | 0x041c | 40 | 025 | SEB84 | - ŏi | DOFA65 | eê | |
| CBubUtility::FillTree - [bugutility.cpp - line 159 (main.bug)] | 0x041c | 40 | 0.21 | 1000 | 10 | 017216 | 11 | |
| CBugUtility::FillTree - [bugutility.cpp - line 159 [main.bug]] | 0x041c | 40 | 025 | S6B8C | - Ê | ADEOOD | 12 | |
| CBugUtility::FillTree - [bugutility.cpp - line 97 (main.bug)] | 0x041c | 40 | 025 | 6890 | B3 | ADECOD | .0 a_0 | |
| CBugUtility::FillTree - [bugutility.cpp - line 97 (main.bug)] | 0x041c | 40 | 0.2 1 | 60090 | - D3 | ADECOD | .0 a_0 | |
| CBugUtility::FillTree - [bugutility.cpp - line 97 (main.bug)] | 0x041c | 40 | 025 | 22002 | D1 | ADFOOD | .0 | |
| CMapWordToOb: InitHashTable - Imap_wp.cpp - line 68 | 0x041c | 68 | 025 | 20D20 | D2 | ADFOOD | .0-4 | |
| III (MECZO DLLI) | | | 0210 | 00D9C | DS | ADFUUD | .0 | |
| CMapWordToOb::InitHashTable - [map_wp.cpp - line 68 [MFC70.DLL]] | 0x041c | 28 | | | | | | |
| CMapWordToOb::InitHashTable - [map_wp.cpp - line 68 (MEC70 DLL 1) | 0x041c | 28 | | | | | | |
| CMapWordToOb::InitHashTable - [map_wp.cpp - line 68 (MEC70 DLL1) | 0x041c | 28 | | | | | | _ |
| Million Charles (Million Charles Contracts Con | 0x041c | 200 | | | | | | |
| CNoTrackObject::operator new - [afxtls.cpp - line 80 | 0x041c | 4,240 | Fund | tion m | | l File | <u> </u> Lin | e / Ulfset |
| MFC70.DLL11 | | | | Utility::Fil | II ree | bugutili | ty | 159 |
| | | | Popu | late i ree | | main.cp | pp . | 253 |
| Memory A Resources E Summary | | | | Bench/L | лдан | nit bugber | icn | 353 |
| | | | LBUG | Bench/L | JIG::L | .o bugber | ich | 400 |
| c:\program files\compuware\devp | artner studio\e: | kamples\bug | bench7\mair | n\bugutili | ty.cp | p | | ^ |
| | | | | | | | | ~ |
| S2 | Buff | | | · | | | | |
| 51 | izeof (s: | zBuff) | |)); | | | | |
| stTVIS.item.pszText = szBu | iff ; | | | | | | | |
| // Allocate the structure | we put in | 1 lParam | | | | | | |
| pLPI = new LParamInfo ; | | | | | | | | |
| m IDeremirreuf m ni Peremti | 1 = nLP | r • | | | | | | |
| // This is a loof unde |) pur. | . , | | | | | | |
| // Inis is a leaf node. | | | | | | | | |
| pLPI->iType = 2 ; | | | | | | | | |
| pLPI->stEO = *pstEO ; | | | | | | | | |
| TTT Shine a Contractor | | 1717.7 | | | | | - 1 | |
| | | | | | | | | |
| Line Number: 159 Showing all items | • | lelp | Save | | Mark | and Close | Cla | ose // |
| Source Pane | | Mai | rk and C | lose | | | | |
| | | | | | | | | |

Displays source code for the detected error, if available.

Click to mark existing allocations and close the dialog box. Marked items will not be shown when Memory and Resource viewer reappears.

Error Detection

ActiveCheck and FinalCheck Error Detection

ActiveCheck

ActiveCheck[™] analyzes your program and searches for errors in your program executable as well as the dynamic-link libraries (DLLs), third-party modules, and COM components used by your program. The following tables list the types of errors found with ActiveCheck error detection.

| Deadlock-related Errors | API and COM Errors |
|---|---------------------------------------|
| Deadlock | COM interface method failure |
| Potential deadlock | Invalid argument |
| Thread deadlocked | Parameter range error |
| Critical section errors | Questionable use of thread |
| Semaphore errors | Windows function failed |
| Resource usage and naming errors | Windows function not implemented |
| Suspicious or questionable resource usage | Invalid COM interface method argument |
| Handle errors | |
| Event errors | |
| Mutex errors | |
| Windows event errors | |
| | |

| .NET Errors | Pointer and Leak Errors |
|---|-------------------------|
| Finalizer errors | Interface leak |
| GC.Suppress finalize not called | Memory leak |
| Dispose attributes errors | Resource leak |
| Unhandled native exception passed to managed code | |

Memory Errors

| Dynamic memory overrun |
|--|
| Freed handle is still locked |
| Handle is already unlocked |
| Memory allocation conflict |
| Pointer references unlocked memory block |
| Stack memory overrun |
| Static memory overrun |
| |

FinalCheck Compile Time Instrumentation - Deepest Error Detection

FinalCheck[™] compile time instrumentation (CTI) enables Error Detection to find more errors (memory leaks, pointer errors, data corruption errors, and so on) as they occur in real time. FinalCheck finds these types of errors, plus all errors found with ActiveCheck.

| Memory Errors | Pointer and Leak Errors |
|------------------------------|-------------------------------------|
| Reading overflows buffer | Array index out of range |
| Reading uninitialized memory | Assigning pointer out of range |
| Writing overflows buffer | Expression uses dangling pointer |
| | Expression uses unrelated pointers |
| | Function pointer is not a function |
| | Leak due to leak |
| | Leak due to module unload |
| | Leak due to unwind |
| | Memory leaked due to free |
| | Memory leaked due to reassignment |
| | Memory leaked leaving scope |
| | Returning pointer to local variable |

List of Available Keyboard Commands - Visual Studio

| Command | Action |
|-----------------|---------------------------------|
| Ctrl+Shift+O | File > Open > Project |
| Ctrl+Shift+N | File > New > Project |
| Ctrl+S | File > Save Project |
| Ctrl+Shift+S | File > Save All |
| Ctrl+Shift+F | Edit > Find in Files |
| Ctrl+Shift+H | Edit > Replace in Files |
| Alt+F12 | Edit > Find Symbol |
| Ctrl+Alt+L | View > Solution Explorer |
| Ctrl+Shift+C | View > Class View |
| Ctrl+Alt+S | View > Server Explorer |
| Ctrl+Shift+E | View > Resource View |
| F4 | View > Properties Window |
| Ctrl+Alt+X | View > Toolbox |
| Shift+Alt+Enter | View > Full Screen |
| Shift+F4 | View > Property Pages |
| Ctrl+Shift+B | Build > Build Solution |
| F5 | Debug > Start |
| Ctrl+F5 | Debug > Start Without Debugging |
| Ctrl+Alt+E | Debug > Exceptions |
| F11 | Debug > Step Into |
| F10 | Debug > Step Over |
| Ctrl+B | Debug > New Breakpoint |
| Ctrl+F1 | Help > Dynamic Help |
| Ctrl+Alt+F1 | Help > Contents |
| Ctrl+Alt+F2 | Help > Index |
| Ctrl+Alt+F3 | Help > Search |
| Shift+Alt+F2 | Help > Index results |
| Shift+Alt+F3 | Help > Search results |

List of Available Keyboard Commands - Visual C++ 6.0

| Command | Action |
|------------------|-------------------------------------|
| Ctrl+F | Edit > Find |
| Ctrl+H | Edit > Replace |
| Ctrl+G | Edit > Go To |
| Alt+F2 | Edit > Bookmarks |
| Alt+F9 | Edit > Breakpoints |
| Ctrl+Alt+T | Edit > List Members |
| Ctrl+Shift+space | Edit > Parameter Info |
| Ctrl+Space | Edit > Complete Word |
| Ctrl+W | View > ClassWizard |
| Alt+0 | View > Workspace |
| Alt+2 | View > Output |
| Alt+Enter | View > Properties |
| Ctrl+F7 | Build > Compile <i>filename</i> |
| F7 | Build > Build application_name |
| F5 | Build > Start Debug > Go |
| F11 | Build > Start Debug > Step Into |
| Ctrl+F10 | Build > Start Debug > Run to Cursor |
| Alt+F12 | Tools > Source Browser |
| Ctrl+Shift+R | Tools > Record Quick Macro |
| Ctrl+Shift+S | Tools > Play Quick Macro |

Export DevPartner Data: Command Line Use

Export DevPartner Data: Command Line Use

You can use DevPartner.Analysis.DataExport.exe from the command line to convert DevPartner coverage analysis (.dpcov), coverage analysis merge (.dpmrg), performance analysis (.dpprf), and Performance Expert (.dppxp) session file data to XML.

Use this syntax to export session data to XML:

DevPartner.Analysis.DataExport.exe [sessionfilename|pathtodirectory] {options}

Options

The following table lists the command line options for DevPartner.Analysis.DataExport.exe. You can use an equal sign, a colon, or a space to separate an option from the value or values you specify.

| Switch | Description |
|--|--|
| /out[put]= <string></string> | Specify the local or remote output directory for exported XML files. Creates the directory if the directory does not exist |
| /r[ecurse] | Search subdirectories for DevPartner Session Files. |
| <pre>/f[ilename]=<string></string></pre> | Specify the name of the XML output file. Appends .xml to the name specified. |
| /showAll | Shows all performance and coverage session file data available in a performance or coverage session file. For example, if you export a performance session file with this option, the resulting XML file contains both performance and coverage data fields. This option is not available for Performance Expert session files. |

| Switch | Description |
|----------------------------------|---|
| /w[ait] | Wait for input before closing console window. |
| /nologo | Do not display the logo or copyright notice. |
| /help or /? | Display help in the console window. |
| /summary | Export Performance Expert summary data which includes a default maximum of the top ten callpaths and the top ten methods that use the most CPU resources. Use the /maxpaths and /maxmethods options to override the maximums. |
| /method | Exports Performance Expert method data. |
| /calltree | Export Performance Expert call tree data. |
| /maxpaths= <integer></integer> | Used only with the Performance Expert /summary option. Exports the specified number of the top call paths that use the most CPU resources. |
| /maxmethods= <integer></integer> | Used only with the Performance Expert /summary option. Exports the specified number of the top methods that use the most CPU resources. |